

## **SQL Server Logon Options dialog box**

### **Database Name**

Type the name of the initial SQL Server 6 database to connect to or select the name from the drop-down box. If not supplied, the default database defined by SQL Server 6 is used.

### **Workstation ID**

Type the name of your workstation.

## Logon to SQL Server dialog box

### Server Name

Type the name of the server containing the SQL Server 6 database tables you want to access (case-sensitive) or select the name from Server Name box, which displays the server names you specified in the Setup dialog box.

### Login ID

If required, type your Login ID (case-sensitive).

### Password

If required, type your password for the system (case-sensitive).

---

```
{button ,AL(`H_CONNECTING_TO_SQL6_USING_A_CONNECTION_STRING_REF;H_CONNECTING_TO_SQL6_USING_A_LOGON_DIALOG_BOX_STEPS;H_SQL6_NUMBER_OF_CONNECTIONS_AND_STATEMENTS_SU  
PPORTED_REF;';0)} See related topics
```

## Connecting to SQL Server 6 using a connection string

If your application requires a connection string to connect to a data source, you must specify the data source name that tells the driver which ODBC.INI section of the registry to use for the default connection information. Optionally, you may specify *attribute=value* pairs in the connection string to override the default values stored in the ODBC.INI section of the registry.

You can specify either long or short names in the connection string. The connection string has the form:

```
DSN=data_source_name[:attribute=value[:attribute=value]...]
```

An example of a connection string for SQL Server 6 is

```
DSN=Accounting;DB=PAYROLL;UID=JOHN;PWD=XYZZY
```

The following table gives the long and short names for each attribute, as well as a description.

The defaults listed in the table are initial defaults that apply when no value is specified in either the connection string or the data source definition in the ODBC.INI section of the registry. If you specified a value for the attribute when configuring the data source, that value is your default.

<b>Attribute</b>	<b>Description</b>
DataSourceName (DSN)	A string that identifies a SQL Server 6 data source configuration in the ODBC.INI section of the registry. Examples include "Accounting" or "SQL Server 6-Serv1."
ServerName (SRVR)	The name of the server containing the SQL Server 6 tables you want to access.
Database (DB)	The name of the database to which you want to connect.
LogonID (UID)	The case-sensitive logon ID used to connect to your SQL Server 6 database. A logon ID is required only if security is enabled on your database. If so, contact your system administrator to get your logon ID.
Password (PWD)	A case-sensitive password.
Language (LANG)	The national language to be used by the client. The initial default is English.
ApplicationName (APP)	The name SQL Server 6 uses to identify your application.
WorkstationID (WKID)	The workstation ID used by the client.
CursorCacheSize (CCS)	The number of cursors the cursor cache can hold. The driver creates a cache of statements; each statement represents an open connection to SQL Server. The cursor cache increases performance but uses database resources. The initial default is 1.
YieldProc (YLD)	<p>YieldProc={0   1   3}. A numeric value that determines if you can work in other applications when SQL Server 6 is busy. This attribute is useful to users of ODBC applications. Valid values are:</p> <ul style="list-style-type: none"><li>• YieldProc=0 (peek and dispatch) causes the driver to check the Windows message queue and send any messages to the appropriate Windows application.</li><li>• YieldProc=1 (no yielding, the initial default) does not let you work in non-Windows applications.</li><li>• YieldProc=3 (dispatch via Windows Yield function) turns control over to the Windows kernel. The Windows kernel checks the message queue and sends any messages to the appropriate applications window.</li></ul> <p>This attribute is not available for editing in Windows NT or Windows 95. YieldProc is set to 1 as the default. This lets you work in other Windows applications when SQL Server 6 is busy. If YieldProc=0, 2, or 3 then you cannot work in other Windows applications when SQL Server 6 is busy.</p>
CharConv (CC)	A value that controls the character set conversion between

SQL Server 6 (version 4.8 or later) and a client application. Common values include iso-1 for ISO-8859-1, cp850 for Code Page 850, roman8 for the Roman8 character set, and SJIS for a Japanese character set. See your SQL Server documentation for a complete list of values.

Cancel (CAN)

Cancel={0 | 1 | 2}. A value that specifies how a previously executed statement should be canceled. Valid values are

- Cancel=0 fetches all remaining records if the statement was a Select.
- Cancel=1 cancels the statement by calling dbcancel. Set Cancel=1 if dbcancel is supported in your client/server configuration. This is the initial default.
- Cancel=2 closes the connection to the server for the statement. Set Cancel=2 only if dbcancel is not supported for your configuration and the performance of fetching all remaining records is unacceptable.

Gateway (GW)

Gateway={0 | 1}. A value that specifies whether you are using the Sybase Net-Gateway to access a DB2 database with this data source. Set Gateway=1 if this is the case. Otherwise, set Gateway=0 (the initial default).

TwoPhaseCommit (TPC)

TwoPhaseCommit={0 | 1}. This attribute lets you have two or more active statements within a transaction, using the SQL Server two-phase commit services. Set TwoPhaseCommit=1 to use two-phase commit. The active statements may deadlock if they reference the same SQL Server 6 table. Otherwise, set TwoPhaseCommit=0 (the initial default).

Netapi (NAPI)

Netapi={0 | 1}. A value that specifies whether NETAPI.DLL is available. Netapi=0, the initial default, indicates it is not available; Netapi=1 indicates it is available. If you supply a value for the WorkstationID attribute, this attribute is ignored.

ModifySQL (MS)

ModifySQL={0 | 1}. This attribute is provided for backward compatibility. It determines whether the driver modifies SQL statements to conform to ODBC specifications or passes the SQL statement directly to SQL Server 6. Specify ModifySQL=1 to have the driver modify the SQL statement to conform to ODBC specifications. Specify ModifySQL=0 to have the driver understand SQL dialects found in earlier drivers. The default is 1.

### **Connecting to SQL Server 6 using a Logon dialog box**

Some ODBC applications display a logon dialog box when you are connecting to a data source. In these cases, the data source name has already been specified.

In the Logon dialog box, do the following:

1. Type the name of the server containing the SQL Server 6 database tables you want to access (case-sensitive), or select the name from the Server Name drop-down box, which displays the server names you specified in the setup dialog box.
2. If required, type your case-sensitive login ID.
3. If required, type your case-sensitive password for the system.
4. (Optional) Click Options to display the SQL Server 6 Logon Options dialog box and specify the initial SQL Server 6 database to connect to and the name of your workstation.
5. Click OK to log on to the SQL Server 6 database installed on the server you specified and to update the values in ODBC.INI.

Copyright 1995 INTERSOLV Inc. All rights reserved. INTERSOLV is a registered trademark, and DataDirect is a trademark of INTERSOLV, Inc. Other company or product names mentioned herein may be trademarks or registered trademarks of their respective companies.

## **ODBC SQL Server 6 Advanced Driver Setup dialog box**

To configure optional settings for a SQL Server 6 data source, specify values as follows:

### **Server List**

A comma-separated list of servers that will appear in the logon dialog box.

### **Database List**

The databases that will be available in the SQL Server Logon Options dialog box. Separate the names with commas.

### **Default Logon ID**

The default logon ID used to connect to your SQL Server 6 database. This ID is case-sensitive. A logon ID is required only if security is enabled on your database. Your ODBC application may override this value or you may override this value in the logon dialog box or connection string.

### **Language**

The national language to be used by the client. The default is English.

### **Application Name**

The name SQL Server 6 uses to identify your application.

### **Workstation ID**

The workstation ID used by the client.

### **Cursor Cache Size**

The number of cursors the cursor cache can hold. The driver creates a cache of statements; each statement represents an open connection to SQL Server 6. The cursor cache increases performance but uses database resources. The default is 1 (one cursor).

### **Yield Proc**

A numeric value that determines whether you can work in other applications when SQL Server 6 is busy. This attribute is useful to users of ODBC applications. Valid values are:

- 0 (peek and dispatch), which causes the driver to check the Windows message queue and send any messages to the appropriate Windows application.
- 1 (no yielding, the default), which does not let you work in other applications.
- 3 (dispatch via Windows Yield function), which turns control over to the Windows kernel. The Windows kernel checks the message queue and sends any messages to the appropriate application window.

It is recommended that you use the value 1.

### **Character Conversion**

This value controls the character set conversion between SQL Server 6 (version 4.8 or later) and a client application. If you omit this value, no character conversion takes place on your server.

Common values include iso-1 for ISO-8859-1, cp850 for Code Page 850, roman8 for Roman8 character set, and SJIS for a Japanese character set. See your SQL Server documentation for a complete list of values.

### **Cancel Behavior**

A value that specifies how a previously executed statement should be canceled. Valid values are

- 0 fetches all of the remaining records if the statement was a Select.
- 1 cancels the statement by calling dbcancel. This is the default and should be used if dbcancel is supported in your client/server configuration.
- 2 closes the connection to the server for the statement. Use this value only if dbcancel is not supported for your configuration and the performance of fetching all remaining records is unacceptable.

### **Using Gateway**

Select this check box if you are using Sybase Net-Gateway to access a DB2 database with this data source.

**NETAPI.DLL Library Available**

The driver uses NETAPI.DLL to get the name of your workstation. Most major PC networks support this feature. If your network supports this capability, select this option. If you supply a workstation ID, this field is ignored.

**Two-Phase Commit**

This check box, when selected, enables you to have two active statements within a transaction, using the SQL Server 6 two-phase commit services. The active statements may deadlock if they reference the same SQL Server 6 table.

**Translate**

Displays the Select Translator dialog box to allow you to perform a translation of your data from one character set to another. Choose the OEM to ANSI translator to translate your data from the IBM PC character set to the ANSI character set.

**Close**

Returns to the ODBC SQL Server 6 Setup dialog box where you can click the OK button to write these settings to the ODBC.INI file.



## Configuring data sources

To configure a SQL Server 6 data source, do the following:

1. Start the ODBC Administrator by running ODBCAD32.EXE.  
A list of data sources appears.
2. If you are configuring a new data source, click Add.  
A list of installed drivers appears.
3. Select INTERSOLV OEM 2.12 32-BIT SQL Server 6 and click OK.
4. If you are configuring an existing data source, select the data source name and click Setup.  
The SQL Server ODBC Setup dialog box appears.
5. Specify a data source name, server name, and database name.
6. (Optional) Enter a description.
7. Click Advanced to configure optional data source settings, such as server list and database list.  
The ODBC SQL Server 6 Advanced Driver Setup dialog box appears.
8. Enter any optional data source settings, such as server list.
9. Click Translate to perform a translation of your data from one character set to another.  
The Select Translator dialog box appears, in which you select a translator. The OEM to ANSI translator translates data from the IBM PC character set to the ANSI character set. The translators listed in this dialog box are determined by the values listed in the ODBC Translators section of ODBCINST.INI.
10. Click OK to close the Select Translator dialog box and perform the translation.
11. Click OK to write these values to the ODBC.INI section of the registry.  
These values are now the defaults when you connect to the data source. You can change the defaults by configuring your data source again. You can override the defaults by connecting to the data source using a connection string with alternate values.

## Data types

The SQL Server 6 data types are mapped to the standard ODBC data types as follows:

<u>SQL Server</u>	<u>ODBC Data Type</u>
binary	SQL_BINARY
bit	SQL_BIT
char	SQL_CHAR
datetime	SQL_TIMESTAMP
float	SQL_FLOAT
image	SQL_LONGVARBINARY
int	SQL_INTEGER
money	SQL_DECIMAL
real	SQL_REAL
smalldatetime	SQL_TIMESTAMP
smallint	SQL_SMALLINT
smallmoney	SQL_DECIMAL
sysname	SQL_VARCHAR
text	SQL_LONGVARCHAR
timestamp	SQL_VARBINARY
tinyint	SQL_TINYINT
varbinary	SQL_VARBINARY
varchar	SQL_VARCHAR

**Isolation and lock levels**

SQL Server 6 supports isolation levels 1 (read committed) and 3 (serializable). SQL Server 6 supports page-level locking.

**Number of connections and statements supported**

The SQL Server 6 database system supports multiple connections. With two-phased commit, SQL Server 6 supports multiple statements per connection. Otherwise, SQL Server 6 supports a single statement per connection if SQL\_AUTOCOMMIT is 0 and multiple statements per connection if SQL\_AUTOCOMMIT is 1.

### **ODBC conformance levels**

The SQL Server 6 driver supports the Core, Level 1, and Level 2 API functions listed in Supported ODBC Functions. In addition, the following Level 2 functions are supported:

- SQLBrowseConnect
- SQLColumnPrivileges
- SQLForeignKeys
- SQLPrimaryKeys
- SQLProcedureColumns
- SQLProcedures
- SQLTablePrivileges

The driver supports the minimum SQL grammar.

## **System requirements**

To use the SQL Server 6 driver, you must have the appropriate Microsoft SQL Server DB-Library and Net-Library, version 6.0, installed.

**Note** The SQL Server 6 driver for Windows NT and Windows 95 requires Microsoft client software; it does not work with Sybase System 10 software.

Your database must support catalog stored procedures.

The DB-Library for Windows NT or Windows 95 is NTWDBLIB.DLL. The Net-Library you need depends on the network protocol used to connect to SQL Server 6. For example, Named Pipes requires DBNMPNTW.DLL. Contact your Microsoft SQL Server vendor to obtain the appropriate DB-Library and Net-Library.

If you attempt to configure a data source and you do not have NTWDBLIB.DLL on your path or in your Windows NT \SYSTEM32 or Windows 95 \SYSTEM directory, the following message appears:

"The setup routines for the INTERSOLV OEM 2.12 32-BIT SQL Server 6 ODBC driver could not be loaded. You may be low on memory and need to quit a few applications."

**About the SQL Server 6 Driver**

The SQL Server 6 driver supports the SQL Server 6 database system available from Microsoft, Inc.

The driver filename is LOSS609.DLL.

Copyright

## **ODBC SQL Server 6 Driver Setup dialog box**

Use the ODBC SQL Server 6 Driver Setup dialog box to create new SQL Server data sources or configure existing data sources.

### **Data Source Name**

A string that identifies this SQL Server 6 data source configuration in the ODBC.INI section of the registry. Examples include "Accounting" or "SQL Server6-Serv1."

### **Description**

An optional long description of a data source name. For example, "My Accounting Database" or "SQL Server 6 on Server number 1."

### **Server Name**

The name of the server that contains the desired database.

### **Database Name**

The name of the database to which you want to connect by default. If you do not specify a value, the default database defined by SQL Server 6 is used.

### **Advanced**

Displays the ODBC SQL Server Advanced Driver Setup dialog box to configure optional data source settings, such as server name.

### **OK**

Creates or modifies the current data source using the options you specify.

### **Cancel**

Exits the ODBC SQL Server 6 Driver Setup dialog without creating or modifying a data source.

---

{button ,AL(^H\_SQL6\_CONFIGURING\_DATA\_SOURCES\_STEPS;H\_SQL6\_ISOLATION\_AND\_LOCK\_LEVELS\_SUPPORTED\_REF;H\_SQL6\_NUMBER\_OF\_CONNECTIONS\_AND\_STATEMENTS\_SUPPORTED\_REF;H\_SQL6\_ODBC\_CONFORMANCE\_LEVELS\_REF;H\_SQL6\_SYSTEM\_REQUIREMENTS\_REF;';0)} See related topics



