

term

COLLABORATORS

	<i>TITLE :</i> term	
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>
WRITTEN BY		February 12, 2022

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	term	1
1.1	term.guide	1
1.2	term.guide/Introduction	2
1.3	term.guide/Gift-Ware_fee	3
1.4	term.guide/Reporting_bugs	4
1.5	term.guide/Background	5
1.6	term.guide/Acknowledgements	6
1.7	term.guide/Source_code	7
1.8	term.guide/Program_updates	7
1.9	term.guide/Documentation_and_online_help	8
1.10	term.guide/Foreign_language_support	9
1.11	term.guide/Workbench_and_Shell	9
1.12	term.guide/Keyboard_control	11
1.13	term.guide/Screen	11
1.14	term.guide/Menus	12
1.15	term.guide/Project	12
1.16	term.guide/Edit	13
1.17	term.guide/Commands	14
1.18	term.guide/Phone	14
1.19	term.guide/Transfer	15
1.20	term.guide/Buffer	16
1.21	term.guide/Terminal	16
1.22	term.guide/Settings	17
1.23	term.guide/Windows	18
1.24	term.guide/Dial	20
1.25	term.guide/Control_panels	20
1.26	term.guide/Serial_panel	20
1.27	term.guide/Modem_panel	22
1.28	term.guide/Screen_panel	25
1.29	term.guide/Terminal_panel	28

1.30	term.guide/Emulation_panel	31
1.31	term.guide/Clipboard_panel	33
1.32	term.guide/Capture_panel	34
1.33	term.guide/Command_panel	36
1.34	term.guide/Miscellaneous_panel	37
1.35	term.guide/Path_panel	39
1.36	term.guide/Transfer_panel	40
1.37	term.guide/Translation_panel	41
1.38	term.guide/Function_key_panel	43
1.39	term.guide/Cursor_key_panel	43
1.40	term.guide/Fast_macro_panel	44
1.41	term.guide/Hotkey_panel	45
1.42	term.guide/Speech_panel	46
1.43	term.guide/Sound_panel	47
1.44	term.guide/Transfer_progress_panel	48
1.45	term.guide/ASCII-transfer_panel	50
1.46	term.guide/Phonebook	52
1.47	term.guide/Rate_panel	55
1.48	term.guide/Copy_panel	56
1.49	term.guide/Dial_panel	57
1.50	term.guide/Printing_panel	59
1.51	term.guide/Text_buffer	59
1.52	term.guide/General_characteristics	59
1.53	term.guide/Operation	60
1.54	term.guide/Clipboard	60
1.55	term.guide/Command_sequences	62
1.56	term.guide/Backslash	62
1.57	term.guide/Caret	64
1.58	term.guide/Tilde	64
1.59	term.guide/Fast!_macros	64
1.60	term.guide/Packet_window	65
1.61	term.guide/Environment_variables	66
1.62	term.guide/Revision_history	66
1.63	term.guide/Index	75

Chapter 1

term

1.1 term.guide

'term' 3.4 - A terminal program for Amiga computers

Copyright © 1990-1993 Olaf Barthel & MXM

You may make and distribute verbatim copies of this documentation if the contents are unchanged or the author has agreed to any changes made.

No guarantee of any kind is given that the program described in this document are 100% reliable. You are using this material on your own risk.

The program 'term' and the data received/sent by it must not be used for the following purposes:

1. The construction, development, production or testing of weapons or weapon systems of any kind.
2. The construction, development, production or use of plants/installations which include the processing of radioactive/fissionable material.
3. The training of persons to deal with the abovesaid actions.

'term' may be included with commercial programs as long as no money is made by including it in the distribution.

You must not make any money by distributing 'term'. A small copy fee for data media (US\$ 5 maximum) or the inclusion of 'term' in Public-Domain collections such as Fred Fish's Amiga Library of Freely Distributable Software is permitted though.

Installer copyright and license notice:

Installer 1.24 and Installer project icon © Copyright 1991-93 Commodore-Amiga, Inc. All Rights Reserved. Reproduced and distributed under license from Commodore.

INSTALLER SOFTWARE IS PROVIDED "AS-IS" AND SUBJECT TO CHANGE; NO WARRANTIES ARE MADE. ALL USE IS AT YOUR OWN RISK. NO LIABILITY OR RESPONSIBILITY IS ASSUMED.

Introduction	Quick overview
Gift-Ware fee	How and what to donate
Reporting bugs	How to report program bugs?
Background	Why was 'term' created?
Acknowledgements	Who was involved in the creation of 'term'?
Source code	Notes on using the source code.
Program updates	How to obtain program updates?
Documentation and online help	Notes on the documentation and the online help features
Foreign language support	How to run 'term' in a language other than english?
Workbench and Shell	Parameters to pass to 'term' when to run it from Workbench and Shell.
Keyboard control	How to control 'term' by keyboard?
Screen	Which information is displayed on the 'term' main screen?
Menus	Information on the pull-down menus.
Control panels	All control panels explained.
Text buffer	Information on the text buffer.
Clipboard	How to use the keyboard and the mouse with the clipboard?
Command sequences	Command sequences explained.
Fast! macros	What are 'fast! macros' and how to use them?
Packet window	What is the 'packet window'?
Environment variables	Which environment variables are used by 'term'?
Revision history	List of changes & enhancements
Index	Contents index

1.2 term.guide/Introduction

Introduction

'term' is a telecommunications program designed for use with any Commodore-Amiga computer running Kickstart 2.04 or higher. Its features include

- Fast built-in VT-220 terminal emulation
- Support for custom terminal emulation modules following the 'XEM 2.0' standard
- Operates in any display environment, supports all screen display modes
- Support for file transfer modules following the 'XPR' standard
- File- and printer-capturing functions
- Review-buffer support

- Powerful phone book and dialing functions
- 'Amiga User Interface Style Guide' conformant user interface
- Online-help (as of Workbench 3.0)
- Built-in 'ARexx' interface

Although this program is freely-distributable, it is not entirely free. If you like and use it frequently, you are requested to send the author a donation which you suppose will do as a payment for the program. See the chapter Gift-Ware_fee for details.

1.3 term.guide/Gift-Ware_fee

Gift-Ware fee

The development of 'term' required considerable expense. The effort to find out by trial and error and with a little help from the DevCon-Disks and the Includes & Autodocs the operating principles of some routines would alone be worth a remuneration to the author - it's simply bad luck if the Atlanta-DevCon records arrive with considerable delay. The author is susceptible to all kinds of donation and gifts so long as it is assured that they are useful to him. Therefore anyone pleased by 'term' or who works with the source code is welcome to remunerate my programming efforts as he/she thinks that it matches my efforts - a lot of thanks! If you have got no ideas yet, here is a (by no means complete) list of suggestions:

- Infocom games and Infocom hintbooks. Although I already own almost all games published in 'The Lost Treasures of Infocom vol I+II' I still collect the originals (not those super-cheap Virgin Software re-releases). With the exception of 'A Mind forever voyaging', 'Arthur', 'Hollywood Hijinx', 'Leather Goddesses of Phobos', 'Nord and Bert couldn't make head or tail of it', 'Plundered Hearts', 'Shogun', 'Spellbreaker', 'The Lurking Horror', 'Trinity', 'Wishbringer', 'Zork Zero' (which I already own) I welcome any game in any format - it does not necessarily have to be an Amiga game, Apple II, Kaypro, Atari-XL, C64, etc. will be fine, too.
- The director's cut of Ridley Scott's film 'Bladerunner' on a PAL-VHS video cassette
- The films 'Jabberwocky', 'Brazil', 'The Fisher King' or 'Time Bandits' on a PAL-VHS video cassette
- A CD by Donald Fagen ('The Nightfly', 'Kamakiriad')
- A CD by the Beatles (except for 'Sgt. Pepper's Lonely Hearts Club Band' and 'Magical Mystery Tour'), Jackson Browne (except for 'Running on empty' and 'Lawyers in love'), Little Feat (-1989), Weather Report, Paul Simon (1971-1985), Eric Clapton (-1988), Al

- Di Meola (except for 'Land of the Midnight Sun' and 'Kiss my Axe')
- Raymond Elias Feist's books 'Magician: Apprentice' and 'Magician: Master'
 - A book by Michael Crichton, Bruce Chatwin, Raymond Chandler or Steven Meretzky
 - Old CinemaWare games - with the exception of 'Defender of the Crown', 'The King of Chicago', 'The Three Stooges', 'Sinbad', 'It came from the desert' 'TV-Sports Basketball' and 'TV-Sports Football'
 - An old game by Activision ('Borrowed Time', 'Hacker', 'Hacker II', 'Little computer people', 'Portal', 'Shanghai', 'Tass Times in Tonetown'), Electronic Arts ('Arcticfox', 'Marble Madness', 'One on one', 'Return to Atlantis', 'Seven cities of Gold', 'Skyfox', 'The Bard's Tale') or Epyx ('Temple of Apshai', 'Rogue', 'World Games', 'Winter Games', 'California Games')
 - Scenery disks for the SubLogic Flight-Simulator II - except for 'Japan', 'USA #7' and 'USA #9'
 - CD-ROMs and CD-ROM caddies
 - MPEG movie files and JPEG image files
 - Cash and checks (no credit cards - sorry) are always welcome.

My address:

Olaf Barthel
Brabeckstrasse 35
D-30559 Hannover

Federal Republic of Germany

Internet: olsen@sourcery.han.de

Would those people looking at the source code to extend it or do some modifications here and there please contact me before publication so that our efforts can be coordinated.

1.4 term.guide/Reporting_bugs

Reporting bugs

'term' is a rather complex program which is difficult to maintain - especially since there is only one person to take care of it: me. Although one tries to write correct, bug-free software, one cannot always achieve this goal. Tough - but that's life. It rains when you leave the umbrella at home. Toast falls buttered-side down. The phone rings while you are in the bath.

In case you come upon one of those nasty features which even the author was unable to track down and remove, follow these steps:

1. Keep calm. Shouting, cursing, crushing disks may help to cool your temper, but it will not help anybody (the least yourself!) if it results in a sudden cardiac infarction: you will have problems in reporting the problem.
2. Read the documentation! The bug you may want to report may be a deliberate feature.
3. Repeat previous step as often as possible. Yes, really, do so. Read the documentation. You will be glad you did.
4. Describe your problem elaborately. A comment like 'things fall down when dropped' may have inspired Sir Isaac Newton, but a similarly laconic comment 'downloads do not work' will most certainly fail to give any useful hints how to approach the problem. In case you encounter a problem with the built-in terminal emulation, try to make a verbatim file capture (i.e. turn off the Capture filter) of the session in which the offending codes were used and send it to me.
5. If you wish to report a bug in the ARexx interface include a sample ARexx script to produce the bug.
6. Do not forget to write it down! There is a difference between noticing a bug and reporting it (honestly!). Do not suppose that a bug will be fixed in a future program revision or rely on anybody else to report it: do it yourself. Send a letter to the author, preferably per electronic mailing services. The addresses are given at the end of this document.
7. State your system and program configuration. It helps a lot to know on which machine the program caused problems. Please include information such as memory expansion size, Amiga model (A500+, A600, A1200, A3000, A4000, etc.), graphics hardware (ECS, AGA, etc.), CPU type (MC68000, MC68020, MC68030, MC68040, etc.).

1.5 term.guide/Background

Background

This program is a product of anger and despair; I was unable to find a telecommunications program to suit my personal needs - neither in the commercial area, nor in the public-domain.

Most programs had a lot of extras but lacked other more important, perhaps more sensible features (just to take an example: in revision 2.20c and after four years of constant development Handshake still fails to use the current keymap settings and also strips the high order bit when receiving text - sorry Eric, that's why I never registered!).

I have hesitated for a long time before starting my first attempt at writing my very own telecommunications program. When Kickstart 2.x was about to become widely available I took the opportunity to create 'term' always trying to use the new OS routines wherever possible. While this started to be quite a difficult task it also was a lot of fun (imagine Columbus wrecking his fleet four times on his journey to the West Indies due to unexpected leakages in all vessels and sudden changes in the ships' sailing manuals - that's how I felt!).

As far as computer-telecommunications are concerned, Germany appears to be a developing country. This is partly due to the Deutsche Bundespost, the federal mail/phone company whose telecommunications monopoly used to be protected by federal law. Until 1989 you would risk a heavy penalty if using a non-registered modem or telephone instead of the Bundespost-supplied hardware. So, if you have any complaints or miss a few extremely important features in 'term', don't boo and hiss, I am not as long in the telecomm business as you are (I have yet seen only a single DEC VT-101 from afar!). Tell me what you need and I will try to add it in the next revision.

This project was started at December 24 1990 and completed by January 25 1991.

1.6 term.guide/Acknowledgements

Acknowledgements

My thanks go to the following people for their invaluable help and assistance: Andreas Kirchwitz, Christoph Teuber, Christopher Wichura, Garry Glendown, Germar Morgenthaler, Henning Hucke, Holger Lubitz, Juergen Otte, Marc-Christian Schroer, Marko Kuechmann, Markus Stoll, Martin Berndt, Martin Taillefer, Matthias Zepf, Michael Vaeth, Michael Wolfgang Hohmann, Oliver Wagner, Peter Fischer, Ralf Thanner, Ralph Schmidt, Roby Leemann & AUGS, Stefan Becker, Thorsten Seidel, Till 'Dill-Prince' Prinzler, Udo Wolt, Ueli Kaufmann, Veith Schoergenhammer, Volker Ulle & the Aquila Sysop Team and to all those who supplied libraries & control sequence tables.

Special thanks go to John Burton of Papua New Guinea who revised and rewrote certain parts of the program, in particular the terminal emulation routines, Leo Schwab who discovered means to use interleaved screen bitmaps in a system-integrated manner and to Nicola Salmoria whose invaluable assistance helped to reduce the incredible number of bugs lurking in the source code.

The xpr-libraries were created by Terence Finney (bplus), Kenneth Osterberg & Markus Pietz (jmodem), Marco Papa & Stephen Walton (kermit), Jack Rouse (quickb), Marc Boucher (xmodem), Ueli Kaufmann (ascii, ymodem & vms) and Rick Huebner & William M. Perkins (zmodem).

The xpr-standard was created by Willy Langeveld, the quicksort routine (QuickSort.asm) was written by David Jones.

The current implementation of the external terminal emulation library interface was developed by Ueli Kaufmann, who also wrote the external terminal emulation libraries supplied with 'term'. Without the invaluable help of Martin Berndt the library interface would probably not be working at all.

Since time did not permit me to translate the full original German documentation into English, I had asked the Z-Net Amiga community for help. As a result this document was translated by three different authors (in order of translation): me, Marc Schroer and Henning Hucke. Garry Glendown took care of the original termRexx documentation - thanks to all of you!

The beta tester group, consisting of Alfredo Rojas, Andreas Kirchwitz, Andrew Harrison, Bernd Ernesti, Chris Hanson, Chris Mattingly, Dabe Murphy, Dean S. Pemberton, Holger Lubitz, Joel E. Swan, Julian Matthew, Kai Iske, Kay Gehrke, Keith A. Stewart, Keith Christopher, Leon D. Shaner, Mark Constable, Martin Bernd, Matti Rintala, Peer Hasselmeyer, Piotr Kaminski, Robert L. Shady, Sebastian Delmont, Stefan Becker, Stefan Hudson and Yves Perrenoud, took care of testing the program - thank you very, very much!

1.7 term.guide/Source_code

Source code

Since there are still only very few well-documented examples (or general programming examples) for Kickstart 2.x and Kickstart 3.x I have decided to include the full 'C' source code with the 'term' distribution.

The source code is not intended for commercial use. If you are about to include portions in commercial programs you will need to ask me for permission. Still you may use parts of the source code for non-commercial software development without my consent.

I sincerely hope that the release of the full 'term' source code will give Kickstart 2.x a better start (I've overcome quite a lot of obstacles) so that more programs to use the new OS features will be available soon.

1.8 term.guide/Program_updates

Program updates

Whenever a new release of 'term' becomes available I will try to make it known in the telecommunications networks. To order a copy send a self addressed envelope, the equivalent to DM 7,- (cash or cheque) and two 3.5" double density disks/one 3.5" high density disk to the author.

The most current 'term' release will be available through ftp from ftp.informatik.uni-oldenburg.de (134.106.1.9), look into the /pub/amiga/term directory.

New program releases will be announced in the comp.sys.amiga.datacomm newsgroup.

Whereever possible, I will include PGP signature certificate files with the binaries to ensure their authenticity.

1.9 term.guide/Documentation_and_online_help

Documentation and online help

'term' comes bundled with a number of documentation files, these are:

term.doc

Human-readable english program documentation in standard ASCII format.

term.guide

English program documentation in AmigaGuide(tm) format suitable to submit to AmigaGuide or MultiView.

termRexx.doc

Human-readable english 'term' ARexx interface documentation in standard ASCII format. This file describes all the ARexx host commands 'term' supports and also gives a brief introduction how to use them.

termRexx.guide

English ARexx interface documentation in AmigaGuide(tm) format suitable to submit to AmigaGuide or MultiView.

xprascii.doc ... xprzmodem.doc

Human-readable documentation on the XPR transfer libraries supplied with 'term'.

In addition to the pure ASCII files documentation files are available in TeX-DVI format and Postscript. As space requirements do not permit to include them on the distribution disks they are only available directly from the author.

term.dvi

English program documentation in a format suitable for printing using a utility to print TeX-DVI-output files, such as supplied with the packages AmigaTeX(tm) or PasTeX.

term.ps

English program documentation in Postscript(tm) format. This file was generated from term.dvi using the dvips utility.

termRexx.dvi

English ARexx interface documentation in a format suitable to printing using a utility to print TeX-DVI-output files, such as supplied with the packages AmigaTeX(tm) or PasTeX.

termRexx.ps

English ARexx interface documentation in Postscript(tm) format. This file was generated from termRexx.dvi using the dvips utility.

In order to take advantage of the online-help feature, Kickstart 3.0 and the file term.guide are required. Copy the file to the drawer the 'term' main program is located in and configure the 'term' help text file settings (see Path_panel) to point to PROGDIR:term.guide. Once this has been done, pressing the Help key in any window to support online help will bring up context sensitive online help.

There is a copyrighted, freely distributable AmigaGuide release available which will run on Kickstart 2.04 installations. As of this writing it does not work properly with 'term', this is why 'term' requires the AmigaGuide release included with Workbench 3.0.

1.10 term.guide/Foreign_language_support

Foreign language support

'term' supports foreign language text catalog tables as introduced with Workbench 2.1 locale.library. As of this writing there is only a german translation of the program text available. If you wish to create your own national translation table you should consult the program source code file term-blank.ct which is a blank translation table. Before actually starting to fill in the translation table you should contact me first; there may already be someone preparing a translation. However, you should keep in mind that once you have created a foreign language translation of the program text I may ask you to update your translation for a future program release.

Once you are done with the translation table, send it to me on disk or via eMail, don't compile the catalog on your own!.

1.11 term.guide/Workbench_and_Shell

Workbench and Shell

The program can be started both from Workbench and from Shell. Kickstart 2.04 (revision 37.175) and Workbench 2.04 (revision 37.67) are required to run 'term'.

The 'behaviour' of 'term' can be changed by adding tool type entries to the corresponding Workbench icon or by specifying additional command line parameters when running the program from the Shell. Supported keywords are:

WINDOW

The console window specifier to be used when opening terminal output windows (this will override the default settings). The default is CON:0/11//100/term Output Window/CLOSE/SCREEN TERM.

PUBSCREEN

The name of a public screen to open the 'term' window on. In case the public screen happens to be unavailable, 'term' will fall back to the Workbench screen. Note that 'term' assumes that the main window is to be opened on a public screen rather than on a custom screen if this option is in effect, regardless how the default settings may be configured.

STARTUP

The name of an ARexx script file to be run on program startup.

PORTNAME

The ARexx host port name 'term' is to use instead of the built-in default name. The port name will be translated to upper case characters as required by the ARexx host port naming convention. The resulting name must be unique or 'term' will fall back to its built-in default name.

SETTINGS

This keyword determines where to read the default configuration file from. In order to read it from Work:term/config, one would use term Settings Work:term/config from Shell or add the tooltype entry SETTINGS=Work:term/config from Workbench. This argument does not necessarily need give the name of a path to search, but can also specify the name of the configuration file to be used.

UNIT

Similar to the DEVICE keyword the UNIT keywords affects the serial driver settings. It determines which serial driver unit is to be used instead of the one specified in the default configuration file. In order to use unit number 4 one would use term Unit 4 from Shell or add the tooltype entry UNIT=4 from Workbench.

DEVICE

In order to use a different serial device driver than the one specified in the default configuration file, use this keyword. To use duart.device one would use term Device duart.device from Shell or add the tooltype entry DEVICE=duart.device from Workbench.

QUIET

If this parameter is present, the program will not start opening a display but rather put an icon on the Workbench backdrop, waiting to be invoked. A double-click will bring it to life. This parameter will be ignored in case the STARTUP-Parameter is used along with it.

SYNC (Shell only)

If called from Shell 'term' will detach itself immediately allowing the Shell window to be closed afterwards. This effect can be avoided if SYNC is entered in the command line.

NEW (Shell only)

Usually, running `term` twice will cause the screen of the other program to be popped to the front instead of creating a second `term` process. To avoid this effect, enter NEW as a calling parameter. If called from Workbench, each program will run as a separate process.

1.12 term.guide/Keyboard_control

Keyboard control

To operate a gadget, press the key corresponding to the letter highlighted in the gadget label. Suppose a slider is labeled Baud rate with the letter r of the word rate underlined; in order to increase the slider value one had to hit the key labeled R, to decrease the value one is to hold down either Shift key while pressing the key R.

With some requesters and windows string gadgets will be auto-activated. Pressing the Return key will cycle through all the available strings gadgets, holding down either Shift key will break the cycle.

1.13 term.guide/Screen

Screen

Unless configured to open only a simple window on a public screen the `term` main screen will always open to the full text-overscan size (which can be set using the Overscan tool in the Prefs drawer).

At the bottom of the screen a small window displays a few basic parameters. These are:

Status

The current program operating status. This includes Ready, Holding (Control + S was pressed), Dialing (the dialing function is at work), Upload (data is being sent), Download (data is being received), Breaking (a break signal is transmitted across the serial line) and Hanging up (connection is being cancelled).

Font

The currently active screen font used for text/graphics rendering.

Protocol

The currently set data transfer protocol.

Emulation

The currently active terminal emulation mode.

Baud rate

The data transfer rate in bits per second.

Parameters

The current serial parameters (Data bits-Parity-Stop bits).

Time

The current time of day.

Online

The time elapsed after a connection was successfully established. This counter will be stopped as soon as the connection is cancelled (e.g. by hanging up) and is reset to 00:00:00 as soon as a new connection is made.

Every five seconds the time display will change to a calling fee display and the other way round.

The screen itself is opened as a public screen (called TERM) which is available to other programs for their purposes. If more than one 'term' process is running, the public screen name will change according to the number of the program (i.e. the first 'term' to be started will call the screen TERM, the second one will call it TERM.1, the third one TERM.2, etc.). The screen title bar will also display the name of the public screen.

1.14 term.guide/Menus

Menus

For each requester and input window there exists a set of menu items to execute the commands associated with the buttons, dials and gauges in the requester/window. Press the right mouse button to have a look at the commands and their shortcuts.

The following text is to describe the menu items available in the 'term' main menu.

Project	Printing, log files, iconification, program termination
Edit	Clipboard support
Commands	ARexx- and AmigaDOS command execution
Phone	Modem and dialing functions
Transfer	File transfer functions
Buffer	Text buffer functions
Terminal	Terminal emulation control
Settings	Program settings control
Windows	Auxiliary windows
Dial	The quick dialing menu

1.15 term.guide/Project

Project

Save screen as Picture/Text

This menu serves to save the current terminal window contents either as plain ASCII text file or as a picture file.

Print Screen/Clipboard

These menu entries are to output text on the printer. You can either print the contents of the main screen or the contents of the clipboard.

Capture to File/Printer

Selecting one of these menu entries will toggle capturing incoming text to the printer and/or a file on disk.

Iconify

Closes all screens and windows 'term' has currently open, resets and releases the serial driver and puts an icon into the Workbench window. Double-clicking this icon will cause 'term' to wake up and to return the state is was in before iconification took place.

While 'term' is iconified, most incoming ARexx-commands will be queued and the corresponding ARexx programs will appear to 'hang'. In order to reactivate the program either double-click on the program icon or send the ARexx command ACTIVATE. As soon as 'term' is 'awake' again pending commands will be processed again

About

Shows some information on the program.

Quit

Terminates the program, hold down a Shift key to quit immediately, otherwise you will be prompted to confirm your decision.

After selecting the Quit menu item the program may take a few seconds to exit since the contents of the Text_buffer are freed first.

1.16 term.guide/Edit

Edit

Copy

In order to transfer any currently marked screen text to the clipboard buffer, select this menu item. Text can be marked by double-clicking the select button while the mouse is over a word or by clicking the select button and dragging the mouse. Holding down either shift key will append the selected text to the current clipboard contents. In any other case the new text will replace the previous contents.

Paste

Pastes the contents of the clipboard at the current cursor position provided that the clipboard contains text data. Hold down either

Shift key to have 'term' include the Paste prefix and the Paste suffix (see Clipboard_panel) along with the clipboard contents.

Clear

Any currently marked text will be released as soon as any rendering operations are to be executed in the main window. To release marked text manually, select this menu item.

1.17 term.guide/Commands

Commands

Execute AmigaDOS command

Enter the command you want to execute and its command line arguments here.

Execute ARexx command

This function calls the ARexx server to execute a script file. If the first input character is a ' or " the input will be considered as a small program in a single line. Note that this function will not be available if the ARexx server isn't running.

The ARexx command set supported by 'term' is described in the 'term' ARexx interface documentation.

1.18 term.guide/Phone

Phone

Phonebook

The phonebook is one of the most powerful and complex functions of 'term' and will be described later in this document (see Phonebook).

Redial

Dialing list entries which the dialing routine was unable to establish a connection to are once again passed to the dialer.

Dial

To dial a single phone number select this menu item. The phone number entered will be passed to the dialing routine.

Send break

Sends a 'break' signal across the serial line.

Hang up

Tells the modem to hang up the serial line.

Wait...

Will cause 'term' to emit the character sequence <Blank

space><Backspace> every second in order to fool the remote into believing that terminal input is currently taking place.

Flush receive buffer

Tells the serial driver to drop its input buffer contents and resets the state of the internal serial buffers.

Release serial device

The serial driver is released for other programs to use it. A requester will appear which allows you to reopen the serial driver or to quit 'term'.

If the serial driver has been released by the ARexx interface and has not been reopened yet, this menu item will do it.

If you are still online, the Redial and Dial menu entries will be disabled. In order to make another call, hang up the line first.

1.19 term.guide/Transfer

Transfer

Upload ASCII file(s)

This is a pure ASCII-file upload. It was added to allow poor BBS programs to receive text files (especially Paragon doesn't seem to like ZModem text file upload).

Download ASCII file(s)

This is a pure ASCII-file download. Refer to Upload ASCII file(s) for features/options of this mode.

Upload text file(s)

Sends a file/files to the remote receiver using the current transfer protocol. If possible this command will 'ask' the transfer protocol to transmit the file(s) in text mode (whatever that means) which may include CR/LF substitution and other gimmicks. Consult the library documentation to find out if your favourite transfer library supports text mode.

Download text file(s)

Request a file/files using the current transfer protocol. Refer to Upload text file(s) for features/options of this mode.

Edit & upload text file

Invokes the currently selected (see Path_panel) text editor on a file to be selected using a file requester.

'term' will block and wait until the editor has returned.

After the editor has returned, the user will be asked whether the file edited is to be transferred as plain ASCII or via text upload.

Upload binary file(s)

Send a file/files to the remote receiver using the current transfer

protocol. True batch upload is supported both through wildcard expressions (#?.txt will send all files whose names end with .txt) or through multiple selection. Refer to the documentation of your favourite transfer library to find out if batch file transfer is supported.

Download binary file(s)

Receive a file/files using the current transfer protocol. If the protocol does not support batch download you are required to enter the name of the file to be received. Files which remain empty after the transfer are deleted automatically.

The transfer routines open an information window in which a number of transfer parameters are displayed (see `Transfer_progress_panel`).

1.20 term.guide/Buffer

Buffer

Clear buffer

Clears the contents of the `Text_buffer`. Any text will be discarded and cannot be recovered. Capture files are not affected by this command.

Display buffer

Opens the `Text_buffer` screen.

Close buffer

Closes the `Text_buffer` screen but does not free the contents.

Freeze buffer

This menu entry will, if enabled, stop the `Text_buffer` from filling up with new text.

Open buffer...

Loads the contents of the `Text_buffer` from a file. If there are still text lines in the `Text_buffer` a requester will appear giving you the choice to discard the old data, append the new data, or to cancel the action.

Save buffer as...

Saves the contents of the `Text_buffer` to a file. You will be notified if the file to save to exists already (you may discard the old file, append the new data or cancel the action).

More detailed information on the `Text_buffer` will be given later in this document.

1.21 term.guide/Terminal

Terminal

Clear screen

Clears the whole 'term' screen and moves the cursor to the top left home position.

Reset font

Will change the screen font back to the default screen font.

Reset styles

Resets all character style attributes (bold, blinking, inverse video, underlined, etc.) and sets the text colour to the default pen.

Reset terminal

Use this menu item to reset the state of the entire terminal emulation.

1.22 term.guide/Settings

Settings

This is where you adjust the program preferences settings. There is a difference between local and global settings: local settings can also be set by making a connection to a mailbox while global settings are kept even while local settings are active. They have to be changed explicitly.

Serial...

See Serial_panel

Modem...

See Modem_panel.

Screen...

See Screen_panel.

Terminal...

See Terminal_panel.

Emulation...

See Emulation_panel.

Clipboard...

See Clipboard_panel.

Capture...

See Capture_panel.

Commands...

See Command_panel.

Miscellaneous...

See `Miscellaneous_panel`.

Paths...

See `Path_panel`.

Transfer protocol...

This command allows you to specify the transfer protocol library to be employed for up-/downloads.

Transfer...

The transfer options can be changed with this command. If possible a control panel will pop up which allows you to change the current parameters by mouse/keyboard. If the selected transfer protocol does not provide these option hooks, a simple string requester will prompt for input. Consult the documentation of your favourite transfer protocol for legal options and the values to which they can be set.

Translation tables...

See `Translation_panel`.

Function keys...

See `Function_key_panel`.

Fast! macros...

See `Fast_macro_panel`.

Hotkeys...

See `Hotkey_panel`.

Speech...

See `Speech_panel`.

Sound...

See `Sound_panel`.

Console window...

Whenever an AmigaDOS/ARexx command is executed an output window is opened. This menu item will bring up a requester allowing you to edit the size and position of the window to be opened (consult your AmigaDOS manual for a description of the window position string). If you do not want the window to appear, simply enter `NIL:`.

1.23 term.guide/Windows

Windows

Status

This function opens a window to display program status information. Click the window to update the information:

Session start

When was the program started?

Bytes received

The number of bytes received.

Bytes sent

The number of bytes sent.

Connection message

The string returned by the modem when a connection was made.

BBS name

If available, the name of the BBS the modem is currently connected to.

BBS phone number

If available, the phone number of the BBS the modem is currently connected to.

BBS comment

If available, the phone book comment corresponding to the BBS the modem is currently connected to.

BBS user name

If available, the user name, as available through the phone book, corresponding to the BBS the modem is currently connected to.

Screen size

The size of the terminal output window in characters (columns / rows).

ARexx port name

If available, the name of the ARexx host 'term' is currently using.

Buffer size (bytes)

The size of the Text_buffer.

Free memory (bytes)

The amount of free system memory.

Review

A review window is opened which basically displays the same text as the text buffer screen. You can scroll through the text displayed both by mouse (see the right hand side scroller) and by cursor keys.

Packet

Opens an input window in which a single line of characters to be transferred across the serial line can be entered. More on this feature is explained under Packet_window below.

Fast! macros

Opens or closes the so-called Fast_macro_panel. The role of the Fast!_macros will be discussed later in this text.

1.24 term.guide/Dial

The quick dialing menu

Note: this menu is available only in case any phone book entries have the special Quick menu switch set.

Selecting any item of this menu will cause the corresponding phone number to be dialled.

1.25 term.guide/Control_panels

Control panels

This where all the control panels employed by 'term' are explained:

Serial panel	Serial settings
Modem panel	Modem settings
Screen panel	Screen settings
Terminal panel	Terminal settings
Emulation panel	Terminal emulation control
Clipboard panel	Clipboard settings
Capture panel	Capture file, log file and text buffer settings
Command panel	Command settings
Miscellaneous panel	Miscellaneous settings
Path panel	Path settings
Transfer panel	Transfer library settings
Function key panel	Function key settings
Cursor key panel	Cursor key settings
Fast macro panel	Fast macro settings
Hotkey panel	Hotkey settings
Speech panel	Speech settings
Sound panel	Sound settings
Transfer progress panel	Data transfer control
ASCII-transfer panel	ASCII-data transfer control
Translation panel	Character translation control
Phonebook	The phone directory
Rate panel	Phone rate control
Copy panel	Copying of configuration elements
Dial panel	Dialing control
Printing panel	Phonebook printing control

1.26 term.guide/Serial_panel

Serial panel

This is where the serial parameters may be changed.

Baud rate

Transfer speed in bits per second.

Bits/char

Number of bits per transferred character (7 or 8).

Parity

Serial parity (none, odd, even, mark or space).

Stop bits

Number of stop bits (1 or 2).

Handshaking

Serial handshaking mode (RTS/CTS, RTS/CTS with DRS signal check, none).

Duplex

Determines whether characters are echoed back to the terminal screen or not (full, half = local echo).

Buffer size

The number to be specified here allows to set the serial driver I/O buffer size. Every number you enter here will result in 'term' and the serial driver allocating twice the buffer size (this is only a word of warning for those among us who prefer buffer sizes of 256K and up).

Break length

Length of the break signal given in microseconds.

Strip bit 8

For those guys and gals who need it: if this switch is effect each character received or transmitted by 'term' will have its high-order bit cleared.

High-speed mode

Activates a special mode of the serial driver which is to skip a couple of internal parity and stop bits checks resulting in higher data throughput rate. If this switch is turned on, the serial parameters will be reset to 8 bits per char, no parity and 1 stop bit.

Check carrier

'term' will recognize the NO CARRIER message a modem emits when the carrier line signal drops back to low. For maximum safety, 'term' will also check the carrier signal line after receiving the NO CARRIER message if this switch is enabled. This is to make sure that no accidentally appearing string causes confusion.

If this switch is enabled, 'term' will check the carrier signal during file transfers and will abort the transfer if the signal is lost.

Note: Be sure to switch this feature off in case you wish to transfer files using a null-modem cable!

Shared access

Requested by many (two to be accurate) users, this switch allows you to run the serial driver in shared access mode. Not all driver types will allow this to happen.

xON/xOFF

This switch enables the processing of the flow-control characters xON (= Control + S) and xOFF (= Control + Q).

Pass ^S/^Q through

If this switch is enabled, 'term' will pass the xON/xOFF characters through to the modem rather than swallowing them.

Serial device

The name of the serial driver to be used by 'term'. This is usually serial.device (modem?.device for the internal Supra modem, sxbios.device for ASDG's serial IO card).

Device unit number

The device unit number of the serial driver selected above. This is usually left '0' but can also be used to address multiple serial IO ports.

Quantum

The number of bytes 'term' tries to read in one 'gulp' and runs through the terminal emulation. The more bytes read, the more time it takes to process them. While the text is processed, mouse and keyboard input are not delayed. So, choose this value carefully.

Use

Accept the current settings.

Default (phone book only)

Drop the current settings, making a connection to the corresponding phone number will leave the corresponding main configuration entry unchanged.

Cancel

Don't use the current settings.

Most modems will not recognize a sudden change in the baud rate. Type AT<RETURN> to make the change known.

If RTS/CTS (DSR) handshaking is selected, 'term' will check to see if the Data set ready line happens to be high active. If not, it will default back to software handshaking (xON/xOFF). The RTS/CTS handshaking mode will ignore the presence or absence of the DSR signal.

'term' will take advantage of Christopher Whichura's OwnDevUnit.library if installed in your system, allowing controlled access to the serial driver's resources.

1.27 term.guide/Modem_panel

Modem panel

This is where modem control strings and other related parameters are configured.

Modem init command

The string to send to the modem after successful program initialization. This string is optional and does not need to be entered.

The dialing routine will use the initialization string entered here before dialing a phone number.

Modem exit command

The string to be sent to the modem shortly before the program terminates. Just like the modem init string this string is optional and does not need to be entered.

The dialing routine will use the initialization string entered here before dialing the next telephone number.

Hangup command

The string to be sent to the modem when asked to hang up the line. This string does have to be present if the Drop DTR on hangup switch is enabled.

Dial prefix

The string to be used to prefix each dialing command. This is usually a variant of ATDP or ATDT.

Dial suffix

The string to be used to append to each dialing command. This is usually the carriage-return character `\r`.

'No carrier' message

The message the modem emits if the data carrier is lost. The program uses this to determine the length of the connection and to calculate the how much the user is to pay for it.

'Connect' message

The message the modem emits after detecting a carrier signal. 'term' uses this input to determine successful telephone connection, to reconfigure itself and to start the online timer.

'No dialtone' message

The message to be returned by the modem in case it does not encounter any dialing tone on the phone line.

'Voice' message

The message 'term' is expected to receive if the modem detects a voice call. If in dialing mode, 'term' will abort the process. The user will in any case be notified of the event.

'Ring' message

The message the modem emits if it receives a call, same effects as with the Voice message.

'Busy' message

The message the modem returns if the number which has just been dialed is busy.

'Ok' message

The message the modem returns if a command was successfully executed.

'Error' message

The message the modem returns if a command was not to be executed successfully.

Redial delay

The time to wait after walking through the whole dialing list without making any successful connection before another attempt is started.

Number of dial retries

The number of times the dialer walks through the dialing list trying to make a successful connection before giving up.

Dial timeout

The time to wait for a successful connection during dialing. After this time has elapsed, the dialer will skip to the next entry in the list.

Redial after hanging up

If this switch is in effect, 'term' will redial all the phone numbers still in the dialing list as soon as the line is hung up or the carrier signal is lost.

Connect auto-baud

Most modems echo the baud rate upon successful connection. If enabled the baud rate will be read and set for the serial driver.

Use this feature with care as it may have certain negative side-effects (such as the modem dropping the line just after connecting to a BBS)! If you happen to use a modern high-speed modem you will most certainly not need this feature. If in doubt whether you need to enable this feature you should rather disable it!

Drop DTR on hangup

Some modems will track the data terminal ready line in order to make sure that the terminal program is listening, once the line goes back to low potential, these modems will drop the line and hang up. Use this button to enable this feature.

'NO CARRIER' = 'BUSY'

If this switch is in effect, the dialing function will treat the modem response code NO CARRIER exactly as the BUSY response code.

Connect limit

This gauge is to set a certain period of time to be counted after a connection is made. When elapsed, a control sequence will be executed as to be set using the Limit macro settings. If set to

0:00 this function will be disabled.

Limit macro

A control sequence to be triggered when the time to be set using the Connect limit gauge has elapsed. If no text is entered this function will be disabled.

Time to connect

'term' cannot measure the time to pass between the remote modem picking up the line and the local modem sending the 'CONNECT' message. This slider allows to set the length of this interval. Upon connection, it will be added to the total online time.

Use

Use the current settings.

Default (phone book only)

Drop the current settings, making a connection to the corresponding phone number will leave the corresponding main configuration entry unchanged.

Cancel

Keep original settings.

1.28 term.guide/Screen_panel

Screen panel

Display modes

All display modes available for the main screen are displayed here.

The A2024-modes should only be used in connection with an A2024/Hedley-monitor. Otherwise the screen may 'crash' and working with 'term' will not be possible any longer.

Colour

This button determines the colour-mode the terminal emulation is going to use. Until now, three modes have been implemented:

4 Colours (Amiga)

Four colours, optionally blinking.

8 Colours (ANSI)

Eight colours, optionally blinking.

16 Colours (EGA)

Sixteen colours, as the EGA-palette, optionally blinking.

2 Colours (Monochrome)

Monochrome, two colours.

Palette

These buttons are used to select a colour of the screen palette that is to be changed.

Red/Green/Blue

Use these sliders to modify the red, green and blue components of the currently active colour.

Use default colours

Press this button to have the current colour palette set to the built-in default colours.

Screen font

The name of the current user-interface font is displayed here.

Select new screen font

Press this button to select a new font to be used for the user-interface design.

Make screen public

As dealt with before, the 'term' mainscreen is opened as 'public'. With this button the user may define if other applications are allowed to open up their windows on the 'term' screen.

'Shanghai' windows

This item, which is only displayed if Make screen public has been selected, is closely related to the function before. If active, all windows that will normally be displayed on the Workbench screen will open on the 'term' main screen.

Blinking

If selected the VT100-blink option is enabled. If running in eight colour mode, 'term' will only use three bitplanes instead of four for text display.

Faster layout

Activating this switch will slow down display updates and window management. Oh well, not always, there may be a speed increase with some configurations, such as with external emulations activated or when using more than four colours on the screen.

I suggest to experiment with the effects of this button before actually using it.

Screen title

If this button is enabled, the 'term' screen will contain a draggable title bar, if not, the title bar will be disabled, leaving more space for the terminal output window.

Use public screen

'term' does not necessarily open a custom screen, this switch will make the main and auxiliary windows appear on a named public screen. 'term' will try to adapt colours and text rendering modes to its new environment. It will share the screen palette with other applications which makes it possible to run the built-in terminal emulation in eight or sixteen colours provided that enough shareable screen pens are available (note: Kickstart 3.0 required). 'term' will inherit the text font to be used for user-interface layout from the public screen it will open its window on. As of Kickstart 2.04 'term' will fall back to opening a

custom screen in case the public screen text font happens to be proportional-spaced.

Note: only the built-in terminal emulation is guaranteed to take advantage of pen-sharing facilities, external emulation libraries will most likely fail to display text correctly!

Take care when resizing the 'term' main window as a size change will reset the terminal emulation.

Public screen name

The name of the public screen 'term' is to open windows on. 'term' will fall back to the Workbench screen if no proper name is given (i.e. no name is entered) or the desired screen is unavailable.

Status line

This switch allows to disable the status line display or to change between two alternative status line displays:

Disabled

No status line is displayed.

Standard

The standard two status lines are displayed.

Compact

A very condensed version of the status line is displayed, only the data is shown but no captions. The data is displayed in the following order:

1. Status
2. Terminal type
3. Transfer protocol
4. Baud rate
5. Serial parameters
6. Time of day
7. Online time

Online display

This switch determines what type of information is to be displayed in the bottom right corner of the status display:

Online time

The time online

Online cost

The amount of money to be paid for the connection

Time & cost

Both time and money, the display will toggle between both of them every five seconds.

Use

Use the current settings.

Default (phone book only)

Drop the current settings, making a connection to the corresponding phone number will leave the corresponding main configuration entry unchanged.

Cancel

Keep the old settings.

Some display modes (such as Super-Hires, Productivity, etc.) restrict the number of screen colours on ECS machines. Instead of 16 bit fractions for red, green and blue only 2-bit fractions are used which leads to a maximum width of the palette of at all 64 colours. This is not a 'feature' of 'term', but a hardware restriction.

1.29 term.guide/Terminal_panel

Terminal panel

All settings that may be done here determine the behaviour of the terminal itself, i.e. how command sequences are interpreted and displayed.

Bell

This is where you select the action(s) 'term' is to take whenever a bell character turns up in the data stream:

Visual

The screen will flash.

Audible

An audible signal will be generated.

Visual & audible

A combination of both effects.

Ignore

Nothing will happen.

System default

The system beep routines will be used.

Alert

'term' notifies the user of certain events, such as a connection being established or a file transfer action which has just been finished. This switch allows you to select the type of notification:

Bell

A bell signal will be given.

Screen

The 'term' screen will be brought to the front.

Bell/Screen

A combination of the two actions above.

None

Nothing will happen.

Emulation

At this point the user may select the terminal emulation. First there is a solid VT102/VT220/ANSI emulation which supports all common commandsequences, then there is a so called Atomic emulation which does only support the very basic command-sequences (CR, LF, Backspace, etc.), all VT102- and ANSI-command-sequences are suppressed, and, last but not least, a TTY-emulation which does not suppress all command-sequences, as Atomic does, but rather echoes them to the screen.

In addition to the built-in terminal emulation, 'term' also supports external terminal emulations. To select one, set the terminal emulation type to External and enter the name of the emulation in the string gadget below (the file may alternatively be selected by hitting the Select new emulation button). In case anything goes wrong loading or initializing the terminal emulation library, 'term' will switch back to the built-in ANSI/VT emulation.

If in hex-mode the program will display all incoming characters in a special notation. The left hand screen side will show the character code in hexadecimal notation, the right hand side will - if possible - display the character as a glyph.

Emulation name

The name of an external terminal emulation library to be used by 'term' instead of the built-in emulation code.

Font

Here the type of the font to be used for text display in the terminal window can be selected:

Standard

The standard text font.

IBM-PC style

A font similar to the IBM-PC text font will be used. This requires the IBM.font to be present in the Fonts: directory. No matter how the translation tables (see Translation_panel) are configured, outgoing Amiga characters are translated into PC character values.

IBM-PC style (raw)

This selection has very much the same effect as IBM-PC style but no character translation is involved.

Text font

Here the name of the standard terminal window text font is displayed.

Select new text font

Press this button to select a new terminal window text font.

Send CR

This button determines the sequence that is sent to the remote if a carriage-return is issued.

As CR

Without any change

As CR+LF

Carriage-return and linefeed

Ignore

Suppress any carriage-return

Send LF

This button determines the sequence that is sent to the remote if a linefeed is issued.

As LF

Without any change

As LF+CR

Linefeed and carriage-return

Ignore

Suppress any linefeed

Receive CR

Receive LF

These two buttons have largely the same effect as the Send CR/LF buttons, they are different in that they affect the incoming data rather than the data transmitted.

Columns

The number of columns to use for the terminal window. The minimum value is 20 columns, the maximum value is defined by the actual screen size.

Lines

The number of lines to use for the terminal window. The minimum value is 20 lines, the maximum value is defined by the actual screen size.

Keymap file

If your installation requires that 'term' is to use a custom keymap layout, enter the keymap file name here.

At the time of this writing the program will not support custom keymap layouts with the Packet_window due to operating system limitations.

Use

Use the current settings.

Default (phone book only)

Drop the current settings, making a connection to the corresponding phone number will leave the corresponding main configuration entry unchanged.

Cancel

Keep the old settings.

1.30 term.guide/Emulation_panel

Emulation panel

The buttons found here allow you to change the internal parameters of the selected emulation.

The following text only describes the parameters to change when using the built-in terminal emulation; if an external terminal emulation is in effect, this menu will conjure up the corresponding parameters menu supported by the external terminal emulation module.

Cursor keys

If this mode is active the cursor keys transmit a command-sequence instead of a cursor move event. If the remote computer needs these sequences, this mode - applications mode - can be activated with this button.

Numeric keypad

If this mode is activated the keys of the numeric keypad transmit a command-sequence instead of a number. If the remote computer needs these sequences, this mode - applications mode - can be activated with this button.

Wrap cursor moves

According to the VT100-specification the cursor movements have to stop at the edges of the screen. In spite of this the cursor may leave these borders, especially in ANSI-mode, and may appear at the other side of the screen. This button activates a more 'tolerant' mode.

Wrap characters

This function activates the automatical carriage return function which is triggered as soon as the cursor crosses the right screen margin. To avoid unpleasant side-effects, this gadget should be activated all the time.

'CLS' resets cursor position

As per the VT-100 specs, the control sequence to clear the screen is not to change the current cursor position. However, several applications expect it to be moved to the top left corner of the screen. This button will activate this behaviour.

Insert mode

Normally, 'term' is in overwrite-mode (characters entered overwrite the contents of the screen). If this gadget is

activated, typed characters are inserted by pushing all the characters right of the cursor towards the right margin.

The insert-mode does only work for lines. If characters are pushed out of the screen they cannot be restored.

New-line mode

This gadget activates a special mode in which some VT100-control-sequences cause 'term' to perform a linefeed instead of clearing the screen or other serious changes of the contents of the screen.

Font scale

VT-100 offers several different sizes of fonts. Some can be selected with this gadget:

Normal

The normal height of the font.

Half width

Half width of font.

Scrolling

This button selects one of two different scrolling modes: smooth or jumping.

Destructive backspace

Determines if the Backspace code, which will delete the character left from the cursor, only moves the cursor to the left or removes the character from the screen.

Swap 'Backspace' and 'Del' keys

For all VT100 groupies: if this switch is enabled the roles of the backspace key and the delete key are reversed. This also applies to sequences such as Control + H which will produce a delete character instead of a backspace character.

Printer control enabled

'term' supports the standard VT220 printer control commands. If you don't want the application on the other side of the line to play with the printer the printer support commands can be disabled with this switch. If disabled 'term' will act like a VT220 terminal with no printer attached.

Answerback message

The string to send across the serial line whenever an ENQ character is received. The string is - as usual - a command sequence.

Use

Use the current settings.

Default (phone book only)

Drop the current settings, making a connection to the corresponding phone number will leave the corresponding main configuration entry unchanged.

Cancel

Keep the old settings.

1.31 term.guide/Clipboard_panel

Clipboard panel

Clipboard unit

The clipboard supports several units (0-255) which can be accessed independently. It can make sense to change this value but generally you will probably leave it as unit '0'.

Character delay

When sending text this number determines how many seconds to wait before sending the next character.

Line delay

When sending text this number determines how many seconds to wait before sending the line-termination character (carriage return).

Line prompt

The character to wait for the receiver to issue after a line of text is send. These character may include control sequence tokens.

Send timeout

If the Text pacing mode is set to Wait for echo or Wait for line prompt the maximum time to wait for echo/prompt before the insertion is aborted.

Text pacing

The mode to determine how text is sent to the remote:

Direct

Each line will be sent without any delay.

Wait for echo

The program will wait for each single character sent to be echoed by the remote.

Wait for any echo

The program will wait for the remote to return any character in response to any character sent. Typically, this is the case with password prompts issued by BBSes.

Wait for line prompt

The program will wait until the remote sends a certain line prompt text.

Character/line delay

The program will respect the character/line delay values to be set using this control panel.

Keyboard delay

The program will send character separated by a delay to be

determined by the current system keyboard repeat delay.

Note: the 'echo' text pacing mode is to be used with great care. Certain online services do not echo characters back to the sender as they run only in half-duplex mode. On the other hand most mailbox programs will not echo certain characters, such as escape codes, etc.

Paste prefix

If enabled, the text to send before the clipboard contents are fed into the input stream, see Clipboard.

Paste suffix

If enabled, the text to send after the clipboard contents are fed into the input stream, see Clipboard.

Use

Use the current settings.

Default (phone book only)

Drop the current settings, making a connection to the corresponding phone number will leave the corresponding main configuration entry unchanged.

Cancel

Keep the old settings.

1.32 term.guide/Capture_panel

Capture panel

Log actions

If enabled will write a protocol of each program action (uploads, downloads, dial attempts, etc.) to a file. Each action is listed along with time and date. Carrier-lost events will also note the approximate cost of the call.

Log file

The name of the file in which the information on the actions executed by 'term' will be logged if Log actions is enabled.

Log calls

If this switch is enabled, 'term' will create call-log files in a format compatible with the NComm terminal program.

Call log file

The name of the file in which the information on calls made by 'term' will be logged if Log calls is enabled.

Maximum text buffer size

To save memory, a high-water mark concerning the maximum amount of memory the Text_buffer will allocate for text may be specified. The minimum value to be entered here is 2,000 bytes which are roughly equivalent to two Text_buffer pages of text. A value of 0

will cause the Text_buffer to always allocate as much memory as required to buffer all the incoming text.

Text buffer enabled

This switch works in conjunction with the Freeze buffer menu entry (freezing the Text_buffer contents). In fact, the menu entry is adjusted according to the configuration settings whenever a new configuration is invoked (that is, whenever a new connection is made through the dialing panel or at program startup time). 'term' will only freeze the buffer if this switch is set, it will leave the buffer state (frozen or not) untouched if this switch is not enabled.

Text buffer file path

The path the file requester will bring up when saving the contents of the text buffer.

Connect-auto-capture

If enabled will automatically open a capture file after successfully making a connection. Any other already open capture file will be closed before proceeding. The files created will bear the names of the corresponding phonebook entry, the first line to be written to tell the time and date when the file was opened.

Creation date

By default 'term' will append the date of the call made to the name of the auto-capture file created. Alternatively, 'term' will use only the BBS name for auto-capture files, including creation date lines in the file.

Capture filter enabled

If selected, command sequences are filtered out before the incoming characters are captured to disk or printer.

Capture file path

This string gadget contains the path in which the the capture files will be created if Connect-auto-capture is enabled.

Open buffer window

This switch controls which part of the text buffer contents the review buffer window will display when opened:

Top

Displays the top of the buffer contents.

End

Displays the end of the buffer contents.

Remember window position

If this switch is in effect, the program will remember the text display position between calls rather than jumping to the top or the end of the text buffer.

Open buffer screen

This switch controls which part of the text buffer contents the review buffer screen will display when opened:

Top
Displays the top of the buffer contents.

Remember
Keeps the previous buffer position.

End
Displays the end of the buffer contents.

Remember screen position
If this switch is in effect, the program will remember the text display position between calls rather than jumping to the top or the end of the text buffer.

Buffer screen position
The buffer screen will usually not be quite as wide as the system overscan settings permit. This switch determines the horizontal placement of the screen:

Left
The screen will be left-edge aligned.

Centre
The screen will be centred.

Right
The screen will be right-edge aligned. This will bring the screen depth arrangement gadget in line with the other screens.

Buffer line width
The text buffer stores lines at a fixed size, this slider determines the maximum line width.

Use
Use the current settings.

Default (phone book only)
Drop the current settings, making a connection to the corresponding phone number will leave the corresponding main configuration entry unchanged.

Cancel
Keep the old settings.

1.33 term.guide/Command_panel

Command panel

Here you will find entries for four command sequences which serve four functions:

Startup/Login macro
At the beginning of every session with 'term' and after a

connection has been established by the dialing routine a command-sequence is executed which may execute command-files or perform a automatical 'login'.

Logoff macro

The macro to execute when the line is hung up or the carrier signal is lost.

Upload macro

'term' will execute this macro after a successful upload has been made.

Download macro

'term' will execute this macro after a successful download has been made.

Use

Use the current settings.

Default (phone book only)

Drop the current settings, making a connection to the corresponding phone number will leave the corresponding main configuration entry unchanged.

Cancel

Keep the old settings.

1.34 term.guide/Miscellaneous_panel

Miscellaneous panel

This is the place where options can be set which would not fit into other control panels

Program priority

Use this slider to determine the priority under which the 'term' main process is to operate. Adjusting this value can make 'term' perform more reliably in a system which experiences heavy task loading. It is recommended to play with this value until a satisfactory state is found, setting the program priority too high or too low may affect the performance of coprocess-services such as the double-buffered file I/O routines.

Backup configuration

By default the local program configuration saved along with a phonebook entry will replace the global configuration as soon as a successful connection is made. If this switch is enabled, 'term' will remember the global configuration in effect before the configuration data of a phonebook entry is adopted. As soon as the serial driver loses track of the carrier signal or the user chooses to hang up the line, 'term' will switch back to the previous global configuration.

Show fast! macros

If this switch is enabled, the `Fast_macro_panel` will be opened whenever the current configuration becomes active (e.g. at startup time).

Release serial device when iconified

By default the serial device driver is released when `'term'` is iconified. Unfortunately, some modems drop the line when the device is closed so this switch allows you to keep the link.

Override transfer path

Each batch file transfer protocol allows you to specify the name of the directory to place the files it receives in. By default `'term'` will redirect the files to a directory to be specified in the `Path_panel`. If this switch is disabled, the internal settings of the current transfer protocol will be used.

Use auto upload panel

Some users found the so-called ZModem auto-upload panel to be invoked whenever `'term'` encounters the ZModem inquiry sequence rather disturbing, this switch will allow them to disable this feature.

Transfer performance meter

When a file transfer is running, `'term'` may optionally display the file transfer performance in a small resizable window. The lines drawn represent the following information:

- Black line
This line displays the current transfer performance (usually heavily oscillating).
- Blue line
This line displays the average transfer performance.
- White line
This line displays the smallest transfer performance (should be constant during the transfer).

Set `'archived'` bit

If enabled, this switch will cause `'term'` to set the Archived bit on files transferred using the XPR-interface.

Transfer file icons

This switch works in conjunction with the drag & upload feature (see `Transfer_progress_panel`). By default, `'term'` will upload only the files whose icons are dragged on the main window, if this switch is in effect the icon files will be transferred as well.

Create icons

If this switch is in effect `'term'` will try to provide icons for all files it receives. The following file types (and the corresponding icon files) are supported:

- Text file
icon `ENV:sys/def_text.info`
 - Sound file
-

icon ENV:sys/def_sound.info

•Picture file

icon ENV:sys/def_picture.info

•Tool

icon ENV:sys/def_tool.info

•Archive file

icon ENV:sys/def_archive.info

•Preferences file

icon ENV:sys/def_pref.info

•Other file types

icon ENV:sys/def_project.info

Text and pictures saved by the program will also get icons attached.

File comment

This is where the action to perform on downloaded files can be set:

Ignore

The file comment will not be touched.

File type

The file will be examined and a guess will be made which type of file it is. The file comment will be set to the name of the file type.

Source and time

The current BBS name and the time the file was received are placed in the file comment.

Simple file I/O

This switch controls whether 'term' is to use double-buffered file management routines or not.

Use

Use the current settings.

Default (phone book only)

Drop the current settings, making a connection to the corresponding phone number will leave the corresponding main configuration entry unchanged.

Cancel

Keep the old settings.

1.35 term.guide/Path_panel

Path panel

In this part of the settings all paths, which 'term' uses to save or load any data, can be determined.

...Uploadpath

...Downloadpath

The directories in which the functions contained in the Transfer menu will search and create files.

Configuration storage directory

The directory that will contain all configuration files (Phonebook, Macrokeys, etc.). The default configuration file is called term.prefs and will be searched in the path defined by the environment variable TERMCONFIGPATH (see Environment_variables).

Text editor

Contains the name and search path of the editor used by Edit & upload text file in the Transfer menu.

"term" help text file

This is where the name of the online-help text file is stored. By default this is PROGDIR:term.guide.

Use

Use the current settings.

Default (phone book only)

Drop the current settings, making a connection to the corresponding phone number will leave the corresponding main configuration entry unchanged.

Cancel

Keep the old settings.

1.36 term.guide/Transfer_panel

Transfer panel

This is where the libraries to be employed for file transfers are to be selected.

Default transfer library

This library will be active most of the time, unless a special library is temporarily enabled. Auto-downloads and auto-uploads will be handled by this library, even if you select a text transfer in the auto-upload panel.

ASCII upload library

The XPR library to be used when sending plain ASCII text as triggered by selecting the Upload ASCII file(s) menu item. This is usually xprascii.library. If no name is given, the Default transfer library will be used.

Use built-in upload routine

If this switch is enabled, 'term' will ignore the ASCII upload

library settings and use a built-in transfer routine instead.

ASCII download library

The XPR library to be used when receiving plain ASCII text as triggered by selecting the Download ASCII file(s) menu item. This is usually xprascii.library. If no name is given, the Default transfer library will be used.

Use built-in download routine

If this switch is enabled, 'term' will ignore the ASCII download library settings and use a built-in transfer routine instead.

Quiet ASCII transfer

When a built-in ASCII transfer routine is running, this switch controls whether incoming text will be displayed in the terminal window. You may want to watch how the remote responds to the data sent/received.

Text upload library

The name of the XPR library to be used when selecting the menu item Upload text file(s). If no name is given, the Default transfer library will be used.

Text download library

The name of the XPR library to be used when selecting the menu item Download text file(s). If no name is given, the Default transfer library will be used.

Binary upload library

The name of the XPR library to be used when selecting the menu item Upload binary file(s). If no name is given, the Default transfer library will be used.

Binary download library

The name of the XPR library to be used when selecting the menu item Download binary file(s). If no name is given, the Default transfer library will be used.

Use

Use the current settings.

Default (phone book only)

Drop the current settings, making a connection to the corresponding phone number will leave the corresponding main configuration entry unchanged.

Cancel

Keep the old settings.

1.37 term.guide/Translation_panel

Translation panel

'term' is capable of replacing any incoming and outgoing character

with custom text. This may come in handy with the numerous incarnations of the dreaded IBM PC font. The control panel to be opened features a large list of buttons, each single one representing a single character. Some characters are shown with their corresponding glyphs, some with their symbolic names and some as plain numbers. Clicking on one of the buttons will bring up a control panel which allows setting the text to be received by the terminal emulation when a certain character is received and the text to be sent when a certain characters is transmitted.

Both texts can consist of standard `Command_sequences`, except for the following commands which are not supported: `\a`, `\c`, `\d`, `\g`, `\i`, `\p`, `\u` and `\x`.

Please note that the translation does not come for free, terminal input and output speed may suffer.

As of this writing only a few translation table files (see below) are included in the distribution. If you wish to create translation tables for IBM doorway mode, national IBM-PC style font variants, etc. feel free to send them to me. I will try to include them in the next 'term' release.

Currently included in the 'term' distribution are the following translation table files:

ISO-4-(GB).prefs
British 7 bit (ISO code 4) character set.

ISO-10-(S).prefs
Swedish 7 bit (ISO code 10) character set.

ISO-11-(S).prefs
Swedish 7 bit (ISO code 11) character set.

ISO-15-(I).prefs
Italian 7 bit (ISO code 15) character set.

ISO-16-(P).prefs
Portuguese 7 bit (ISO code 16) character set.

ISO-17-(E).prefs
Spanish 7 bit (ISO code 17) character set.

ISO-21-(D).prefs
German 7 bit (ISO code 21) character set.

ISO-60-(N).prefs
Norwegian 7 bit (ISO code 60) character set.

ISO-61-(N).prefs
Norwegian 7 bit (ISO code 61) character set.

ISO-69-(F).prefs
French 7 bit (ISO code 69) character set.

PC-8.prefs

Character translation for standard IBM-PC style font. If you wish to use these translation tables, make sure to set the Font type in the Terminal_panel to IBM-PC style (raw).

Unfortunately, there is no translation available for the Norwegian and Danish variants of the PC-8 character set as I do not yet have a fitting Amiga font available. Similar reasons have yet prevented to implement PC-850 character set support.

1.38 term.guide/Function_key_panel

Function key panel

This control panel allows setting user definable texts for all ten function keys. All texts are considered Command_sequences, a topic which will be covered later in this document.

Modifier

All in all 40 keys may be covered with user defined Command_sequences. As the Amiga keyboard only has ten function-keys this button switches between the modifier keys (Shift, Control, Alt) which, if pressed in addition with a function key, will execute one of the 40 command sequences.

Load

Load the function key settings from a file.

Save

Save the function key settings to a file.

Use

Use the current settings.

Cancel

Keep the old settings.

As the definition of the function keys with command sequences contradicts the standard definition of the four function keys of a VT-100-terminal, the keys F1-F4, which may be executed by pressing the Shift key and the appropriate function-key simultaneously, are mapped to the standard sequences for function-keys. The user may - of course - change these settings.

If an external terminal emulation happens to be active, those function keys the emulation has allocated for itself will be disabled and cannot be edited.

1.39 term.guide/Cursor_key_panel

Cursor key panel

This control panel both works and looks similar to the `Function_key_panel`, the only difference is that it is to assign command sequences to the cursor keys rather than to the function keys. Displayed are the assignments for all four cursor keys and the following buttons:

Modifier

Any cursor key can be pressed along with one of the modifier keys (Shift, Control, Alt). This button will switch between the different assignments.

Load

Load the cursor key settings from a file.

Save

Save the cursor key settings to a file.

Use

Use the current settings.

Cancel

Keep the old settings.

1.40 term.guide/Fast_macro_panel

Fast macro panel

The design and implementation of the settings to be configured in this menu are closely related to the menu entry `Function_key_panel` discussed before, the only difference to be seen in the fact that the `fast!` macros are mapped to buttons rather than function keys (more on this topic later in this document, see `Fast!_macros`).

Macro list

The list of macros entered yet, to edit one of these, select it by clicking the mouse button with the mouse pointer on it.

Macro

The name of a macro by which it is listed in the `fast!` macro list.

Macro code

The command sequence (see `Command_sequences`) associated with a `fast!` macro. Command sequences are discussed later in this document.

New

Appends a new macro to the list. The user may then select and customize it.

Delete

Removes the currently selected macro from the list.

Load

Loads the macro list from a file.

Save

Saves the macro list to a file.

Top

Places the currently selected macro at the top of the list.

Up

Moves the currently selected macro one entry up.

Down

Moves the currently selected macro one entry down.

End

Places the currently selected macro at the end of the list.

1.41 term.guide/Hotkey_panel

Hotkey panel

This is where the key sequences used to arrange screens and to execute special functions are to be configured.

term screen to front

The keys to press to bring the 'term' screen to the front.

Buffer screen to front

The keys to press to bring the screen of the Text_buffer process to the front.

Skip dial entry

As an alternative to the Skip button, pressing these keys will skip a dialing entry if the dialing function is currently active.

Abort ARexx command

An ARexx script started from within 'term' can be aborted by pressing these keys. Use this function only if pressing Control + C does not stop the program execution.

Commodity priority

The commodity priority to assign this task to. You may want to change this value if you have more than one program running which uses the same key sequences as 'term'. The program with the higher commodity priority will receive the keystrokes first.

Hotkeys enabled

Whether the hotkeys are enabled or not can be toggled by clicking on this button, or by using the Exchange program to be found in the Tools/Commodities drawer.

Load

Loads the hotkey settings from a file.

Save

Saves the hotkey settings to a file.

Use

Use the current settings.

Cancel

Keep the original settings.

If any changes made here do not seem to take effect immediately, the user has probably typed a keyword wrong (causing the entire hotkey setup to fail). I'm sorry about this, but the current implementation of hotkey support does not sport error checking.

1.42 term.guide/Speech_panel

Speech panel

If enabled, the Amiga speech synthesizer will be used to alert the user of certain actions, such as carrier lost, connection made, etc. This feature makes sense if 'term' is running in the background where the user cannot see what is actually happening on the main screen. By default this feature is disabled.

Note: speech synthesis is no longer available with Kickstart 3.0 and Workbench 2.1!

Rate

Speaking speed in words per minute.

Pitch

The greater this value, the higher the voice appears to be speaking.

Frequency

Voice frequency in Hertz.

Volume

The volume of the voice.

Sex

Enabled female or male voice.

Speech enabled

Toggles the activity of the speech synthesizer.

Speak!

Speaks a small sample text, note that speech must be enabled for this function to work.

Load

Loads the speech settings from a file.

Save

Saves the speech settings to a file.

Use

Use the current settings.

Cancel

Keep the original settings.

1.43 term.guide/Sound_panel

Sound panel

As an option 'term' will associate sounds with special program functions and events. This is where the sounds are configured:

Terminal bell sound

The sound to be played whenever a BEL character is output on the terminal screen.

'Connect' sound

The sound to be played when a connection is established.

'Disconnect' sound

The sound to be played when a connection is lost.

'File transfer finished' sound

The sound to be played when a file transfer is finished successfully.

'File transfer failed' sound

The sound to be played when a file transfer is finished unsuccessfully.

Modem 'ring' sound

The sound to be played when the modem detects a call by a different modem.

Modem 'voice' sound

The sound to be played when the modem detects a phone call.

Preload sound files

If this switch is enabled 'term' will load all sound files immediately rather than accessing and loading them on demand. This may save access time when a sound is to be played but may eat up precious memory.

Load

Load the sound settings from a file.

Save

Save the sound settings to a file.

Use

Use the current settings.

Cancel

Keep the old settings.

There is no fixed size limit to sound files, the amount of available system memory matters. The sound files may be compressed, mono or stereo files.

1.44 term.guide/Transfer_progress_panel

Transfer progress panel

The transfer routines open an information window in which a number of transfer parameters are displayed. Additionally, the file transfer can be aborted by clicking either of two buttons (Abort entire transfer and Skip current file). For most transfer protocols both buttons (abort and skip) have the same effect. Consult the documentation to see if different levels of abort are supported by your favourite transfer protocol.

The following information is displayed in the transfer window:

Protocol

The name of the transfer protocol currently running.

Information

A list to contain error message, the names files transferred and miscellaneous other messages addressed to the user.

File

The name of the file being transferred.

Next file

The name of the next file to be transferred.

Space left

The space left on the destination device. 'term' will try to calculate the number of blocks the file being received will take on the destination device and display a warning the file in question is probably not going to fit.

Caution: 'term' only makes a very likely guess which may or may not come true. The guess may be wrong if the destination device happens to be a kind of ram-disk which shrinks and expands as memory requirements come and go. Such devices are usually 100% full. In most other cases you will probably be able to make room for the file being received before any space problem turns up.

Completion time

If the corresponding information is available, the point of time when the current file will be transferred completely.

File size

If available, the size of the file.

Bytes transferred

Number of bytes transferred yet.

Total size

The total size of all files to be transferred.

Total bytes transferred

The total number of bytes transferred yet.

Files transferred

The number of files transferred yet and the number of files to go.

Blocks transferred

Number of data blocks transferred yet.

Characters/second

The effective transfer speed in characters per second.

Character delay

The delay between two character being sent.

Packet delay

The delay between two packets being sent.

Packet type

A short description of the data block type employed for data transfer.

Block check type

The method employed to verify the integrity of the data blocks being transferred (this usually is a form of cyclic redundancy checking).

Block size

Size of a data block in bytes.

Expected time

The time the transfer protocol expects the transfer will take.

Elapsed time

The time elapsed during transfer.

Message

A message of the transfer protocol addressed to the user.

Number of errors

The number of errors occurred during file transfer.

Number of timeouts

The number of timeouts occurred during file transfer.

If the currently active transfer protocol provides the necessary information, two bars will be displayed at the bottom of the transfer window indicating the amount of transferred data and of time to go

before the transfer is finished.

'term' knows about the Z-Modem data-inquire sequence the remote receiver issues when expecting files. If recognized, this sequence will cause 'term' to display a requester asking for the type of data upload: text or binary. One could call this feature 'auto upload'. You also have the opportunity to select Abort which will transfer the ZModem abort sequence or to click on the Ignore gadget which will plainly ignore the fact that the ZModem inquiry sequence has been recognized. The Z-Modem abort sequence will also be transferred if you select the Cancel button in the file requester to appear after selecting text- or binary-upload.

Some transfer protocols will allow you to enter a default receive path the library is supposed to create files it receives in. On request (see `Miscellaneous_panel`) 'term' will ignore these settings and use the settings to be changed in the `Settings/Paths` (see `Path_panel`) menu instead.

Each file that is received and which does not remain empty is examined briefly to find out about the file type. If recognized successfully and the corresponding feature is enabled, a small comment indicating the file type will be attached to the file. 'term' currently knows about 83 different file types.

If the 'term' main window is opened on the Workbench screen, you can select and drag icons on it in order to upload the corresponding files. A requester will be opened to ask for the upload style (either binary or text).

In case a file transfer terminates with an unrecoverable error (note: the transfer protocol is responsible for reporting error conditions to 'term') the file transfer window will stay open until explicitly closed by the user so the transfer error report list can be viewed.

1.45 term.guide/ASCII-transfer_panel

ASCII-transfer panel

The built-in ASCII transfer routines as to be enabled in the `Transfer_panel` display transfer progress information in a special window (note that sending and receiving will open different windows). Here is a description of the controls and displays:

Bytes transferred

The number of bytes sent/received.

Lines transferred

The number of text lines sent/received.

Information

Transfer progress information and error display.

Character delay

When sending text this number determines how many seconds to wait before sending the next character.

Line delay

When sending text this number determines how many seconds to wait before sending the line-termination character (carriage return).

Text pacing

The mode to determine how text is sent to the remote:

Direct

Each line will be sent without any delay.

Wait for echo

The program will wait for each single character sent to be echoed by the remote.

Wait for any echo

The program will wait for the remote to return any character in response to any character sent. Typically, this is the case with password prompts issued by BBSes.

Wait for line prompt

The program will wait until the remote sends a certain line prompt text.

Character/line delay

The program will respect the character/line delay values to be set using this control panel.

Keyboard delay

The program will send character separated by a delay to be determined by the current system keyboard repeat delay.

Note: the 'echo' text pacing mode is to be used with great care. Certain online services do not echo characters back to the sender as they run only in half-duplex mode. On the other hand most mailbox programs will not echo certain characters, such as escape codes, etc.

Quiet ASCII transfer

This switch controls whether incoming text will be displayed in the terminal window. You may want to watch how the remote responds to the data sent/received.

Abort entire transfer

Stops the ASCII data transfer.

Skip current file

Stops sending the current file and proceeds to the next.

In case a file transfer terminates with an unrecoverable error the file transfer window will stay open until explicitly closed by the user so the transfer error report list can be viewed.

1.46 term.guide/Phonebook

Phonebook

The functions described in the following can be found in the Modem menu and relate to the menu entries Phonebook, Dial and Redial.

'term' is equipped with a telephone number management system, the phonebook, which is described in the following lines.

Name list

The names of all phonebook entries are displayed here.

BBS name

Name of the last selected telephone book entry.

Comment

A comment to associate with a phonebook entry.

Phone number

The telephone number of the last selected telephone book entry.

If a BBS supports multiple lines, the phone number of each line may be entered, each one separated by a vertical bar | character (example: 123456|654321 would cause the dialing routine to dial the numbers 123456 and 654321). The dialing routine will process all these phone numbers before proceeding to the next phonebook entry.

The | character also works for the modem init, modem exit and dial prefix sequences. Whenever the dialing routine dials another phone number from a list separated by bars, it will try to find a matching init/exit/dial prefix sequence. If more phone numbers are specified than sequences are available, it will use the last sequence given (an example: a phone number may be given as 123456|654321|12345, the dial prefix string may be ATDP|ATDT; the dialing routine will call the first number using ATDP123456, the second number using ATDT654321 and the third number, since no special dial prefix is available, again using ATDT12345).

Quick menu

If this switch is in effect, the corresponding phone book entry will be put into the quick dialing menu (see at the right hand side of the main menu. Selecting the menu entry will dial the corresponding phone number. Note: only up to 50 phone numbers can be put into the list.

New entry

Generates a new telephone book entry with standard settings and places it at the end of the telephone book.

Clone entry

Will duplicate the currently selected phonebook entry and place it at the end of the list.

Remove entry

Removes the last selected telephone book entry from the telephone book and frees the memory allocated for this entry.

Dial list

Will pass the list of currently marked phonebook entries to the dialing routine.

Clear list

Will clear the marks set for each telephone entry in the dialing list.

Use entry

Takes over the local configuration settings saved with the currently selected phone book entry. Also installed are the associated password and user name entries.

Load list

Loads the contents of a telephone book from a file.

Sort list

If any phonebook entries have been selected to be dialed, the phonebook entries will be sorted in the order of dialing. The remaining phonebook entries will be sorted in ascending alphabetical order.

Save list

Saves the contents of a telephone book to a file.

Copy config

A lot of time can be saved by copying selected parts of the global configuration to a local configuration which is part of a phonebook entry. Selecting this button will invoke a control panel which allows to select which parts of the global configuration should be copied. The control panel also remembers which parts were copied when it was invoked the last time, see `Copy_panel` for more information.

Password

Press this button if you wish to save a special access password with the currently active telephone book file. You will then be asked to enter the password. What you type will not appear on the screen.

To clear an existant password and to save the phonebook file without encryption, just press return when asked to enter the new password.

The next time you save the phonebook data, the password will be encrypted and saved with it, the phonebook data itself will be encrypted using the password.

Whenever an encrypted phonebook file is loaded, it will take longer to load than an ordinary phonebook file, the same applies to saving phonebook data.

Print

This button will cause another control panel window to be opened

which is to be described under `Printing_panel`.

Another list is located at the right hand side of the window. Each entry refers to a control panel to be invoked on the currently selected phonebook entry.

Settings

- Serial
- Modem
- Screen
- Terminal
- Emulation
- Clipboard
- Capture
- Commands
- Misc
- Paths
- Transfer
- Translations
- Function keys
- Cursor keys
- Fast! macros

These entries refer directly to the settings main menu entries of the same name.

User/Password

This entry will open a control panel in which the password and user name to be used for the current phonebook entry can be entered. Both password and name are made available from within the 'term' ARexx interface to allow auto login script files to set up a connection.

Rates

'term' will count the minutes you are online and connected to a BBS as soon as a connection is made through the dialing routine. This entry opens a control panel which allows setting the necessary data (see `Rate_panel`).

If you are still online, the Dial list gadget will be disabled. In order to make another call hang up the line first.

To put a phonebook entry into the dialing list, Shift-click (i.e. hold down either shift key, then click once on the list entry) its name. The number appearing to the left of its name indicates the precedence of entries in the dialing list. To remove an entry from the list, Shift-click it again. Instead of Shift-clicking on an entry, the space bar may be pressed as well.

Double-clicking on a name will immediately dial the selected entry.

To dial the list of selected entries, press the Dial list button, control will be passed over to the dialing panel.

As I have been asked several times: For dialing a telephone number the dialing prefix specified for this telephone number is used. If the MNP-error correction for a certain mailbox has to be specifically switched on via the dial string, this has to be done in the modem

settings for this mailbox and not in the global settings of 'term'. The Modem init string and Modem exit string entries of the telephone book can also be used for initialisation.

1.47 term.guide/Rate_panel

Rate panel

'term' will count the minutes you are online and connected to a BBS as soon as a connection is made through the dialing routine. As soon as the connection is lost or you hang up, 'term' will use the information to be specified in this control panel to calculate the amount of money to be paid for the call.

Pay/unit

The amount of money to be paid for each single time unit when online. This fee must be given in the smallest currency unit available (pence, cents, centimes, etc.).

Seconds/unit

This is where you enter how many seconds each time unit lasts.

There are two different groups of the two entries listed above available: one for the first unit and one for all following units. So, if you only pay for the call you make but not for the time you spend making it, just enter the fee in the first group and set the second group to zero.

Days and dates

This list contains the default rate settings and exceptions for certain dates and days of the week. Each line displays the type of the entry and a comment (separated by the '>>' character). The following types are available:

Day(s)

Settings for certain days of the week

12. Jan (example)

Settings for a specific date

If there is no special type available for an entry, it's probably the default settings you are dealing with. These settings are used whenever 'term' cannot find an entry for the current day.

For each entry in this list there is at least one associated starting time available which defines when the associated rate settings are to be used. You will find the time settings in the list titled Time. To add a new time use the Add time button, to edit an existing entry, use the Edit time button. To remove an entry, press the Remove time button.

Add date

Will invoke a control panel to create a new rate entry to be used on a specific date. Use the sliders and button to select the day the settings will be valid for.

The control panel will allow you to enter nonexistant dates, such as '31. Feb' so you will have to make sure that the date in question really exists.

Add day(s)

Will create a new rate entry referring to one or more days of the week. Use the buttons of the control panel to select the days the current settings will be valid for.

Import

Much work can be saved if the rate settings for the current phonebook entry are imported (or copied) from a different phonebook entry. To do so, select this button. The control panel to be opened will display the list of phonebook entries available and three buttons:

Replace rates

The rate settings of the current phonebook entry will be replaced by the settings of the selected entry.

Append rates

The rate settings of the selected entry will be appended to the current phonebook entry.

Cancel

Will abort the selection.

Whenever a rate entry is selected, the corresponding parameters (Pay/unit and Seconds/unit) can be edited. If the entry refers to a certain date or a specific day of week three additional buttons are made available:

Edit

Just as the labels says, will allow you to modify an entry after it has been created.

Clone

Will duplicate the current rate entry and append it to the list.

Remove

Removes an entry from the list.

1.48 term.guide/Copy_panel

Copy panel

This control panel allows you to select which parts of the global configuration to copy into the currently selected phonebook entry.

All

Selects all parts.

Clear

Clears the current selection.

Copy to all

The selected parts will be copied to all phone book entries. If any phone book entries are selected when this action is to be performed, only the selected entries will be affected.

Copy

This is where you select from which source the configuration information will be copied:

Global configuration

Parts of the currently active global configuration will be copied.

Defaults

When going online, instead of overriding the currently active global configuration with the supplied local phone book configuration the corresponding global configuration will be left unchanged.

1.49 term.guide/Dial_panel

Dial panel

The following information about the dialing process is displayed:

Calling

The name of the telephone book entry belonging to the number being dialled. If it is just a telephone number the string - Unknown - is shown, meaning that the name of the mailbox is unknown.

Comment

This is where the comment corresponding to the current dialing list entry is displayed.

Number

The telephone number being dialed or just dialed.

Next

The name of the telephone book entry which will be processed next if no connection is established. If no further entry exists, - None - will be displayed.

Timeout

A counter which is decreased every second and which reflects the time remaining to establish a connection or to cycle through the dial queue again.

Attempt

This field shows the number of unsuccessful cycles made through the dialing queue to establish a connection.

Message

A message to the user. This can be:

Dialing...

A dial is in process.

Line is busy.

The dialed number is engaged.

Incoming call!

The modem has been called from another modem.

Incoming voice call!

The modem is receiving a call which was not originated by another modem.

No dialtone detected!

The modem was unable to detect any dialing tone on the line, it may possibly be not connected.

Connection established.

Just as the name says...

Maximum number of dial retries reached!

Just as the name says...

Dial attempt timeout.

The time available to establish a connection has been reached or exceeded.

Redial Delay...

Pause until the next cycle through the dialing queue.

Additionally three buttons can be found in the input field which initiate the following functions.

Skip call

With this function the current dialing attempt is cancelled and the next number is processed. If no succeeding telephone number exists 'term' waits for the next cycle through the dial queue or until Skip call is pressed again.

There also is a hotkey combination available to accomplish the same effect.

Remove

This button works in part similar to the Skip call button. Additionally, it removes the current phonebook entry from the dialing list.

Go to online

If the line is very noisy, the connection to a mailbox has been made but the CONNECT signal has been lost, you can use this button to switch directly to the online mode of the modem. This will also start the pay unit counter and the dial queue will be exited.

Abort dialing

Operation of this button exits the dial queue (leaving the the dial

queue intact) and ends the dialing process.

If a connection is successfully made the corresponding entry in the dial queue will be removed.

Selecting the close gadget will close the window and cause the phone book panel to be reopened.

1.50 term.guide/Printing_panel

Printing panel

This control panel is part of the phone book. It is opened whenever the Print button is selected and allows for setting the output options.

Output file or device

This is where you enter the name of the file or device (such as PRT:) the phonebook printout is to be sent to.

Plain text

If enabled only the plain and bare information text will be printed, else text attribute control sequences will be sent as well.

Include...

Each switch determines whether the corresponding phonebook entry information will be included in the printout.

Use

Will start printing the phonebook contents.

Cancel

Returns to the phonebook.

1.51 term.guide/Text_buffer

Text buffer

The text buffer is a function which continually stores text displayed on 'term's main screen, so that the user can inform himself about the received text at any time.

General characteristics	General information on the text buffer.
Operation	How to operate the text buffer?

1.52 term.guide/General_characteristics

General characteristics

The size of the text buffer is managed dynamically so that for every new line which is read new memory must be allocated. So the size of the text buffer is limited only by the amount of the available memory. It is recommended that the text buffer is emptied periodically to avoid using the entire free memory.

If there is insufficient memory to place a new line into the text buffer, the first line will be deleted to make room for the new line.

1.53 term.guide/Operation

Operation

The contents of the text buffer can be paged through using the keys for moving of the cursor (Shift + Cursor keys moves page by page, Control + Cursor key jumps to the beginning or end of the text buffer). Additionally, the numeric keypad keys are overlaid with jump and paging functions (corresponding to the inscriptions/graphics on the front of the keys).

Additionally there is another menu whose functions should be explained briefly:

Search

A search function is called which searches from the topmost line on the screen downwards for an entered search string. Upper- and lowercase are ignored by this function. If the search string is found it is displayed and highlighted.

Repeat search

Continues the search process started with Search. The previously entered search string is carried over.

Go to main screen

Switches to the main screen of 'term'.

Clear buffer

Clears the contents of the Text_buffer.

Close buffer, Quit

Closes the Text_buffer screen but leaves the contents unchanged.

1.54 term.guide/Clipboard

Clipboard

Cut & paste functions are available on the main screen, the buffer

screen and the review buffer. Here is how to use them:

Buffer screen

Use the mouse to point to the first character you wish to send to the clipboard, hold down the select button, drag the mouse to the last character you wish to copy and release the button. The text marked will be transferred to the clipboard.

Holding down the Control key while clicking on a character will feed the single character into the input stream, it will not be buffered in the clipboard.

Main screen

Use the mouse to point to the first character you wish to send to the clipboard, hold down the select button, drag the mouse to the last character you wish to select and release the button. Select the Copy menu item (see Edit menu) to transfer the text to the clipboard. Instead of dragging the mouse you may also double-click on a single word to select it.

Holding down the Control key while clicking on a character will feed the single character into the input stream, it will not be buffered in the clipboard.

Review buffer

Use the mouse to point to the first character you wish to send to the clipboard, hold down the select button, drag the mouse to the last character you wish to select and release the button. Press Amiga + C to copy the selected text to the clipboard.

To paste the clipboard contents, i.e. feed them into the terminal input stream, either select the Paste menu item (see Edit menu) or press Amiga + V. In order to send the clipboard contents along with a Paste prefix and Paste suffix hold down any Shift key when selecting the Paste menu entry or when selecting text with the mouse (this works both with the main screen and the Text_buffer screen).

Hold down one of the Alt keys and press the left mouse button to make 'term' emit a number of cursor move sequences which will position the on-screen cursor at the spot where you clicked the mouse.

In standard string editing gadgets a solution had to be found to preserve the line editing functions while still supporting menu shortcuts. To undo any changes made press Amiga + Q, to clear the string editing gadgets press Amiga + X. Menus associated with the shortcuts Amiga + Q/X are called by holding down any Shift key along with the Amiga keys (i.e. Shift + Amiga + Q will select the Quit menu item if available).

Clipboard functions are also available within string gadgets: press Amiga + C to copy the contents of the gadget to the clipboard and press Amiga + V to insert the current clipboard contents at the current cursor position.

1.55 term.guide/Command_sequences

Command sequences

Each string sent directly to the modem is a command sequence. This includes telephone numbers, modem initialisation strings, function key assignments, etc. In addition to the normal text strings various other commands are supported which will be described in the following section.

Backslash	The backslash \
Caret	The caret ^
Tilde	The tilde ~

1.56 term.guide/Backslash

Backslash

\
Generates a single backslash.

\0
Resets the text pacing mode (see Clipboard_panel) to the settings defaults. Any changes of the text pacing mode affect only the line to be sent. The next following line will be sent using the default text pacing mode.

\1
Sets the text pacing mode to Direct.

\2
Sets the text pacing mode to Wait for echo.

\3
Sets the text pacing mode to Wait for any echo.

\4
Sets the text pacing mode to Wait for line prompt.

\5
Sets the text pacing mode to Character/line delay.

\6
Sets the text pacing mode to Keyboard delay.

\a
Executes an ARexx command (all text to follow this character).

\b
Generates a backspace (deletes the character to the left of the cursor).

\c

Calls a main menu entry, the menu entry to be called is determined by the argument to follow; this is either a six digit number (example: \c 010203 would call subitem 1, item 2, menu 3) or the name of the menu entry enclosed in single quotes to call (example: \c 'about' would call the About... menu entry, the search is case-insensitive and only compares the characters given).

\d

Executes an AmigaDOS command (all text to follow this character).

\e

Generates the escape character (ASCII code 27).

\f

Generates a form feed (skip to beginning of the next page or clear the screen).

\g

Places the string to follow this character in the clipboard.

\h

Appends the string to follow this character to the current clipboard contents.

\i

Feeds the contents of the clipboard into the input stream.

\n

Generates a line feed.

\p

Feeds the password of the telephone book entry into the input stream of the last made connection. The password is automatically cleared for security reasons when the connection is broken.

\r

Generates a carriage return.

\t

Generates a tab jump.

\u

Similar to the \p command, the \u command will feed the current user name into the input stream.

\x

Generates a break signal (as with the Send break menu entry).

\^

Generates a caret character.

*

The code to follow the asterisk determines the character to produce. This can be any three digit number or a symbolic name from the following list (1):

NUL, SOH, STX, ETX, EOT, ENQ, ACK, BEL, BS, HT, LF, VT, FF, CR,

SO, SI, DLE, DC1, DC2, DC3, DC4, NAK, SYN, ETB, CAN, EM, SUB,
ESC, FS, GS, RS, US, SP, DEL, SS2, SS3, DCS, CSI, ST, OSC, PM, APC,
NBS and SHY

If none of the mentioned combinations is recognized the character which follows the \ will be fed into the input stream without any changes.

----- Footnotes -----

(1) EOU may be implemented in a future release

1.57 term.guide/Caret

Caret

This character is used to change the following character to a 'control character'. So the sequence ^J will become a Line feed and ^I becomes a tab jump. The character which follows the ^ has to be located between @ and [, otherwise it is fed into the input stream without changes.

1.58 term.guide/Tilde

Tilde

This character causes the program to pause for exactly half a second before it continues to process the following commands.

1.59 term.guide/Fast!_macros

Fast! macros

In implementation and design the fast! macros are closely related to the function key macros (see `Function_key_panel`). If invoked by selecting the corresponding menu entry, a window will open on the right hand side of the screen sporting a scrollable list of macros (the contents of this list can be edited using the `Fast_macro_panel`). When a list entry is selected, the associated command sequence (see `Command_sequences`) will be executed.

By using the fast! macros it is theoretically possible to control a BBS just by mouse, provided that you have the appropriate macros in your fast! macro list.

The fast! macro panel can be resized and acts just like the main 'term' window: menu items can be selected and characters entered are

sent to the serial driver.

1.60 term.guide/Packet_window

Packet window

In this window a line can be edited before it is sent. All the usual editing functions known from standard input fields are available (Shift + cursor left/right jumps to the start/end of the line).

Additionally, some extended functions exist which are performed by pressing a cursor key together with the Shift or Control key:

Control + Cursor left
Jumps to the next word.

Control + Cursor right
Jumps to the previous word.

Cursor up
Shows the last entered command in the input line.

Shift + Cursor up
Shows the very first command entered so far.

Cursor down
Shows the next entered command (if you moved back for some commands before).

Shift + Cursor down
Shows the very last command entered so far.

This string gadget has a buffer where all previously entered commands are stored ('Command history'). You can page through this buffer, load and save it and individual lines can be recalled. As with the Text_buffer this buffer is managed dynamically. The same memory restrictions that apply to the Text_buffer are valid for this buffer.

The input line also has a menu which offers the following functions:

Load history
Loads the contents of the input line buffer from a file. Each stored line in this file can be recalled and sent.

Save history as...
Saves the contents of the input line buffer to a file.

Clear history
Simply releases all previously stored commands and the memory used by them.

Other window
Switches to the main screen of 'term'.

Quit

Closes the window (corresponds to clicking the close gadget of the window).

Every character entered into this window is shown immediately so that those things where it is better that they should not appear on the screen (like passwords for a mailbox) should be entered in another way.

The content of every input line is interpreted as a command sequence and therefore can also contain control characters.

If a line taken from the input buffer is sent without change it is not stored in the buffer again ('true history' as known from 'ConMan').

The contents of the input buffer are cleared automatically after the window is closed. Under no circumstances are the contents maintained until the next call!

Provided that the packet window is large enough, a list to contain the command line history will be displayed.

1.61 term.guide/Environment_variables

Environment variables

Information which is to be available the next time the program is run is placed as AmigaDOS variables in the directory ENV: and ENVARC: by 'term'.

The variables used by 'term' can be used and manipulated by other programs transparently. In detail these variables are:

TERMCONFIGPATH

The name of the directory in which all information used by 'term' is placed (standard configuration, telephone book, etc.). The default settings file name is ENVARC:term.

TERMWINDOW

The window definition which can also be entered in the program via the menu item Settings.

xpr...

The standard settings used for the corresponding transfer protocol (xprzmodem, xprkermit, etc.).

xem...

The standard settings used for the corresponding external terminal emulation library (xemvt340, xemascii, etc.).

1.62 term.guide/Revision_history

Revision history

Changes introduced with v3.4:

- Raised the maximum number of quick dial menu entries to 50.
 - Fixed a small bug connected with the text display screen.
 - XPR protocols which do not support batch transfers now work again as they did in v2.4.
 - Corrected a spelling mistake in the call logfile creation routine.
 - Fixed a memory allocation error in the review buffer code.
 - Fixed a major bug in the file transfer routines. In previous releases (say 3.1 and above) 'term' used to throw invalid file locks around (seems I will have to use less ambiguous identifier names in the future...).
 - Fixed an Enforcer hit in the quick-dial menu creation.
 - Rarely, the program could fail to rebuild the quick-dial menu after leaving the phonebook.
 - As required by the specs, the XPR interface now switches baud rates and serial parameters.
 - Enhanced the capture functions.
 - Changed the user interface layout for some windows, such as the modem settings window.
 - When running on a public screen will no longer cause lockups and trouble with Workbench. Rendering errors are still possible.
 - The very first characters to follow a modem connect message are no longer quietly discarded.
 - Finally solved the truly mysterious case of the missing screen line.
 - Fixed yet another Enforcer hit in the packet window code.
 - The standard beep routine would not work.
 - Libraries and devices can now be selected using simple menus rather than the file requester.
 - The program now flushes capture files to disk every minute in order to insure that at least fragments of the captured session will be safe when disaster strikes.
 - Finally got the cross-hatch pattern to draw ghosted list views right.
-

- The terminal hex mode would write too many bytes per line.
 - The program would not pay attention to any icon tool type settings.
 - Upon making a connection the dialing routine will no longer drop the line by accident.
 - The review buffer window will filter out unprintable characters before displaying text lines.
 - The program no longer knocks itself out if an initialization error occurs during the startup phase.
 - You can now select the name of the public screen the 'term' window is to be opened upon using a menu.
 - If using a public screen the program will make use of the corresponding screen font and no longer try to modify it in any weird way.
 - The ARexx command READ did not pay attention to the translation table settings.
 - A configuration file to be loaded upon startup as specified using tooltypes or command line options will no longer be ignored.
 - The positions and sizes of certain program windows will be stored in the main configuration file.
 - Initially, when a file was received the information window would not display the space left on the output device.
 - Introduced the 'time to connect' interval.
 - Added the serial read quantum.
 - The phone book window will now be opened large enough to hold all its gadgets inside.
 - Blinking text display is no longer restricted to eight colour screens, provided the display architecture permits high-resolution screens in more than 4 bit planes.
 - The program now exists cleanly if vital resources such as the output screen cannot be opened.
 - The file transfer routines should run a tiny little bit faster now.
 - Added the transfer performance meter.
 - The clear screen control sequence now optionally resets the cursor position.
 - Rarely, the text buffer screen would not update the first text line properly. Also, the screen display mode will no longer fall
-

back to HIRES/HIRES_INTERLACED.

- Rarely, the review buffer window would render text in the wrong colours.
 - The pen/palette sharing code was submitting incorrect colour codes.
 - The review buffer window now responds to the same keypresses as the text buffer screen and the main input window.
 - Not all packet menu items were to be invoked using menu shortcuts.
 - Added 'Completion time' display to the transfer progress window.
 - Introduced special transfer library settings. You can now select which library to use for ASCII, text or binary transfers.
 - Added built-in ASCII transfer routines.
 - You can now search forwards or backwards through the text buffer.
 - Text stored in the buffer no longer gets trailing spaces stripped in order to keep weird uuencoded data intact.
 - The menu items featured in the 'Edit' menu now properly reflect the state of the clipboard.
 - A menu shortcut would be used twice in the main window menus.
 - Rarely, the colour choices for the bar charts in the transfer progress window would be wrong.
 - The quick dial menu would not be rebuilt if the phonebook was sorted or new entries were added.
 - The ARexx commands DELAY and SEND would not turn off the text cursor prior to text processing.
 - Unless it is absolutely necessary, the text display scope is no longer moved automatically.
 - As for the text display screen and window the 'Alt' keys now have the same effect as the 'Control' key.
 - If new text is added to the text buffer the buffer screen and the review window are properly updated now.
 - A dialing list built using the quick dial menu was not enumerated properly.
 - Building a dialing list using the quick dial menu via extended selection, then selecting the phonebook control panel, clearing the dialing list and leaving the phonebook will no longer start dialing the list just cleared.
 - Checkmarks now indicate which entries in the quick dial menu are
-

to be dialed.

- The bar charts displayed in the transfer progress window are now updated in a more efficient manner (the text colour has changed, too). Also, unzooming the window will properly update the bar charts now.
- A hardware buffer overrun error is no longer considered a fatal error.
- With some requesters and windows string gadgets are auto-activated now. Pressing the Return key will cycle through all the available strings gadgets, holding down either Shift key will break the cycle.
- Trying to quit the program will no longer ask for confirmation if there is no reasons to ask for.
- The bar charts in the transfer progress window will be omitted if the remaining screen space would not permit the entire window to be displayed.
- The fast! macro window contents would be rendered in the wrong colours.
- The phonebook window did not support any online-help features.

Changes introduced with v3.3:

- Added the quick dialing menu.
 - Enhanced the modem and screen settings
 - Fixed a few bugs in the ARexx interface commands REQUESTFILE and REQUESTRESPONSE
 - Unfortunately a single line was missing in the XPR option setup, causing them program not to save the transfer protocol options.
 - No longer forces the creation date of an auto-capture file to be included in the file. As an option, will use the naming convention used in previous program releases.
 - The program now optionally creates icons for files.
 - Added a terminal hex-mode for debugging purposes
 - Fonts are now opened using properly initialized DPI and aspect ratio values which results in much better scaled outline font rendering.
 - The name of an external emulation library is no longer quietly suppressed.
 - It is possible to disable the double-buffered file management routines now.
-

- Added the text pacing option.
- Apparently, external and internal terminal emulations tried to turn on/off each other's cursors.
- Copying text to the clipboard now permits to append the text to the current clipboard contents.

Changes introduced with v3.2:

- Could not enter phonebook passwords
 - The XPR interface now states much more clearly what the likely cause of a serial I/O error might have been
 - New sound support functions added
 - Added 'OK' and 'ERROR' modem response codes
 - The order of messages displayed in the file transfer window has changed (now works top down rather than bottom up).
 - The ARexx interface routines did not check whether the serial device handles were available or not (boom!)
 - Redid the fast! macro handling
 - The text buffer screen did not notice when the buffer contents were cleared
 - Retuned the phone book and dial list routines which could generate Enforcer hits and trash innocent memory
 - Boldface/italics characters will no longer leak into the window borders
 - The cursor image now reflects the state of the terminal window
 - The program would generate an Enforcer hit when files were to be transferred by dropping their icons on the main window
 - When opening a capture file the program could ask twice whether an already existing file should be replaced.
 - Paste operations triggered from the review buffer window would not start any paste operation until the main window was reselected
 - Reworked the character translation table format. Translation table files should be smaller now and should load a lot faster
 - The screen/output window size now changes to the number of columns specified in the terminal settings
 - Rarely, the file transfer window would be opened very narrow and tall. So tall in fact that display elements would overlap each other, no text could be displayed in the big listview and Enforcer hits were not to be avoided.
-

- The file transfer interface would produce Enforcer hits when to transfer files using an old-style XPR library.
- The phonebook dial list handling would select single entries when a shift key was pressed during keyboard selection.
- The review buffer window no longer loses track of the text area it ought to display after resizing the window.
- Rewrote much of the keyboard/mouse/peanut butter handling loop. No longer quite so complex.
- Thanks to user persistence the 'Password' text entry field available through the password/user panel no longer hides the actual password text.
- 'Hang up' menu item did not cause a backed-up configuration to be restored.
- Naughty XPR protocols which would issue error reports through `xpr_update()` during `XPRSetup()` would cause the transfer window to be opened not to close afterwards.
- No more odd happenings in the status line online time display. The code responsible would misinterpret a string index. This has been fixed.
- It is no longer possible to dial phone book entries which have no name or phone number attached.
- The terminal emulation code no longer leaves background colour artifacts when scrolling text with a background colour other than the default background colour enabled.
- Calls to `BeginIO()` rather than `SendIO()` were giving some - if not most - device drivers hard times. According to the few tests I have run so far the program now performs more reliable when doing file transfers. 'term' now works again in conjunction with `isdn.device`.
- The program no longer encodes the creation date into the name of an auto-capture file but rather writes creation time and date to the first new line in the file.
- New tooltype/command line option 'Quiet' will cause 'term' to start up iconified.

Changes introduced with v3.1:

- Previous releases of the phone book would not clone single phone book entries correctly.
 - The configuration copying routine will now selectively copy config information to the currently selected phone book entries.
 - The phone book encryption/decryption routines are a tad faster
-

now.

- The program will now prompt twice for a phone book access password.
 - Comment, phone number, user name and password can be much longer now than they used to be in previous releases.
 - The phone book now only contains the configuration information to differ from the global configuration.
 - Previous releases would not save any rate information along with encrypted phone book files, this has been fixed.
 - The configuration copying routine now allows to 'drop' parts of the phone book configuration rather than replacing them with parts of the global configuration. This feature works in conjunction with the new phone book file format.
 - A new feature has been added: as an option, the program will immediately start to redial the currently configured dialing list as soon as the line is hung up or the carrier is lost.
 - The program finally includes context-sensitive online help implemented through amigaguide.library (note: Kickstart 3.0 required). Any window to offer a help text will display it when the 'Help' key is pressed.
 - The ARexx interface documentation was entirely rewritten. The main program documentation was updated and slightly enhanced. Be sure to reread it!
 - Both the text buffer screen and review buffer window now feature new and improved scrollers. Scrolling and screen refreshes are also quite a bit faster now.
 - The text searching routine has been enhanced and now works much faster than in previous releases. It also happens to find multiple occurrences of a string in a single line.
 - Improved text buffer handling, reduced memory fragmentation if running under control of Kickstart 3.0.
 - The text buffer will no longer quietly swallow single characters and will finally correctly wrap lines longer than 80 characters.
 - The review buffer window now also sports a search function just like the text buffer screen, other useful menu items have been added as well.
 - In previous releases the program would miscalculate the number of bytes left on a filing device when receiving a file. It would not take the number of bytes received into account, this has been fixed.
 - In order to transfer files one can simply drag the corresponding icons on the 'term' main window (requires that the 'term' window
-

is opened on the Workbench screen).

- Instead of identifying the type of a file received, the program will optionally attach a file comment to show the name of the BBS the file was received from and the time and date when the file was received.
 - In case a file transfer is terminated due to errors the file transfer window will remain open until explicitly closed.
 - The XPR interface will disable the `xpr_unlink()` routine if the 'override transfer path' option is in effect.
 - The XPR interface will no longer sort files to be uploaded by size and name as most users found this feature annoying. It now sorts the files by name.
 - The file transfer window now correctly displays the names of all files sent and received.
 - The file transfer server was removed as it would not lead to a performance gain but a performance loss.
 - 'term' now finally also runs as a window on the Workbench or any other public screen (that's what you always wanted, right?). If running under control of Kickstart 3.0 will attempt to share screen colours with other applications, making it possible to run the terminal emulation in eight or sixteen colours if enough shareable pens are available.
 - 'term' will refuse to run on a public screen if running under control of Kickstart 2.x and if the screen font happens to be proportional-spaced.
 - Some minor and some major bugs in the built-in terminal emulation have been fixed.
 - The program distribution now includes the 11 point IBM.font donated by Bernhard F. Muller.
 - I was surprised to discover that in previous releases the terminal emulation server would never get activated as the conditions it would be enabled would very rarely be met. Since the file transfer server would actually lead to a performance loss rather than a performance gain I chose to remove the terminal server along with it. Both may be implemented in a future release.
 - The terminal emulation should work a tad faster now.
 - The program now requires `diskfont.library` to be installed in order to work correctly.
 - The program will ask for a confirmation prior to resetting the serial device driver while the program is still online. Most seasoned JR-Comm had trouble to adjust to the fact that the JR-Comm command 'send password' would use the same menu shortcut as the 'term' 'release serial device' command.
-

- The name of the call log file can now be configured completely. Previous releases would use the call file path and use the name 'term-call.log'.
- The status window now displays the name of the ARexx host port, the BBS name, phone number, comment and current user name.
- In order to confuse and annoy you, the menu layout has been changed once again.
- A new feature has been added: the 'wait' menu item will repeatedly send the sequence <Space><Backspace> in order to simulate terminal input.
- The program now requires a bit more memory than before (program size has climbed by about 50 KBytes).
- New command line options and tool types have been added, some have been renamed.
- The program is now much smarter in determining the sizes of the phone book and file transfer window.
- The lists used by the phone book and the date panel no longer look quite so weird if using a proportional-spaced font.
- The main screen text snipping scheme has changed a bit and now resembles the standard console device snipping. Also supported is double-clicking on single words in order to snip them.
- The ARexx interface has been entirely rewritten from scratch.

1.63 term.guide/Index

Index

	Path_panel	
...Downloadpath		Path_panel
...Uploadpath		Path_panel
12. Jan (example)		Rate_panel
16 Colours (EGA)		Screen_panel
2 Colours (Monochrome)		Screen_panel
4 Colours (Amiga)		Screen_panel
8 Colours (ANSI)		Screen_panel
Abort ARexx command		Hotkey_panel
Abort dialing		Dial_panel
Abort entire transfer		ASCII-transfer_panel
About		Project
Add date		Rate_panel
Add day(s)		Rate_panel
Alert		Terminal_panel

All	Copy_panel
Answerback message	Emulation_panel
Append rates	Rate_panel
Archive file	Miscellaneous_panel
ARexx port name	Windows
As CR	Terminal_panel
As CR+LF	Terminal_panel
As LF	Terminal_panel
As LF+CR	Terminal_panel
ASCII download library	Transfer_panel
ASCII upload library	Transfer_panel
Attempt	Dial_panel
Audible	Terminal_panel
Backup configuration	Miscellaneous_panel
Baud rate	Screen
Baud rate	Serial_panel
BBS comment	Windows
BBS name	Phonebook
BBS name	Windows
BBS phone number	Windows
BBS user name	Windows
Bell	Terminal_panel
Bell	Terminal_panel
Bell/Screen	Terminal_panel
Binary download library	Transfer_panel
Binary upload library	Transfer_panel
Bits/char	Serial_panel
Black line	Miscellaneous_panel
Blinking	Screen_panel
Block check type	Transfer_progress_panel
Block size	Transfer_progress_panel
Blocks transferred	Transfer_progress_panel
Blue line	Miscellaneous_panel
Break length	Serial_panel
Buffer line width	Capture_panel
Buffer screen	Clipboard
Buffer screen position	Capture_panel
Buffer screen to front	Hotkey_panel
Buffer size	Serial_panel
Buffer size (bytes)	Windows
Bytes received	Windows
Bytes sent	Windows
Bytes transferred	Transfer_progress_panel
Bytes transferred	ASCII-transfer_panel
Call log file	Capture_panel
Calling	Dial_panel
Cancel	Emulation_panel
Cancel	Modem_panel
Cancel	Clipboard_panel
Cancel	Terminal_panel
Cancel	Serial_panel
Cancel	Screen_panel
Cancel	Printing_panel
Cancel	Function_key_panel
Cancel	Capture_panel
Cancel	Miscellaneous_panel
Cancel	Command_panel

Cancel	Path_panel
Cancel	Sound_panel
Cancel	Speech_panel
Cancel	Transfer_panel
Cancel	Hotkey_panel
Cancel	Cursor_key_panel
Cancel	Rate_panel
Capture	Phonebook
Capture file path	Capture_panel
Capture filter enabled	Capture_panel
Capture to File/Printer	Project
Capture...	Settings
Centre	Capture_panel
Character delay	ASCII-transfer_panel
Character delay	Clipboard_panel
Character delay	Transfer_progress_panel
Character/line delay	ASCII-transfer_panel
Character/line delay	Clipboard_panel
Characters/second	Transfer_progress_panel
Check carrier	Serial_panel
Clear	Copy_panel
Clear	Edit
Clear buffer	Buffer
Clear buffer	Operation
Clear history	Packet_window
Clear list	Phonebook
Clear screen	Terminal
Clipboard	Phonebook
Clipboard unit	Clipboard_panel
Clipboard...	Settings
Clone	Rate_panel
Clone entry	Phonebook
Close buffer	Buffer
Close buffer, Quit	Operation
Colour	Screen_panel
Columns	Terminal_panel
Commands	Phonebook
Commands...	Settings
Comment	Dial_panel
Comment	Phonebook
Commodity priority	Hotkey_panel
Compact	Screen_panel
Completion time	Transfer_progress_panel
Configuration storage directory	Path_panel
Connect auto-baud	Modem_panel
Connect limit	Modem_panel
Connect-auto-capture	Capture_panel
Connection established.	Dial_panel
Connection message	Windows
Console window...	Settings
Control + Cursor left	Packet_window
Control + Cursor right	Packet_window
Copy	Edit
Copy	Copy_panel
Copy config	Phonebook
Copy to all	Copy_panel
Create icons	Miscellaneous_panel

Creation date	Capture_panel
Cursor down	Packet_window
Cursor keys	Emulation_panel
Cursor keys	Phonebook
Cursor up	Packet_window
Day(s)	Rate_panel
Days and dates	Rate_panel
Default (phone book only)	Emulation_panel
Default (phone book only)	Capture_panel
Default (phone book only)	Modem_panel
Default (phone book only)	Serial_panel
Default (phone book only)	Command_panel
Default (phone book only)	Path_panel
Default (phone book only)	Transfer_panel
Default (phone book only)	Clipboard_panel
Default (phone book only)	Terminal_panel
Default (phone book only)	Miscellaneous_panel
Default (phone book only)	Screen_panel
Default transfer library	Transfer_panel
Defaults	Copy_panel
Delete	Fast_macro_panel
Destructive backspace	Emulation_panel
DEVICE	Workbench_and_Shell
Device unit number	Serial_panel
Dial	Phone
Dial attempt timeout.	Dial_panel
Dial list	Phonebook
Dial prefix	Modem_panel
Dial suffix	Modem_panel
Dial timeout	Modem_panel
Dialing...	Dial_panel
Direct	ASCII-transfer_panel
Direct	Clipboard_panel
Disabled	Screen_panel
Display buffer	Buffer
Display modes	Screen_panel
Down	Fast_macro_panel
Download ASCII file(s)	Transfer
Download binary file(s)	Transfer
Download macro	Command_panel
Download text file(s)	Transfer
Drop DTR on hangup	Modem_panel
Duplex	Serial_panel
Edit	Rate_panel
Edit & upload text file	Transfer
Elapsed time	Transfer_progress_panel
Emulation	Phonebook
Emulation	Screen
Emulation	Terminal_panel
Emulation name	Terminal_panel
Emulation...	Settings
End	Fast_macro_panel
End	Capture_panel
End	Capture_panel
Execute AmigaDOS command	Commands
Execute ARexx command	Commands
Expected time	Transfer_progress_panel

Fast! macros	Windows
Fast! macros	Phonebook
Fast! macros...	Settings
Faster layout	Screen_panel
File	Transfer_progress_panel
File comment	Miscellaneous_panel
File size	Transfer_progress_panel
File type	Miscellaneous_panel
Files transferred	Transfer_progress_panel
Flush receive buffer	Phone
Font	Terminal_panel
Font	Screen
Font scale	Emulation_panel
Free memory (bytes)	Windows
Freeze buffer	Buffer
Frequency	Speech_panel
Function keys	Phonebook
Function keys...	Settings
Global configuration	Copy_panel
Go to main screen	Operation
Go to online	Dial_panel
Half width	Emulation_panel
Handshaking	Serial_panel
Hang up	Phone
Hangup command	Modem_panel
High-speed mode	Serial_panel
Hotkeys enabled	Hotkey_panel
Hotkeys...	Settings
IBM-PC style	Terminal_panel
IBM-PC style (raw)	Terminal_panel
Iconify	Project
Ignore	Terminal_panel
Ignore	Terminal_panel
Ignore	Miscellaneous_panel
Ignore	Terminal_panel
Import	Rate_panel
Include...	Printing_panel
Incoming call!	Dial_panel
Incoming voice call!	Dial_panel
Information	ASCII-transfer_panel
Information	Transfer_progress_panel
Insert mode	Emulation_panel
ISO-10-(S).prefs	Translation_panel
ISO-11-(S).prefs	Translation_panel
ISO-15-(I).prefs	Translation_panel
ISO-16-(P).prefs	Translation_panel
ISO-17-(E).prefs	Translation_panel
ISO-21-(D).prefs	Translation_panel
ISO-4-(GB).prefs	Translation_panel
ISO-60-(N).prefs	Translation_panel
ISO-61-(N).prefs	Translation_panel
ISO-69-(F).prefs	Translation_panel
Keyboard delay	ASCII-transfer_panel
Keyboard delay	Clipboard_panel
Keymap file	Terminal_panel
Left	Capture_panel
Limit macro	Modem_panel

Line delay	ASCII-transfer_panel
Line delay	Clipboard_panel
Line is busy.	Dial_panel
Line prompt	Clipboard_panel
Lines	Terminal_panel
Lines transferred	ASCII-transfer_panel
Load	Speech_panel
Load	Fast_macro_panel
Load	Sound_panel
Load	Cursor_key_panel
Load	Function_key_panel
Load	Hotkey_panel
Load history	Packet_window
Load list	Phonebook
Log actions	Capture_panel
Log calls	Capture_panel
Log file	Capture_panel
Logoff macro	Command_panel
Macro	Fast_macro_panel
Macro code	Fast_macro_panel
Macro list	Fast_macro_panel
Main screen	Clipboard
Make screen public	Screen_panel
Maximum number of dial retries reached!	Dial_panel
Maximum text buffer size	Capture_panel
Message	Transfer_progress_panel
Message	Dial_panel
Misc	Phonebook
Miscellaneous...	Settings
Modem	Phonebook
Modem exit command	Modem_panel
Modem init command	Modem_panel
Modem 'ring' sound	Sound_panel
Modem 'voice' sound	Sound_panel
Modem...	Settings
Modifier	Function_key_panel
Modifier	Cursor_key_panel
Name list	Phonebook
New	Fast_macro_panel
NEW (Shell only)	Workbench_and_Shell
New entry	Phonebook
New-line mode	Emulation_panel
Next	Dial_panel
Next file	Transfer_progress_panel
No dialtone detected!	Dial_panel
None	Terminal_panel
Normal	Emulation_panel
Number	Dial_panel
Number of dial retries	Modem_panel
Number of errors	Transfer_progress_panel
Number of timeouts	Transfer_progress_panel
Numeric keypad	Emulation_panel
Online	Screen
Online cost	Screen_panel
Online display	Screen_panel
Online time	Screen_panel
Open buffer screen	Capture_panel

Open buffer window	Capture_panel
Open buffer...	Buffer
Other file types	Miscellaneous_panel
Other window	Packet_window
Output file or device	Printing_panel
Override transfer path	Miscellaneous_panel
Packet	Windows
Packet delay	Transfer_progress_panel
Packet type	Transfer_progress_panel
Palette	Screen_panel
Parameters	Screen
Parity	Serial_panel
Pass ^S/^Q through	Serial_panel
Password	Phonebook
Paste	Edit
Paste prefix	Clipboard_panel
Paste suffix	Clipboard_panel
Paths	Phonebook
Paths...	Settings
Pay/unit	Rate_panel
PC-8.prefs	Translation_panel
Phone number	Phonebook
Phonebook	Phone
Picture file	Miscellaneous_panel
Pitch	Speech_panel
Plain text	Printing_panel
PORTNAME	Workbench_and_Shell
Preferences file	Miscellaneous_panel
Preload sound files	Sound_panel
Print	Phonebook
Print Screen/Clipboard	Project
Printer control enabled	Emulation_panel
Program priority	Miscellaneous_panel
Protocol	Transfer_progress_panel
Protocol	Screen
Public screen name	Screen_panel
PUBSCREEN	Workbench_and_Shell
Quantum	Serial_panel
Quick menu	Phonebook
QUIET	Workbench_and_Shell
Quiet ASCII transfer	Transfer_panel
Quiet ASCII transfer	ASCII-transfer_panel
Quit	Project
Quit	Packet_window
Rate	Speech_panel
Rates	Phonebook
Receive CR	Terminal_panel
Receive LF	Terminal_panel
Red/Green/Blue	Screen_panel
Redial	Phone
Redial after hanging up	Modem_panel
Redial delay	Modem_panel
Redial Delay...	Dial_panel
Release serial device	Phone
Release serial device when iconified	Miscellaneous_panel
Remember	Capture_panel
Remember screen position	Capture_panel

Remember window position	Capture_panel
Remove	Dial_panel
Remove	Rate_panel
Remove entry	Phonebook
Repeat search	Operation
Replace rates	Rate_panel
Reset font	Terminal
Reset styles	Terminal
Reset terminal	Terminal
Review	Windows
Review buffer	Clipboard
Right	Capture_panel
Save	Sound_panel
Save	Hotkey_panel
Save	Cursor_key_panel
Save	Fast_macro_panel
Save	Function_key_panel
Save	Speech_panel
Save buffer as...	Buffer
Save history as...	Packet_window
Save list	Phonebook
Save screen as Picture/Text	Project
Screen	Phonebook
Screen	Terminal_panel
Screen font	Screen_panel
Screen size	Windows
Screen title	Screen_panel
Screen...	Settings
Scrolling	Emulation_panel
Search	Operation
Seconds/unit	Rate_panel
Select new screen font	Screen_panel
Select new text font	Terminal_panel
Send break	Phone
Send CR	Terminal_panel
Send LF	Terminal_panel
Send timeout	Clipboard_panel
Serial	Phonebook
Serial device	Serial_panel
Serial...	Settings
Session start	Windows
Set 'archived' bit	Miscellaneous_panel
SETTINGS	Workbench_and_Shell
Settings	Phonebook
Sex	Speech_panel
Shared access	Serial_panel
Shift + Cursor down	Packet_window
Shift + Cursor up	Packet_window
Show fast! macros	Miscellaneous_panel
Simple file I/O	Miscellaneous_panel
Skip call	Dial_panel
Skip current file	ASCII-transfer_panel
Skip dial entry	Hotkey_panel
Sort list	Phonebook
Sound file	Miscellaneous_panel
Sound...	Settings
Source and time	Miscellaneous_panel

Space left	Transfer_progress_panel
Speak!	Speech_panel
Speech enabled	Speech_panel
Speech...	Settings
Standard	Screen_panel
Standard	Terminal_panel
STARTUP	Workbench_and_Shell
Startup/Login macro	Command_panel
Status	Screen
Status	Windows
Status line	Screen_panel
Stop bits	Serial_panel
Strip bit 8	Serial_panel
Swap 'Backspace' and 'Del' keys	Emulation_panel
SYNC (Shell only)	Workbench_and_Shell
System default	Terminal_panel
term screen to front	Hotkey_panel
term.doc	Documentation_and_online_help
term.dvi	Documentation_and_online_help
term.guide	Documentation_and_online_help
term.ps	Documentation_and_online_help
TERMCONFIGPATH	Environment_variables
Terminal	Phonebook
Terminal bell sound	Sound_panel
Terminal...	Settings
termRexx.doc	Documentation_and_online_help
termRexx.dvi	Documentation_and_online_help
termRexx.guide	Documentation_and_online_help
termRexx.ps	Documentation_and_online_help
TERMWINDOW	Environment_variables
Text buffer enabled	Capture_panel
Text buffer file path	Capture_panel
Text download library	Transfer_panel
Text editor	Path_panel
Text file	Miscellaneous_panel
Text font	Terminal_panel
Text pacing	ASCII-transfer_panel
Text pacing	Clipboard_panel
Text upload library	Transfer_panel
Time	Screen
Time & cost	Screen_panel
Time to connect	Modem_panel
Timeout	Dial_panel
Tool	Miscellaneous_panel
Top	Fast_macro_panel
Top	Capture_panel
Top	Capture_panel
Total bytes transferred	Transfer_progress_panel
Total size	Transfer_progress_panel
Transfer	Phonebook
Transfer file icons	Miscellaneous_panel
Transfer performance meter	Miscellaneous_panel
Transfer protocol...	Settings
Transfer...	Settings
Translation tables...	Settings
Translations	Phonebook
UNIT	Workbench_and_Shell

Up	Fast_macro_panel
Upload ASCII file(s)	Transfer
Upload binary file(s)	Transfer
Upload macro	Command_panel
Upload text file(s)	Transfer
Use	Emulation_panel
Use	Command_panel
Use	Miscellaneous_panel
Use	Path_panel
Use	Capture_panel
Use	Terminal_panel
Use	Clipboard_panel
Use	Modem_panel
Use	Printing_panel
Use	Sound_panel
Use	Transfer_panel
Use	Function_key_panel
Use	Cursor_key_panel
Use	Speech_panel
Use	Hotkey_panel
Use	Serial_panel
Use	Screen_panel
Use auto upload panel	Miscellaneous_panel
Use built-in download routine	Transfer_panel
Use built-in upload routine	Transfer_panel
Use default colours	Screen_panel
Use entry	Phonebook
Use public screen	Screen_panel
User/Password	Phonebook
Visual	Terminal_panel
Visual & audible	Terminal_panel
Volume	Speech_panel
Wait for any echo	ASCII-transfer_panel
Wait for any echo	Clipboard_panel
Wait for echo	Clipboard_panel
Wait for echo	ASCII-transfer_panel
Wait for line prompt	ASCII-transfer_panel
Wait for line prompt	Clipboard_panel
Wait...	Phone
White line	Miscellaneous_panel
WINDOW	Workbench_and_Shell
Wrap characters	Emulation_panel
Wrap cursor moves	Emulation_panel
xem...	Environment_variables
xON/xOFF	Serial_panel
xpr...	Environment_variables
xprascii.doc ... xprzmodem.doc	Documentation_and_online_help
*	Backslash
\0	Backslash
\1	Backslash
\2	Backslash
\3	Backslash
\4	Backslash
\5	Backslash
\6	Backslash
\a	Backslash
\b	Backslash

\c	Backslash
\d	Backslash
\e	Backslash
\f	Backslash
\g	Backslash
\h	Backslash
\i	Backslash
\n	Backslash
\p	Backslash
\r	Backslash
\t	Backslash
\u	Backslash
\x	Backslash
\\	Backslash
\^	Backslash
'Busy' message	Modem_panel
'CLS' resets cursor position	Emulation_panel
'Connect' message	Modem_panel
'Connect' sound	Sound_panel
'Disconnect' sound	Sound_panel
'Error' message	Modem_panel
'File transfer failed' sound	Sound_panel
'File transfer finished' sound	Sound_panel
'NO CARRIER' = 'BUSY'	Modem_panel
'No carrier' message	Modem_panel
'No dialtone' message	Modem_panel
'Ok' message	Modem_panel
'Ring' message	Modem_panel
'Shanghai' windows	Screen_panel
'Voice' message	Modem_panel
