

**AEMail**

**COLLABORATORS**

	<i>TITLE :</i> AEMail		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		October 9, 2022	

**REVISION HISTORY**

NUMBER	DATE	DESCRIPTION	NAME

# Contents

<b>1</b>	<b>AEMail</b>	<b>1</b>
1.1	AEMail.guide . . . . .	1
1.2	COPYRIGHTS . . . . .	2
1.3	PROGRAM PURPOSE . . . . .	2
1.4	SYSTEM REQUIREMENTS . . . . .	3
1.5	RESTRICTIONS . . . . .	3
1.6	REGISTRATION . . . . .	5
1.7	INSTALLATION . . . . .	7
1.8	TIME ZONES . . . . .	13
1.9	CONFIGURATION . . . . .	16
1.10	CONFIGURATION: Tool Types . . . . .	20
1.11	CONFIGURATION: Tool Types/INTERLACE= . . . . .	21
1.12	CONFIGURATION: Tool Types/MAIL_DIR= . . . . .	22
1.13	CONFIGURATION: Tool Types/CONFIG= . . . . .	22
1.14	CONFIGURATION: Tool Types/MAILCAP_DIR . . . . .	22
1.15	CONFIGURATION: Tool Types/USERID . . . . .	23
1.16	CONFIGURATION: Tool Types/PASSWRD= . . . . .	23
1.17	CONFIGURATION: Tool Types/PASSPROTECT= . . . . .	23
1.18	CONFIGURATION: Tool Types/DOMAIN= . . . . .	24
1.19	CONFIGURATION: Tool Types/FROM= . . . . .	24
1.20	CONFIGURATION: Tool Types/REALNAME= . . . . .	24
1.21	CONFIGURATION: Tool Types/REPLYTO= . . . . .	25
1.22	CONFIGURATION: Tool Types/ORGANIZATION= . . . . .	25
1.23	CONFIGURATION: Tool Types/POP_SERVER= . . . . .	26
1.24	CONFIGURATION: Tool Types/SMTP_SERVER= . . . . .	26
1.25	CONFIGURATION: Tool Types/EDITOR= . . . . .	26
1.26	CONFIGURATION: Tool Types/TCPLLOG= . . . . .	27
1.27	CONFIGURATION: Tool Types/DELETEMAIL= . . . . .	28
1.28	CONFIGURATION: Tool Types/FULLHEADER . . . . .	29
1.29	CONFIGURATION: Tool Types/STRIPDUPS . . . . .	29

---

---

1.30 CONFIGURATION: Tool Types/HDRINREPLY . . . . .	30
1.31 CONFIGURATION: Tool Types/STARTNET . . . . .	30
1.32 CONFIGURATION: Tool Types/STOPNET . . . . .	31
1.33 CONFIGURATION: Tool Types/AUTOCONNECT . . . . .	33
1.34 CONFIGURATION: Tool Types/FLDRFONT & FLDRFONTSZ . . . . .	33
1.35 CONFIGURATION: Configuration Screen . . . . .	34
1.36 CONFIGURATION: Configuration Screen/Identity Page . . . . .	36
1.37 CONFIGURATION: Configuration Screen/TCP/IP Page . . . . .	38
1.38 CONFIGURATION: Configuration Screen/Path Page . . . . .	41
1.39 CONFIGURATION: Configuration Screen/General Parameters Page . . . . .	44
1.40 STARTING AEMAIL . . . . .	48
1.41 MAIN AEMAIL SCREEN . . . . .	54
1.42 INVOKING AEMAIL FROM THE SHELL . . . . .	56
1.43 USING AEMAIL AS MAILTO AGENT . . . . .	58
1.44 EDITING STRING ENTRY GADGETS . . . . .	59
1.45 USING THE CLIPBOARD WITH AEMAIL . . . . .	61
1.46 FILTERING MESSAGES WITH AEMAIL . . . . .	64
1.47 COMMAND ICON TOOL BAR . . . . .	65
1.48 COMMAND ICON TOOL BAR/Display Folder List . . . . .	66
1.49 COMMAND ICON TOOL BAR/Display Address Book . . . . .	66
1.50 COMMAND ICON TOOL BAR/Display Previous Message . . . . .	67
1.51 COMMAND ICON TOOL BAR/Display Folder's Message List . . . . .	68
1.52 COMMAND ICON TOOL BAR/Display Next Message . . . . .	68
1.53 COMMAND ICON TOOL BAR/Save (Export) Message to File . . . . .	68
1.54 COMMAND ICON TOOL BAR/Print . . . . .	70
1.55 COMMAND ICON TOOL BAR/Delete/Undelete Messages . . . . .	72
1.56 COMMAND ICON STRIP/Compose a Message . . . . .	72
1.57 COMMAND ICON TOOL BAR/Send Message Immediately . . . . .	74
1.58 COMMAND ICON TOOL BAR/Queue Message for Later Deliverly . . . . .	75
1.59 COMMAND ICON TOOL BAR/Retrieve Messages . . . . .	76
1.60 COMMAND ICON TOOL BAR/Retrieve Messages (From Files) . . . . .	79
1.61 COMMAND ICON TOOL BAR/Start/Terminate Network Connection . . . . .	80
1.62 COMMAND ICON TOOL BAR/Copy Messages . . . . .	81
1.63 COMMAND ICON TOOL BAR/Transfer Messages . . . . .	81
1.64 AEMAIL MENUS . . . . .	82
1.65 AEMAIL MENUS/Project menu . . . . .	82
1.66 AEMAIL MENUS/Project menu/CONFIGURATION... . . . .	83
1.67 AEMAIL MENUS/Project menu/SEND QUEUED MAIL . . . . .	84
1.68 AEMAIL MENUS/Project menu/ICONIFY AEMAIL . . . . .	84

---

---

1.69	AEMAIL MENUS/Project menu/ABOUT . . . . .	85
1.70	AEMAIL MENUS/Project menu/QUIT . . . . .	85
1.71	AEMAIL MENUS/Folders menu . . . . .	87
1.72	AEMAIL MENUS/Folders menu/FOLDER MAINTENANCE . . . . .	87
1.73	AEMAIL MENUS/Folders menu/SET SORT KEY . . . . .	88
1.74	AEMAIL MENUS/Folders menu/Remove DELETED msgs . . . . .	88
1.75	AEMAIL MENUS/Messages menu . . . . .	88
1.76	AEMAIL MENUS/Messages menu/SHOW . . . . .	89
1.77	AEMAIL MENUS/Messages menu/COMPOSE... . . . .	90
1.78	AEMAIL MENUS/Messages menu/SELECT... . . . .	91
1.79	AEMAIL MENUS/Messages menu/COPY . . . . .	92
1.80	AEMAIL MENUS/Messages menu/TRANSFER . . . . .	92
1.81	AEMAIL MENUS/Messages menu/DISPLAY FULL HEADER . . . . .	93
1.82	AEMAIL MENUS/Messages menu/INCL HDR IN RESP . . . . .	94
1.83	AEMAIL MENUS/Retrieve Msgs menu . . . . .	94
1.84	AEMAIL MENUS/Retrieve Msgs menu/FROM ... . . . .	94
1.85	AEMAIL MENUS/Retrieve Msgs menu/CHECKMARKED ITEMS . . . . .	95
1.86	AEMAIL MENUS/TCP/IP menu . . . . .	96
1.87	AEMAIL MENUS/TCP/IP menu/START NET . . . . .	96
1.88	AEMAIL MENUS/TCP/IP menu/STOP NET . . . . .	98
1.89	AEMAIL MENUS/TCP/IP menu/TCP Logging File . . . . .	99
1.90	AEMAIL WINDOWS . . . . .	100
1.91	AEMAIL WINDOWS/Folder List Window . . . . .	101
1.92	AEMAIL WINDOWS/Message List Window . . . . .	102
1.93	AEMAIL WINDOWS/Message Selection . . . . .	105
1.94	AEMAIL WINDOWS/Folder Configuration Window . . . . .	105
1.95	AEMAIL WINDOWS/Filter Selection Window . . . . .	107
1.96	AEMAIL WINDOWS/Examples of using Message Filtering . . . . .	112
1.97	AEMAIL WINDOWS/Set Sort Keys Window . . . . .	114
1.98	AEMAIL WINDOWS/Sort Key Examples . . . . .	116
1.99	AEMAIL WINDOWS/Address Book Window . . . . .	117
1.100	AEMAIL WINDOWS/Message Display Window . . . . .	123
1.101	AEMAIL WINDOWS/Message Display Window/ATTACHMENT REQUESTER . . . . .	125
1.102	AEMAIL WINDOWS/Message Display Window/SAVE TEXT REQUESTER . . . . .	128
1.103	AEMAIL WINDOWS/Compose Message Window . . . . .	129
1.104	AEMAIL WINDOWS/Compose Message Window/ADD ATTACHMENTS . . . . .	138
1.105	AEMAIL WINDOWS/Compose Message Window/ADD HEADERS . . . . .	142
1.106	AEMAIL FILES . . . . .	142
1.107	AEMAIL FILES/mailcap . . . . .	143

---

---

1.108	AEMAIL FILES/mailcap sample file . . . . .	146
1.109	AEMAIL FILES/aemail.cnfg . . . . .	146
1.110	AEMAIL FILES/.headers . . . . .	147
1.111	AEMAIL FILES/folder.config . . . . .	148
1.112	AEMAIL FILES/@{i}Folder_Name@{ui}.config . . . . .	149
1.113	AEMAIL FILES/.addrbook . . . . .	150
1.114	AEMAIL FILES/.signature . . . . .	151
1.115	AEMAIL FILES/Messages . . . . .	151
1.116	AEMAIL FILES/TCPLOG . . . . .	152
1.117	BUG REPORTS & SUGGESTIONS . . . . .	153
1.118	REVISION HISTORY . . . . .	154
1.119	VERSION 1.10 ENHANCEMENTS . . . . .	170
1.120	VERSION 1.12 ENHANCEMENTS . . . . .	172
1.121	IN CONCLUSION . . . . .	175
1.122	REFERENCES . . . . .	176

---

# Chapter 1

## AEMail

### 1.1 AEMail.guide

AEMAIL (Amiga E-Mail)

Version 1.43

(BETA)

by John F. Zacharias

A mail client designed to read, process, compose and send e-mail from an Amiga computer over the Internet.

**PROGRAM PURPOSE**

**COPYRIGHTS**

**SYSTEM REQUIREMENTS**

**RESTRICTIONS**

**REGISTRATION**

**INSTALLATION**

**SETTING THE TIME ZONE**

**CONFIGURATION**

**STARTING AEMAIL**

**USING AEMAIL AS MAILTO AGENT**

**EDITING STRING ENTRY GADGETS**

**USING THE CLIPBOARD WITH AEMAIL**

**FILTERING MESSAGES WITH AEMAIL**

**COMMAND ICON TOOL BAR**

**AEMAIL MENUS**

**AEMAIL WINDOWS**

**VIEWING/SAVING MESSAGE ATTACHMENTS**

**AEMAIL FILES**

**BUG REPORTS & SUGGESTIONS**

**REVISION HISTORY**

**REFERENCES**

**IN CONCLUSION**

---

## 1.2 COPYRIGHTS

AEMAIL (Amiga E-Mail) Version 1.43

AEMail is copyright (c) 1996-98 by John F. Zacharias, all rights reserved.

Permission is given to Beta Testers to test and evaluate the program in return for feedback on the use of the program and reporting of any bugs encountered.

AEMAIL SOFTWARE IS PROVIDED "AS-IS" AND SUBJECT TO CHANGE;  
NO WARRANTIES ARE MADE. ALL USE IS AT YOUR OWN RISK. NO LIABILITY  
OR RESPONSIBILITY IS ASSUMED.

Installer and Installer project icon  
(c) Copyright 1995-96 Escom AG. All Rights Reserved.  
Reproduced and distributed under license from Escom AG.

INSTALLER SOFTWARE IS PROVIDED "AS-IS" AND SUBJECT TO CHANGE;  
NO WARRANTIES ARE MADE. ALL USE IS AT YOUR OWN RISK. NO LIABILITY  
OR RESPONSIBILITY IS ASSUMED.

## 1.3 PROGRAM PURPOSE

What is AEMAIL?

AEMAIL is a mail client designed to read, process, compose and send e-mail from an Amiga computer over the Internet. It provides an easy to use graphical interface designed specifically for the Amiga. It connects to an Internet server through

AmiTCP  
or any TCP/IP stack compatible with AmiTCP. This  
includes

TermiteTCP  
and  
Miami

. It uses the AmigaDOS editor, ed, or any  
other editor of the user's choosing for developing email messages. No other  
external programs or modules are required. The POP3 and SMTP protocols are  
built into the program.

The current version of AEMAIL supports attachments following the MIME  
(Multipurpose Internet Mail Extension) outlined in RFC 1341, 1521,  
1524 (Mailcap files), and 1806 as well as UUENCODED attached files. Not  
all of the features of MIME headers are fully supported and exceptions  
will be noted in this documentation.

AEMail can also be used as a mailto: agent in WWW browsers, such as

IBrowse  
,  
Voyager  
and



AWeb  
, which allow the user to specify such  
an agent for composing and sending email.

You can also call AEMail from another program to send a message created by that program.

## 1.4 SYSTEM REQUIREMENTS

### System Requirements

This program can run on any Amiga Operating System 2.1 and above.

This program requires a TCP/IP stack compatible with

AmiTCP

. It has been

tested with the 4.0 Demo Version of AmiTCP, but will possibly run on earlier versions at level 2.0 or greater. It also has been tested under

TermiteTCP

and

Miami

which use a TCP/IP stack that is compatible with

AmiTCP.

Other TCP/IP software may or may not be compatible with AmiTCP. If the software uses a socket library (bsdsocket.library) with calls that are compatible with AmiTCP, it possibly will work.

If you wish to display MIME attachments from within AEMail, you will also need a Mailcap file. Specifications for how to set up a mailcap file are given under

AEMAIL FILES: mailcap

. It is possible to display

attachments with either AmigaDos 2.x or 3.x. Datatypes are not required for this display.

A

sample mailcap

file is also provided in the archive. This sample

mailcap file can be used without modification on any system running under AmigaDos 3.0 or later since it uses MultiView (which uses datatypes) as the display agent. If you are using a version of AmigaDos before 3.0, you will have to modify the mailcap file to specify your own favorite display program for specific Content Type/Subtypes.

## 1.5 RESTRICTIONS

### Restrictions

---

Only one version of AEMail can be running at a time. If you are using AEMail as a

mailto:

mail agent in a browser, you can not have AEMail running when you invoke your browser if you expect to send any email from your browser. AEMail will be automatically loaded by the browser when you click on a mailto: link.

This same restriction applies if you call AEMail from an external program to Queue or Send a message created by that program.

The Drag Select option for message list will only work with AmigaDOS3.0 or above.

While AEMail appears to work fine with a standard configured AMIGA, there are some possible problems with system addons that might not behave correctly with AEMail.

One such problem had been with hacks or commodities that moved a window to the front when you clicked into it such as the Click-To-Front commodity. The folder window disappeared. That problem has been corrected. Any other hack or commodity that automatically brings the current window to front either when you click on it or when you pass the cursor over it, should work now. Please let me know if you are still having problems.

Another commodity that causes problems with AEMail is one that automatically activates the window under the mouse pointer (AutoPoint). Since AEMail uses multiple windows, it controls which window is active at any point in time. It is not always the window under the mouse pointer since that might not cause AEMail to react properly. As a result, if you activate AutoPoint while AEMail is active, you will experience flashing windows as AEMail switches control away from the window under the mouse pointer.

Other system configurations may also cause problems with AEMail. If you encounter one of these, please send me e-mail describing the problem and what add-on you were using. If it is a public domain program, it would be helpful if you included the program as an attached archive to your message. (see

composing a message  
).

When you call an editor that requires a stack size larger than the default stack size and that program does not create it's own stack, you will have to create a script for that editor and set the stack size from that script. Increasing the stack size of AEMail will not work because AEMail establishes it's own stack size and called programs do not inherit stack size from the calling program.

If you are having problems with editors and stack size, you can use the supplied script for CED (s:AEMced.scr) and modify it to your specifications. One warning, however, if you call a word processor you will need to ALWAYS save the file as ASCII and that program must be able to accept an already existing ASCII file when it is called.

You can send me e-mail by using the  
Address Book

---

Nickname AEMAIL.  
(see Bug Reports and Suggestions  
)

## 1.6 REGISTRATION

### AEMail Registration

AEMail is now shareware. Versions prior to 1.15 were freeware. A shareware fee of \$30 is requested for AEMail. The shareware fee (US Funds only) should be sent to:

John Zacharias  
10004 Vanguard Drive  
Sacramento, CA 95827  
USA

You must include your Real Name and email address with your remittance. A handy form has been provided in the file registration.form which you can print out and use for this purpose. If you have more than one email address with more than one AEMail\_Mail directory, please include ALL these addresses on the registration.form.

The registration.form has an icon which, if you double click on it, will use the PrintFiles program in your SYS:Tools directory to print out the registration form.

Your registration will be acknowledged by email that must be received by AEMail. AEMail version 1.43 does have several features that are not implemented for un-registered users and, in addition for un-registered users, the message display will be slowed down

The features in AEMail 1.43 that are not available to un-registered users are:

- Ability to use multiple signature files.
- Ability to add user defined headers to a message.
- You will not be able to shrink/expand group displays in the Address Book displays. The standard Address Book display will have expanded group displays and the Compose window address book display will have only the group header displayed.
- Enhanced speed on message display.
- Password protection for separate configurations.
- Filtering messages on "Other Message Hdrs".
- Filtering messages on the content of the message body.

Future versions of AEMail may also have enhancements that will only be available to registered users.

For the un-registered Freeware version, permission is given to to test and evaluate the program in return for feedback on the use of the program and reporting of any bugs encountered.

---

I do ask, however, that, in return for the use of this product, you inform me of any suggestions you have and of any bugs that you encounter. You can do that by sending e-mail to me using the Nickname AEMAIL which can be found in your

Address Book  
when you first load AEMail. (see also

Bug Reports and Suggestions  
)

-----  
WARNING WARNING WARNING WARNING WARNING WARNING WARNING WARNING  
-----

When you send your first message with any new version of AEMail, a special "Notification" message will be sent to me at jzachar@calweb.com. Besides the normal header information, the body of this message will contain the following information (obtained from your configuration file):

Your email address  
Your Real Name  
Your POP3 Server name  
Your SMTP Server name  
Your SMTP Domain Name  
Your editor call  
The version of the Exec (OS) that you are using  
Your Display ID (from the screen mode setting)  
Your Overscan Type (from the screen mode setting)  
Base configuration file name  
Currently active configuration file name  
Mail directory

This information is provided to help me determine and debug problems with AEMail. Future versions may contain more or less information as the need arises.

Most of the Internet information is public information and can be obtained from your service provider.

I WILL KEEP THIS INFORMATION IN STRICT CONFIDENCE. IF YOU DO NOT WANT THIS INFORMATION DIVULGED TO ME, DO NOT USE AEMAIL!

I am including this warning because of concerns expressed to me by some people.

-----  
WARNING WARNING WARNING WARNING WARNING WARNING WARNING WARNING  
-----

This "notification" message will also give me the opportunity to inform all users of updates to AEMail by e-mail. When I receive the notification message your email address is placed in a database for informing you of updates. If you do not want to be so informed, send me email to that effect and your name will be removed from the database.

The notification message will not appear in your PENDING folder although you will see it in your SENT folder after the notification message has

been sent. You will not have an opportunity to change any of the information. If you feel some of the information is in error, you can correct it by sending me a separate email message.

Please note that a new notification message will be sent when you upgrade to a new version of AEMail. This lets me know which version you are using. Some of the data in future notification messages may also change to help give me feedback on how AEMail is being used and what setup you are using.

Also, if you are using multiple  
configuration files  
, a separate  
notification message will be sent the first time you send mail with any particular configuration. If you re-install AEMail for any reason you may have an additional Notification message sent.

## 1.7 INSTALLATION

### INSTALLATION OF AEMail

The AEMail Install Script uses the Installer program first provided by Commodore and later revised by Amiga Technologies. You should use the Install\_AEMail script to install AEMail. It is not recommended that you attempt to install AEMail by hand since some actions are necessary through the install script. This is especially true if you are attempting to install a registered version with the supplied diskette!

Installer and Installer project icon  
(c) Copyright 1995-96 Escom AG. All Rights Reserved.  
Reproduced and distributed under license from Escom AG.

To install AEMail simply double click on the Install\_AEMail icon. The install script provides two user levels that the user can choose:

Intermediate (control of configuration parameters)  
Expert (control of configuration and where files are placed)

The Install script makes an attempt to determine which TCP/IP stack that you have installed. This controls which defaults will be taken. The way the install scripts knows which TCP/IP stacks are present is as follows (you must have installed the particular stack before installing AEMail):

AmiTCP: This is controlled by the presence of the AmiTCP: assign statement and the presence of the AmiTCP:bin drawer.

Miami: This is controlled by the presence of the Miami: assign statement. When you installed Miami you should have let the install create the Miami: assign. This was only available under later versions of Maimi.

While the Miami: assign is not an absolute requirement if you are using Miami, it is required if you intend

to use the supplied "startnet.miami" and "stopnet.miami" scripts supplied with this archive. The scripts will not even be moved to your AEMail drawer if the Miami: assign is not present.

TermiteTCP: This is controlled by the presence of the TermiteTCP.prefs environmental variable. Also, if you want to pick up some of the other TermiteTCP variables, such as the email address, you must have run TermiteTCP prior to installing AEMail (TermiteTCP does not have to be online, however).

The action that takes place during the install is slightly different depending on whether

AmitTCP

has been installed or not. The installation

script determines if AmitTCP is installed by checking for an assignment to AmitTCP:. This AmitTCP: assignment was automatically created when you installed AmitTCP.

The AmitTCP: assignment determines where the installation script will place the AEMail executable. For AmitTCP the executable is placed in the AmitTCP:bin drawer. If it is not present, the placement of the executable defaults to an AEMail drawer (created by the script if it does not already exist) on the largest partition on your hard drive.

If you wish to control where AEMail will be placed, you will need to execute the Install script at the Expert user level.

The reason that AEMail is placed in the AmitTCP:bin drawer is that the assumption is made that you are using AmitTCP. The startnet and stopnet scripts should be in the same directory that contains AEMail if they are to work without modification.

If you select the Intermediate user level, the following actions will be taken:

The AEMail executable file will be placed in AmitTCP:bin or, if AmitTCP was not installed, on the largest partition on your hard drive.

Note: No special directory will be created if AmitTCP:bin is present, otherwise a directory called AEMail will be created for containing the AEMail executable. When the installation script terminates it will tell you where it placed the AEMail executable.

The AREXX scripts StartNet.Miami and StopNet.Miami will also be moved to this drawer if you have Miami installed on your system.

Your AEMail mail directory will normally be a directory called AEMail\_Mail in AmitTCP: or, if AmitTCP: was not present, in the AEMAIL directory. The AEMail mail directory will be assigned to AEMAIL:. If an AEMAIL: assignment already exists, that directory will be used as the mail directory except that it will be renamed to AEMail\_Mail if it had been named something else. This operation is automatic and makes updating the AEMail program easy without disturbing your existing mail files.

The documentation files that you want copied will be copied to a drawer

---

called documentation in the drawer which contains the AEMail executable.

If you want the AEMail.readme file, it will be copied to the directory containing your AEMail executable.

A handy registration form called registration.form will be available in your main AEMail directory. It has an icon which, if you double click on it, will use the PrintFiles program in your SYS:Tools directory to print out the registration form.

If you are running under AmigaDos 3.0 or greater, the supplied  
mailcap  
file will be copied to the AEMail\_Mail directory. No ↔  
mailcap  
file will be copied if you are using AmigaDos 2.1.

An AEMAIL: assign statement will automatically be placed in your S:User-Startup file.

An ASSIGN C: SYS:REXXC ADD will also be added to your s:User-Startup file to provide a path to your AREXX commands.

As noted above, the default drawer in which your documentation is placed is a drawer called documentation in the drawer containing your AEMail executable. This is different from prior versions where the documentation files were placed in the same drawer as the AEMail executable. Your old documentation files WILL BE deleted by the installation script. If you want these retained you will have to re-name them yourself.

If you select either user level you will also be able to provide configuration data that will be stored in the  
Tool Types  
parameters of  
the AEMAIL icon. Further, if the AEMAIL: assignment existed at the start of the installation that assignment will be used. However, if the mail directory had been called something else, you will be asked if you want to rename it to AEMail\_Mail. If you select NO, the directory will not be renamed; however, a new AEMail\_Mail directory will be created in the same parent directory and used for the AEMAIL: assignment.

In addition to what is available for the Intermediate user, the Expert user will be able to select what directories will be used and will be able to copy the documentation files to a directory of his/her choice. The Expert user will also be able to select an alternate location for a pre-existing mailcap file and, if running under AmigaDos 2.1, will be able to build their own mailcap file.

If you are updating from a previous version of AEMail, it is recommended that you install at the Intermediate level. That will insure that all of your old assignments and mail files will be available. Also, you should not try to configure AEMail with the Install script since you already have a configuration file assigned.

The one exception to this is if you are updating from a version of AEMail below 1.10. In this case you will HAVE to install at the Expert level in

---

order to locate where your old AEMail installation was placed.

Certain configuration parameters must be provided before AEMail will run. These configuration parameters are provided either by

Tool Types  
in the

AEMail icon or through a special  
Configuration Screen  
when you first run

AEMail and saved in an  
aemail.cnfg  
file in the S: directory.

The installation script will try to automatically configure certain items to default values. These include the switch for deleting mail from your POP Server once it has been transferred to your Amiga and the switch for stripping duplicate messages. The edit call will default to c:ed and will open the editor on the Workbench. Also, if you installed

TermiteTCP

,  
the installation script will obtain your POP3 UserID and SMTP Domain Name as well as your email address from the ttcp-email-address environmental variable provided TermiteTCP has been run (not necessarily on-line) before the AEMail installation was performed.

The installation script will allow you to provide additional configuration parameters as Tool Types in your AEMail icon or to change the default ones. However, if you are updating from a prior version you may already have an aemail.cnfg file in your S: directory which will override the Tool Types. If the S:aemail.cnfg file is present, you will be asked if you want to use it or if you want to re-configure using tool types. If you select this option your current s:aemail.cnfg file will be renamed to s:aemail.cnfg.old and you can reconfigure through the installation script. If you need to restore your old s:aemail.cnfg file you can rename the s:aemail.cnfg.old to s:aemail.cnfg

If these parameters are not provided by Tool Types (through the installation script) or by an existing configuration file, the Edit Configuration screen will be displayed upon the initial startup of AEMail. You can not proceed beyond this configuration screen until certain required configuration parameters are provided. The absolute minimum configuration parameters that must be provided are:

POP3 UserID  
Password  
Your email Address  
SMTP Domain Name  
Edit Call

A POP Server name and a SMTP Server name must also be provided. However, if they are missing AND, if the SMTP Domain Name has been specified, default values will be assigned to these items. These default values will prepend POP. to the domain name for the POP server and SMTP. to the domain name for the SMTP Server as defaults. Please note: these may NOT be correct for

---



your POP and SMTP servers. If they are not, you will have to edit the Configuration and make appropriate changes on the Identity page of the

Configuration screen

If you have installed and ran TermiteTCP before you installed AEMail, the only configuration parameter you may have to provide is your password. The POP3 UserID and the SMTP Domain Name are extracted from the email address that you gave TermiteTCP. If these are not the correct values you will have to change them in the Identity page of the Configuration screen.

For AmiTCP or Miami users, you will need to provide your POP3 UserID and SMTP Domain name as well as your email address.

One of the things that is needed to run AEMail is an editor. By default AEMail will use the AmigaDOS editor, ed, which comes with all Amigas. However, you can change this through the install to any editor that you want provided that you have specified that you want to configure AEMail when you do the install.

If you are using

AmiTCP

, it is recommended that you place AEMail in the same directory that contains your AmiTCP startnet and stopnet scripts (usually AmiTCP:bin) although this is not an absolute requirement. If the directory containing your StartNet or StopNet scripts is NOT the AmiTCP:bin directory or the scripts have names different from startnet or stopnet, you will have to add the

STARTNET

and

STOPNET

tool types

to your AEMail icon. You can do that with the installation script at either the Intermediate or Expert user levels.

If you are using

TermiteTCP

, there are no Start Net or Stop Net scripts.

For

Miami

, special startnet.miami and stopnet.miami scripts have been provided with the install of AEMail. If the Miami assign is present, the install script assumes the Miami startnet and stopnet scripts should be used over the AmiTCP ones.

**SPECIAL NOTE FOR MIAMI USERS:** In the TCP/IP Settings page on Miami, the Down when Offline item should be checked and the settings SAVED. If this item is not checked, it will take AEMail 80 seconds to determine that Miami is offline if Miami is loaded but not online.

The installation script will automatically create a directory for your email storage (mail and configuration files) and place an TWO ASSIGN statement in your S:User-Startup file as follows:

```
ASSIGN AEMAIL: [your-mail-directory-path]
ASSIGN C: SYS:REXXC ADD
```

The second assign statement is used to provide a path to your AREXX commands because the only paths visible when you run a program from the Workbench are the program directory and C:.

If you are using AmiTCP (as determined by the presence of the AmiTCP: assignment), the default directory that is created is AmiTCP:AEMail\_Mail; otherwise, it will be a directory called AEMail\_Mail in the AEMail directory that has been created.

If an AEMAIL: assignment already exists, the AEMail\_Mail directory will not be created nor will the existing mail or Configuration files in the directory be disturbed.

If you want to place the AEMail\_Mail directory some place else you will have to specify the Expert user level when you perform the installation.

**WARNING:** If you are updating and you change the AEMail\_Mail directory you will lose all previous folder configuration data including your registration information if you are a registered user. You will need to copy this data yourself from your old AEMail\_Mail directory to the new AEMail\_Mail directory.

If you are updating AEMail and you are using the same AEMail\_Mail directory, you will be asked if you want to save your existing folder.config file to folder.config.old. If you are updating from a version prior to 1.40, you should reply "Yes" to this request. If you are re-installing version 1.40, reply "No". The format of the folder.config file changes once you add filters to any folders. By having the folder.config.old file you can revert to an earlier version of AEMail by renaming folder.config.old back to folder.config.

The mail directory can start out empty. The AEMail program will generate any necessary configuration and support files required. The AEMail\_Mail directory can be anywhere on any one of your hard drive partitions (or on a floppy or other read/writable media); it does not have to be in the AmiTCP: directory; but it must be mounted when you execute AEMail.

**Special Note on Use of multiple configuration files:** The normal AEMail configuration file is s:aemail.cnfg. With version 1.13 you will be able to assign your configuration file to some other name and location (you will need the Expert user level to do this) and this will become your base configuration. Also, the installation will ONLY configure this base configuration. You will have to use the Configuration screen to configure any other configuration files for other users.

As stated above, you will need a  
mailcap

file if you want to display MIME

mail attachments. A sample mailcap file is provided on the AEMail program disk which uses MultiView to display audio, images, and video content types provided that you have the appropriate datatypes loaded into your system. This, of course, requires AmigaDos 3.0 or higher. If you are using AmigaDos 2.1, the mailcap file needs to be modified to reflect the display

---

programs that you want. The installation script at the Expert level will help you do this.

If you are running under AmigaDos 3.0 or higher, the installation script will automatically move the supplied mailcap file to AEMAIL: unless you specified a different location for a pre-existing mailcap file.

A description of the mailcap file format is given in AEMAIL FILES: mailcap

AEMail gets the current time zone from either the locale.prefs file that is part of AmigaDos or the tz environmental variable. See

Handling of Time Zones  
for further information on this.

When the installation script terminates it will store the directory in which it placed AEMail in the Environmental variable AEMail\_dir. This facilitates updating to future releases of AEMail. The version 1.30 installation script, at all installation levels, will look for this Environmental variable to try to determine where to place AEMail.

The AEMail icon that is created when AEMail is installed will have five Tool Types entered but commented out. These are:

```

;PASSPROTECT=YES

;FLDRFONT=

;FLDRFONTSZ=

;CONFIG=

;MAIL_DIR=

```

These five Tool Types can not be duplicated by the configuration screen. ↵

They can be activated by removing the ";" at the beginning of the tool type and adding the appropriate argument information after the "=" sign. You can do this with the Information menu item in the Workbench Menus (click on the AEMail icon first before using the Information menu item).

## 1.8 TIME ZONES

### Setting the Time Zone for AEMail

AEMail will handle time zones in both full hour and half hour increments. AEMail uses either the tz environmental variable, a special aem\_tz environmental variable, or the locale.prefs file that is part of AmigaDos to determine your local time zone. The locale.prefs file will only allow for full hour time zone offsets. You can use the tz

environmental variable for half hour time zones, but, if this variable is used by other programs in your system it is suggested that you use the `aem_tz` variable instead.

To set the time zone in the `locale.prefs` file, execute the Locale program under your Prefs directory by double clicking on the Locale icon. At the bottom right of the Locale Preferences window you will see a world map with a white line through it that indicates the time zone that you are in. To change this, click on the country you are in. The white line will move to that position and the Time Zone heading at the top of the map will reflect the time zone offset for your part of the world. Then click on the [Save] gadget at the bottom of the window.

Currently AEMail first looks for the environmental variables `aem_tz` or `tz`. The format for `tz` is dictated by `SAS_C` and should be `aaabbbccc` where `aaa` is the abbreviation for local standard time, `bbb` is the offset in hours from GMT (-11 to 12) which is SUBTRACTED from GMT to get the local standard time. `ccc` is the abbreviation for local daylight savings time or summer time (in the United Kingdom or Europe). If the time zone has daylight savings time this should be present even if daylight savings time is not currently in effect (contrary to the specification for `Tz` for the SAS-C compiler). AEMail automatically determines when DST or Summer Time is in effect.

AEMail also recognizes an alternate form of `tz` where `aaa` and `ccc` can be abbreviations longer than 3 characters. This is desirable in some European countries. AEMail will also recognize time zones in increments of one half hour. To specify an half hour time zone, specify it as `+ hhmm`. As an example: `+230` would specify a time zone in which 2 and a half hours are SUBTRACTED from GMT.

You can enter the above with the `tz` environmental variable, but since this variable might be used with other programs in it's strict sense, an alternate environmental variable has been provided called `aem_tz`.

If `aem_tz` is present it will take precedence over `tz`.

If the `tz` or `aem_tz` environmental variables are not present, the system then attempts to get the time zone offset from the `locale.prefs` file. Only the time zone offset is present in this file. The abbreviations for local standard time and daylight savings time are obtained from a table that is by no means complete. Only the time zone abbreviations for the United States, Canada, and the United Kingdom are contained in this table, so one of the environmental variables is preferred.

if neither the `tz` nor `aem_tz` environmental variables nor the `locale.prefs` file are present, the system defaults to CST with an offset of 6.

NOTE: the standard header in an email message has the time zone offset sign reversed from that of the `locale.prefs` and the environmental variables. AEMail automatically makes this reversal, so the offset should be set to positive for US time zones and negative for European time zones. They will appear as negative (for US) and positive (for Europe) in the Date: header.

---

You can set the tz or the aem\_tz environmental variables by using the SETENV AmigaDos Command. This must be done from the shell. The syntax to use is as follows:

```
SETENV tz aaabbbccc                (for tz) and
SETENV aem_tz aaaaaaaaaabbbbbcccccccc (for aem_tz)
```

aaa, your local time zone abbreviation must always be present. If you don't know your abbreviation (or don't want it in the header), use xxx. If AEMail sees xxx it will assume that no abbreviation is present and it will be left off the Date: header

bbb is the time offset in hours from GMT. Plus indicates that you are west of GMT and minus indicates that you are east of GMT. Acceptable values are -12 to 24. If you want to specify a half our time zone it can be entered as hhmm. If AEMail sees a value of 30 or above it assumes that a half hour increment is being used. In this case -1200 to 2400 are acceptable.

If your time zone observes daylight savings time, ccc is the abbreviation to use for daylight savings time. If ccc is not present, no adjustment will be made during the times of the year that daylight savings time is observed.

The result of the SETENV command is only in effect while your computer is on. If you want to make the tz or aem\_tz environmental variables always present enter the one of the following AmigaDOS command after the SETENV command:

```
COPY ENV:tz ENVARC:tz                (or)
COPY ENV:aem_tz ENVARC:aem_tz
```

Using the tz or aem\_tz environmental variables gives you more control over which abbreviations will be used for your time zone. However, the locale.prefs file may be more useful for those that prefer the "point and click" method of doing things. To set the correct time zone for locale.prefs, enter the Locale editor in your Prefs drawer. You will see a time zone map with which you can move the white strip indicating the time zone on the map. Click either to the left or right of the strip to move the strip. The correct time zone offset for standard time will be shown at the top of the map.

Since the locale.prefs does not have any abbreviations, AEMail makes certain assumptions as to what the abbreviation should be. These assumptions are as follows:

Time Zone Name	Standard Time	DST	-----Time Zone----- (in "locale")	(in email Date:)
Greenwich Mean Time	GMT*	BST	0	+0000
Atlantic Time	AST	ADT	4	-0400
Eastern Time (US)	EST	EDT	5	-0500
Central Time (US)	CST	CDT	6	-0600
Mountain Time (US)	MST	MDT	7	-0700
Pacific Time (US)	PST	PDT	8	-0800
Yukon Time	YST	YDT	9	-0900
Hawaiian Time	HST	---	10	-1000

International Date Line IDL --- 12 -1200

--- indicates this time zone does not observe DST

\*Note: GMT (Greenwich Mean Time) is also known as UTC or Universal Time Coordinated.

If you want to use a different abbreviation or control whether DST is used or not, you should use the tz or aem\_tz environmental variable.

DST in the United States and Canada begins on the first Sunday in April.

"Summer Time" in the United Kingdom and Europe begins on the last Sunday in March.

Both DST and "Summer Time" end on the last Sunday in October.

## 1.9 CONFIGURATION

### Configuring AEMail

The configuration of AEMail is provided by parameters presented as

```

Tool Types
in the AEMail icon or by a
Configuration screen
that can be
called up from within AEMail using the
Project/Configuratio/Edit..
menu
item. All configuration items provided by Tool Types can also be provided
by the Configuration screen with the exception of the
MAIL_DIR=
, the

CONFIG=
, the
PASSPROTECT=YES
, the
FLDRFONT=
, and the
FLDRFONTSZ=
Tool Types. These five Tool Types have special uses, as explained ↵
below,
that can not be duplicated by the configuration screen.
```

Certain configuration parameters can ONLY be provided by the Configuration screen.

Currently, setting the time zone that you are in is done outside the AEMail environment. To set the time zone for AEMail see

SETTING THE TIME ZONE

.

If you are running AEMail from the shell or as a  
mailto:

agent, it must  
be either pre-configured (through the  
S:aemail.cnfg file  
) , or you will

have to use the configuration screen for the configuration. You can  
specify an alternate configuration file (other than S:aemail.cnfg) by  
using the

config=  
parameter on the AEMail call line.

The first thing AEMail does when it is activated is check to see that  
certain configuration information has been provided either through Tool  
Types or as contained in the AEMail configuration file. The necessary  
items are:

POP3 UserID

Password

From Addr  
(your email address)

SMTP Domain Name

Edit Call

If any of these items are missing, the following requester will be  
displayed:

The following Configuration items are empty

list of empty items

They are required items!

The

Pop Server call  
and the  
SMTP Server call  
will also be included in

this list if the SMTP Domain Name was missing.

Also, the Edit Call item, if it is missing, will default to:

C:ed %s

with the editor opening on the Workbench. The only way the Edit Call can  
appear in the list is if the

General Parameters  
page of the

Configuration screen  
had been entered and the EditCall field cleared.

If this requester is displayed, you will be given the following choices:

[Configure AEMAIL now]

[Cancel AEMAIL]

If you were to click on [Cancel AEMAIL], AEMail will terminate. You can not proceed any further until you have entered these items with the Configure screen or by providing them as Tool Types.

Clicking on the [Configure AEMAIL now] will bring up the

Configuration screen  
.

Also, if Mail Directory appears in the list of empty items, it means that the AEMail: assign is not in the system and the

MAIL\_DIR=

Tool Type

has not been given. There is no way you can provide this information through the Configuration screen. You will have to either provide the ASSIGN statement or add the MAIL\_DIR= Tool Type. If you use the standard install script, this should never be necessary.

PLEASE NOTE: If you have included the ASSIGN AEMAIL: statement in the S:user-startup file and that assignment includes embedded spaces in one of the directories in the assignment path, the assignment path MUST be surrounded with quotes. The Install script for Version 1.43 automatically does this; however, the install scripts for AEMail versions prior to 1.20 did not do this.

The three Tool Types, MAIL\_DIR=, CONFIG=, and PASSPROTECT=YES have special uses. CONFIG= is used to specify an alternate configuration file other than s:aemail.cnfg that AEMail is to open with. MAIL\_DIR= is used to specify a mail directory other than the one provided by the AEMAIL: assign. It is used to provide an alternate location for the mail files. And PASSPROTECT=YES is used to password protect AEMail when you click on it's icon. Using this Tool Type will call up a requester as soon as you load AEMail which will force you to enter the password that was configured for that instance of the configuration file.

If you have two or more users of AEMail on the same system and you want each user to have different locations for their mail files, you can establish an alternate location for one of the mail directories. To do this, you will have to have two different AEMail icons with different names if they are in the same directory. You can still have only one AEMail executable, however.

One of the icons will have to be a Project icon if you only want one AEMail executable. To create the project icon execute the IconEdit program which is in your SYS:TOOLS directory. When IconEdit is loaded, go to the Open menu and locate the icon for your AEMail executable. (don't confuse this with the icon for the AEMail drawer. The AEMail



executable icon looks like a mailbox). Open this icon. To change the icon to a project icon, go to the Type menu in IconEdit and select Project. Then Save as using a different name for this new icon.

You are still not finished, however. You must edit this icon using the Information menu item on the Workbench menu. First change the Project line (it will say JUNK) to AEMail. If you are in a different directory then the AEMail executable, you will have to enter the full path name to that directory. Then add (or change) the CONFIG= Tool Type to reflect where the configuration file is for that particular user and add (or change) the MAIL\_DIR= Tool Type to give the full path name of the mail directory for that user. Be sure to include the ending '/' after the directory name.

If you want password protection (only available to registered AEMail users) you should also add the Tool Type PASSPROTECT=YES. Do this for each icon that you want to password protect.

Please Note: The Project icon will also inherit the Tool Types from the main executable icon; however, if there is an identical Tool Type, the Project icon's Tool Type will take precedence.

As an example, lets say you have two users named John and Jan. John is the primary user of AEMail. You install AEMail (using any mode) in a directory called HD1:AEMail and the default AEMAIL: assign is set to:

```
ASSIGN AEMAIL: HD1:AEMail/AEMail_Mail
```

If you wanted your configuration file to be John\_aemail.cnfg in the AEMail directory, you could add the following Tool Type to the AEMail icon in HD1:AEMail (this can be done with the Install script as the expert mode or through the Information menu):

```
CONFIG=HD1:AEMail/John_aemail.cnfg
```

You could then create another directory in HD1:AEMail called Jan\_mail. This is where Jan's mail will go. Execute IconEdit and create a project icon that could be called Jan's AEMail. Now select the icon that you just created and the Information item on the Workbench menus. Change Jan's CONFIG= Tool Type to:

```
CONFIG=HD1:AEMail/Jan_aemail.cnfg
```

and add the MAIL\_DIR= Tool Type as follows:

```
MAIL_DIR=HD1:AEMail/Jan_Mail/
```

Then, when John wants to use his copy of AEMail and his files, he double clicks on the main AEMail icon, and when Jan wants to use her copy she double clicks on the one called Jan's AEMail. The one restriction is that you cannot have both copies of AEMail running at the same time. Each set will be set up with different configuration files so that information in these files can be different.

If you are a registered AEMail user you can also add the PASSPROTECT=YES tool type to either of your icons. Please note, however, if you place the

PASSPROTECT=YES Tool Type on the main AEMail executable icon (John's AEMAIL), the project icon (Jan's AEMAIL) will act as if PASSPROTECT=YES was placed on that icon even if it wasn't. However, you can place PASSPROTECT=YES on Jan's AEMAIL icon without placing it on the main AEMAIL icon and the main AEMail will not be password protected.

You can also place the configuration files and mail drawers in different main drawers. If this is done you will have to remember to put the FULL PATH NAME to the AEMail executable in the project icon.

Currently, the creation of the project icon and the modifications mentioned above has to be done by hand. In a future version of AEMail, the installation script will be modified to do this automatically.

You can configure both instances of AEMail through either the  
Tool Types  
in the appropriate icon or with the  
configuration screen  
when you execute  
that particular instance of AEMail.

## 1.10 CONFIGURATION: Tool Types

### Configuring AEMail with Tool Types

Tool Types have been provided to initially provide certain Configuration information when AEMail is first activated without the need to build the Configuration information through the  
Configuration screen  
.

To modify or delete any specific Tool Type, select the AEMail icon and then select the Information item from the Workbench menu. You will have to select the appropriate Tool Type and modify it when it appears in the string gadget below the Tool Type list.

The current Tool Types utilized by the program are:

```
INTERLACE=YES  
  
MAIL_DIR=  
  
CONFIG=  
  
MAILCAP_DIR=  
  
USERID=  
  
PASSWRD=  
  
PASSPROTECT=YES  
  
DOMAIN=
```

FROM=  
REALNAME=  
REPLYTO=  
ORGANIZATION=  
POP\_SERVER=  
SMTP\_SERVER=  
EDITOR=  
TCPLOG=  
DELETEMAIL=YES  
FULLHEADER=YES  
STRIPDUPS=YES  
HDRINREPLY=YES  
STARTNET=  
STOPNET=  
AUTOCONNECT=YES  
FLDRFONT=  
FLDRFONTSZ=

## 1.11 CONFIGURATION: Tool Types/INTERLACE=

INTERLACE=YES

Opens the AEMail Public Screen (AEMAIL-1) in hires, interlace mode. If this tool type is omitted, the screen will be opened as a hires, non-interlaced screen.

You can actually have more control over the Screen Mode you desire by selecting the [Set Screen Mode] button in the AEMAIL

Configuration: General Parameters  
configuration display.

Selecting a Screen Mode from the Configuration display precludes the use of this Tool Type.

## 1.12 CONFIGURATION: Tool Types/MAIL\_DIR=

MAIL\_DIR=directory-path

If you do not place the AEMAIL ASSIGN statement in your S:User-Startup, you can use this Tool Type to assign your mail directory. This can also be used to provide an alternate location to the AEMAIL Assign statement when you have more than one instance of AEMail in your system. This parameter CAN NOT be provided with the Configuration screen. (DEFAULTS to AEMAIL: This assumes that the AEMAIL ASSIGN is present). If you are using a different directory, be sure and include the ending '/' at the end of the directory path.

## 1.13 CONFIGURATION: Tool Types/CONFIG=

CONFIG=configuration-file

If you do not care to use the standard s:aemail.cnfg file for your configuration data, but want a file named something else or in a different location, you can use this tool type. When AEMail opens it will look here for the configuration file. YOU MUST PRECEDE THE FILE NAME WITH THE FULL PATH NAME. This parameter CAN NOT be provided with the Configuration screen, although the initial file can be created, saved, and edited from the "Project/Configuration" menu. (DEFAULTS TO s:aemail.cnfg)

## 1.14 CONFIGURATION: Tool Types/MAILCAP\_DIR

MAILCAP\_DIR=directory-path

Your mailcap file can reside in any directory you want. Use this Tool Type to assign the mailcap directory path. If this parameter is missing, the MAIL\_DIR path will be used as the mailcap directory path.

The mailcap file must be called "mailcap". Since the mailcap file follows a standard format dictated by the internet (RFC 1524), you can use the same mailcap file used by another process. That is the purpose of this Tool Type.

This parameter can also be provided by the  
 Default Path Page  
 of the  
 Configuration Screen  
 (DEFAULTS TO AEMAIL:).

## 1.15 CONFIGURATION: Tool Types/USERID

```
USERID=UserId
```

Enter your POP3 UserId for signing onto your POP Server on your Internet provider (ISP). This may be the same as the one initially used to sign into your ISP. It is also very possibly (but not always) the part of your email address that precedes the @ sign. Check with your ISP for what should be used.

Example: my POP3 UserId is "jzachar" so I would enter

```
USERID=jzachar
```

for this Tool Type. THIS IS A REQUIRED PARAMETER, but it can be provided with the

```
Identity
page of the
Configuration Screen
.
```

## 1.16 CONFIGURATION: Tool Types/PASSWRD=

```
PASSWRD=your_password
```

Enter the password required for signing onto your POP3 server. This may or not be the same as that used to sign onto your Internet provider. THIS IS A REQUIRED PARAMETER, but it can be provided with the

```
Identity
page of the
Configuration Screen
.
```

**SPECIAL NOTE:** if the password is provided by a Tool Type it can be read by anyone that performs an Information on the AEMail icon. If you provide the password through the Configuration screen, it can not be seen.

## 1.17 CONFIGURATION: Tool Types/PASSPROTECT=

```
PASSPROTECT=YES
```

Use this Tool Type if you want to password protect your copy of AEMail. This will call up a special password window when you first load AEMail which will require you to enter your password before you proceed. You will be given three chances to enter the correct password. If the password fails validation after the third try, AEMail will terminate. This Tool Type is ignored for unregistered users.

The Password that is used is the one required for signing onto your POP3

---

server (see  
    PASSWRD=  
    ).  
)

## 1.18 CONFIGURATION: Tool Types/DOMAIN=

DOMAIN=Domain\_Name

Enter the Domain name used by your Internet provider's SMTP server.  
It very possibly is the same as the Domain part of your email address  
(the part following the @ sign)

Example: my Internet provider's domain name is "calweb.com" so I would  
enter:

DOMAIN=calweb.com

for this Tool Type. THIS IS A REQUIRED PARAMETER, but it can be provided  
with the

Identity  
page of the  
Configuration Screen  
.

## 1.19 CONFIGURATION: Tool Types/FROM=

FROM=your\_email\_address

Enter your FULL email address (i.e. user@domain). This is email address  
that you are known by on the Internet.

Example: my email address is "jzachar@calweb.com" so I would enter

FROM=jzachar@calweb.com

for this Tool Type. THIS IS A REQUIRED PARAMETER, but it can be provided  
with the

Identity  
page of the  
Configuration Screen  
. If it is missing

it defaults to UserID@Domain. This default action may NOT be correct  
for your situation, so be sure to change it if required to.

## 1.20 CONFIGURATION: Tool Types/REALNAME=

---

REALNAME=your\_real\_name

Enter your full name. Example:

REALNAME=John Zacharias

This is an OPTIONAL parameter, but if it is omitted your full name will NOT be provided in the FROM: address of any messages you send unless you add it yourself when you

compose a message

. This parameter can also be provided

with the

Identity

page of the

Configuration Screen

.

## 1.21 CONFIGURATION: Tool Types/REPLYTO=

REPLYTO=reply-email-address

This is the email address that you want all replies directed to. This may be the same as your From: email address or it can be a different address if you want replies sent somewhere else. This is an OPTIONAL parameter and can also be provided with the

Identity

page of the

Configuration screen

.

The standard Reply-To address provided here can also be modified each time you

compose a message

to send.

## 1.22 CONFIGURATION: Tool Types/ORGANIZATION=

ORGANIZATION=organization-name

This parameter is OPTIONAL and, if present, will provide an Organization: header for any message that you compose and send. This parameter can also be provided with the

Identity

page of the

Configuration screen

.

## 1.23 CONFIGURATION: Tool Types/POP\_SERVER=

```
POP_SERVER=your_POP_host
```

Enter the name of your POP host. This sometimes is pop. or mail. prepended to your Domain name. As an example, mine is "pop.calweb.com" so I would enter:

```
POP_SERVER=pop.calweb.com
```

If this parameter is omitted, pop.domain-name will be generated as your POP\_SERVER name provided a domain name has been specified. Unless your POP server is different it is recommended that you do not include this Tool Type.

This parameter can also be provided by the  
Identity  
page of the  
Configuration Screen.

## 1.24 CONFIGURATION: Tool Types/SMTP\_SERVER=

```
SMTP_SERVER=your_SMTP_host
```

Enter the name of your SMTP host. This sometimes is smtp. or mail. prepended to your Domain name. As an example, mine is "smtp.calweb.com" so I would enter

```
SMTP_SERVER=smtp.calweb.com
```

If this parameter is omitted, smtp.domain-name will be generated as your SMTP\_SERVER name provided a domain name has been specified. Unless your SMTP server is different it is recommended that you do not include this Tool Type.

This parameter can also be provided by the  
Identity  
page of the  
Configuration Screen.

## 1.25 CONFIGURATION: Tool Types/EDITOR=

```
EDITOR=call_line_for_your_editor
```

Enter the full call parameter required to activate your editor from the shell. Use %s where you would place the file name.

You are no longer restricted to an editor call that does not remain in

---



control when you call it as you were with previous versions of AEMail. In other words, a direct call to CygnusEd (CED) is acceptable.

If your editor opens on the Workbench screen rather than a screen of its own, you should prepend WB; in front of your editor call. As an example, the standard AmigaDOS ED program always opens on the Workbench screen. An example edit call for the Amiga ED would be as follows:

```
EDITOR=WB;c:ed %s WINDOW raw:0/0/640/400/AEMailCompose
```

The window statement in the above call is used to create a full screen window with an interlaced display.

If you are not using an interlaced display you can remove the WINDOW parameter or change it to raw:0/0/640/200/AEMailCompose. You can, of course, make other changes to the window parameters if you desire.

If you are using Amiga ED you should probably also remove or rename the ED-Startup file in the S: directory so that you will have a full set of ED menus.

If this Tool Type is missing, the following call is the default editor call:

```
EDITOR=WB;c:ed %s
```

This defaults to using the Amiga Ed program for your editor.

The specification for your editor call can also be provided by the

```
General Parameters
page of the
Configuration Screen
. A
```

convenient check mark item is provided in the Configuration Screen to open the editor on the Workbench screen.

## 1.26 CONFIGURATION: Tool Types/TCPLOG=

```
TCPLOG=name_of_log_file
```

Enter the full path, including file name, of your  
TCP logging file

If this parameter is omitted, it defaults to tcplog in the directory AEMail is loaded from.

This parameter does not start TCP logging, it only establishes the name of the TCPLOG file. Logging can be started or stopped at any time by the menu item

```
TCP/IP/TCP Logging File/Active
. The Logging file can be set
```

active when AEMail is started through a parameter in the  
Paths

page  
of the Configuration Screen

When TCP logging is active, all sends and receives over the TCP/IP connection are recorded to this file. Each time an AEMail session is started and logging is active, data is appended to this file. As a result this file can become quite large. IT IS THE USER'S RESPONSIBILITY TO PERIODICALLY PURGE (DELETE) THIS FILE. A menu item is provided to perform this

purge  
and another item to  
display  
the log file with your editor from  
within AEMail.

NOTE: When there is a need to report a problem, especially with your TCP/IP connection, the TCP Logging file should be set active and a copy of the resultant file provided with any feedback on the program activity (see

Bug Reports & Suggestions  
) . The file can be sent as an attachment  
to any message that you send to AEMAIL. You probably should compress the  
file with LHA before attaching it as an Applicatio/Octet Stream  
Content Type/Subtype with encoded binary encoding.

I have discovered that this file comes in handy when analysing problems with your Internet provider since it time stamps all entries to the nearest second.

This parameter can also be provided by the  
Default Path Parameters  
page of the  
Configuration Screen.

## 1.27 CONFIGURATION: Tool Types/DELETEMAIL=

DELETEMAIL=YES

This Tool Type sets the initial value of the  
Delete Host Mail  
menu item

under the  
RETRIEVE MSGS menu  
. If this Tool Type is entered, the Delete  
Host Mail menu item will be initially checked.

This parameter can also be set by the  
General Parameters  
page of the  
Configuration Screen  
or the DELETEMAIL flag can be set with the Delete

Host Mail menu item and its state can be saved in the configuration file by selecting the PROJECT/CONFIGURATION/SAVE menu item.

## 1.28 CONFIGURATION: Tool Types/FULLHEADER

FULLHEADER=YES

This Tool Type sets the initial value of the Display Full Header menu item under the MESSAGES menu. If this Tool Type is entered, the Display Full Header menu item will be initially checked.

This parameter can also be set by the General Parameters page of the Configuration Screen or the FULLHEADER flag can be set with the Display Full Header menu item and its state can be saved in the configuration file by selecting the PROJECT/CONFIGURATION/SAVE menu item.

## 1.29 CONFIGURATION: Tool Types/STRIPDUPS

STRIPDUPS=YES

This Tool Type sets the initial value of the Excl Dup Msgs menu item under the RETRIEVE MSGS menu. If this Tool Type is entered, the Excl Dup Msgs menu item will be initially checked.

This parameter can also be set by the General Parameters page of the Configuration Screen or the STRIPDUPS flag can be set with the Excl Dup Msgs menu item and its state can be saved in the configuration file

by selecting the  
PROJECT/CONFIGURATION/SAVE  
menu item.

### 1.30 CONFIGURATION: Tool Types/HDRINREPLY

HDRINREPLY=YES

This Tool Type sets the initial value of the  
Incl Hdr in Resp  
menu item

under the

MESSAGES menu

. If this Tool Type is entered, the  
Incl Hdr in Resp menu item will be initially checked.

This parameter can also be set by the  
General Parameters  
page of the

Configuration Screen

Hdr in Resp menu item and its state can be saved in the  
configuration file  
by selecting the  
PROJECT/CONFIGURATION/SAVE  
menu item.

### 1.31 CONFIGURATION: Tool Types/STARTNET

STARTNET=call\_line\_for\_your\_startnet\_script

This Tool Type is used to specify the call line for your script that  
starts up your TCP/IP stack. If you are using

AmiTCP

, this is normally

the file startnet in the AMITCP:bin directory. If you are using  
Miami

,

an AREXX script has been provided with the AEMail archive called  
startnet.miami and it is located in the AEMail program directory.

A full path name to that script must be entered. If the script is an  
AREXX script it should be preceded with "rx " (a space is between the rx  
and the script name). The standard AmiTCP startnet script is NOT an AREXX  
script even though it uses AREXX commands. It is an AmigaDOS script. The  
Miami script, on the other hand, is an AREXX script.

If you do not use the STARTNET Tool Type, AEMail assumes that you do not

have a script. If you activate the  
     Start Net  
     item in the  
     TCP/IP  
     menu  
 and you don't have a startnet script, AEMail's action is to  
     iconify  
     and

allow you to manually start your TCP/IP stack. Connect using the method prescribed by your TCP/IP stack. When you un-iconify AEMail, AEMail will immediately check to see if any mail is present on your POP server.

If you are using a TCP/IP stack that can't use a script (such as

    TermiteTCP  
     ) or you have no script to make connection to your Internet provider, then this Tool Type should not be used. Then if you select the Start Net menu item, the system will automatically iconify AEMail and present the Workbench screen.

Since AmiTCP Demo Version 4.0 puts up a requester on the workbench screen that must be responded to, AEMail will automatically switch to the Workbench screen before calling this script. Although the Miami script does not require manual intervention, the default action is to also switch to the Workbench screen since this allows you to see the action of the dialer. When the connection has been made using Miami, the screen will automatically switch back to the AEMail screen.

The Start Net script can also be set by the  
     TCP/IP  
     page of the

    Configuration Screen  
     . The Configuration screen will also allow you to set whether or not the system switches to the Workbench screen when the Start Net script is executed.

Note: Check your startnet script to be sure that full path names are specified. If you are using the standard AmiTCP startnet script, that script may not be executed from the Amitcp:bin directory (unless AEMail is executed from there). Therefore, you should verify that Amitcp:bin/ is prepended to all calls to functions within the AmiTCP:bin/ directory within the script. Pay particular attention to the online call - it should be AmiTCP:bin/online. You will also have to move the AREXX commands (such as WaitForPort and RX) to the C: directory. The  
     installation  
     script will automatically do this for you.

## 1.32 CONFIGURATION: Tool Types/STOPNET

STOPNET=call\_line\_for\_your\_stopnet\_script

This Tool Type is used to specify the call line for your script that terminates your TCP/IP connection. If you are using

AmiTCP  
, this is  
normally the file stopnet in the AMITCP:bin directory. If you are using

Miami  
, an AREXX script has been provided with the AEMail archive  
called stopnet.miami and it is located in the AEMail program  
directory.

A full path name to that script must be entered. If the script is an  
AREXX script it should be preceded with "rx " (a space is between the  
rx and the script name). The standard AmiTCP stopnet script is NOT an  
AREXX script even though it uses AREXX commands. It is an AmigaDOS  
script. The Miami script, on the other hand, is an AREXX script.

If you do not use the STOPNET Tool Type, AEMail assumes that you do not  
have a script. If you activate the

Stop Net  
item in the  
TCP/IP  
menu

and you don't have a stopnet script, AEMail's action is to  
iconify  
and

allow you to manually stop your TCP/IP stack. You can then disconnect  
using the method prescribed by your TCP/IP stack. When you un-iconify  
AEMail, AEMail will test to see if you are, in fact, disconnected.

If you are using a TCP/IP stack that can't use a script (such as

TermiteTCP

) or you have no script to terminate your connection to  
your Internet provider, then this Tool Type should not be used. Then if  
you select the Stop Net menu item, the system will automatically  
iconify AEMail and present the Workbench screen.

The Stop Net script can also be set by the  
TCP/IP  
page of the

Configuration Screen

. The Configuration screen will also allow you  
to set whether or not the system switches to the Workbench screen when  
the Stop Net script is executed. Since terminating your connection with a  
script usually does not require any visual interaction, the default action  
is to NOT switch to the Workbench screen.

Note: Check your stopnet script to be sure that full path names are  
specified. If you are using the standard AmiTCP stopnet script, that  
script may not be executed from the Amittcp:bin directory (unless AEMail  
is executed from there). Therefore, you should verify that Amittcp:bin/  
is prepended to all calls to functions within the Amittcp:bin/ directory  
within the script. Pay particular attention to the offline call - it  
should be Amittcp:bin/offline. You will also have to move the AREXX commands  
(such as WaitForPort and RX) to the C: directory. The

installation  
script will automatically do this for you.

---

### 1.33 CONFIGURATION: Tool Types/AUTOCONNECT

AUTOCONNECT=YES

When AEMail is first activated it attempts to determine if you are connected to your Internet provider. If you are not and this Tool Type is present, AEMail will automatically run your

```
StartNet
script. (see

Starting AEMAIL
.)
```

Before activating this Tool Type, you should check to see if AEMail can activate your TCP/IP stack properly using the

```
Start Net
menu item in the

TCP/IP menu
```

. If there are any problems with your Start Net activation they will show up at this time rather than constantly every time you try to activate AEMail.

**WARNING:** You should not use this Tool Type if a StartNet script is not present for your TCP/IP stack. You should activate your TCP/IP stack manually before you start AEMail.

You can also set the AUTOCONNECT flag with the  
TCP/IP Parameters  
page

of the  
Configuration Screen  
.

### 1.34 CONFIGURATION: Tool Types/FLDRFONT & FLDRFONTSZ

FLDRFONT=fontname

This allows the user to specify their own font for the folder strip. Since the size of the folders in the folder strip is constrained by the size of the font that you use, you can specify a different font and font size (see FLDRFONTSZ= below) to reduce the size of the folder strip. If not specified the folder font will default to the standard Topaz 8 font. When you enter the font name it is entered WITHOUT the .font suffix and it must be found in your FONTS: directory.

If you use FLDRFONT= without FLDRFONTSZ=, the resulting font will be the one you specify at the 8 size. If no such size exists in your FONTS: directory, it will be computed. This can sometimes be

unsatisfactory.

Currently this parameter can only be provided by a Tool Type. A future version will allow you to specify the font through a special configuration page.

FLDRFONTSZ=fontsize

This Tool Type is used in conjunction with the FLDRFONT= Tool Type described above. These two Tool Types allow the user to specify their own font and font size for the folder strip. Since the size of the folders in the folder strip is constrained by the size of the font that you use, you can specify a different font and font size to reduce the size of the folder strip. If not specified the folder font will default to the standard Topaz 8 font.

If you use FLDRFONTSZ= without FLDRFONT=, the resulting font will be Topaz with a computed font size corresponding to this parameter

Currently this parameter can only be provided by a Tool Type. A future version will allow you to specify the font through a special configuration page.

## 1.35 CONFIGURATION: Configuration Screen

### Configuration Screen

The Configuration screen which is displayed on the Workbench Screen when either you click on the [Configure AEMAIL now] button or when you select the

```
Configuration/Edit
menu item under the
Project menu
. The Configuration
```

screen is divided into four pages with the page name shown with a button at the top of the page area. When you click on any one button that button will become highlighted and the appropriate page will be displayed.

The four pages are:

```
IDENTITY
TCP/IP
PATHS
GENERAL
```

At the bottom of the Configuration screen is a row of buttons as follows:

```
[USE] [SAVE] [SAVE AS] [CANCEL]
```



Clicking on any one of these buttons will perform the requested action, regardless of which page you are on, and return you to the main

AEMail screen

.

If you want the configuration information to apply only to the current AEMail session select [USE]. If you want to make the configuration permanent, select [SAVE]. This will cause a new

configuration file  
to be written and

will also signal that the configuration file is to take precedence over the Tool Types the next time AEMail is loaded.

Normally the configuration file is either s:aemail.cnfg or the file specified in the

CONFIG=  
tool type. However, if you opened another

configuration file with the

Project/Configuration/Open...  
menu item,

that configuration file will be the current active one.

The [SAVE AS] button does the same as [SAVE] except that a file requester will be displayed that will allow you to rename and place the configuration file anywhere you wish. **WARNING:** when you use the [SAVE AS] button, AEMail assumes that that file is now your active configuration file and any saves occurring after that will be to that file.

To return to the base configuration (either s:aemail.cnfg or the CONFIG= file), use the

Project/Configuration/Restore Default  
menu item.

[CANCEL] will abort the operation without making any changes to the configuration information.

The [USE], [SAVE], [SAVE AS] or [CANCEL] buttons are active no matter which configuration page is currently active. When the Configuration screen is first activated, the Identity page will be active.

Before exiting from the Configuration Screen with [USE], [SAVE] or [SAVE AS] the required configuration parameters must be present. If not, the following requester will be displayed:

The following Configuration items are empty

list of empty items

They are required items!

This is the same requester that is displayed when AEMail is started without these parameters being provided. Your choices with this requester are:

---

[Reenter Configuration Data]      [Cancel Configuration Request]

Clicking on the [Cancel Configuraion Request] will act the same as if you clicked on [CANCEL] in the main configuration screen. In this event your "old" configuration data will still be active and if you did not have the required parameters in the first place, you will not be able to do anything but enter the data or exit from AEMail.

The one exception to the "old" configuration remaining the same is with the

.headers  
file. This is always updated no matter which button is pressed.

## 1.36 CONFIGURATION: Configuration Screen/Identity Page

### Identity Page

The Identity page appears as follows:

```

=====
AEMAIL Configuration Screen
-----

[ IDENTITY ]_____
|
|      POP3 UserID: [                ] [CLR] [DEFAULT] [CHANGE PASSWORD] |
|
| From (email) Address: [                ] [CLR] [DEFAULT] |
|
|      Reply To Address: [                ] [CLR] {DEFAULT} |
|
|      Real Name: [                ] [CLR] [DEFAULT] |
|
|      Organization: [                ] [CLR] [DEFAULT] |
|
|      POP Server: [                ] [CLR] [DEFAULT] |
|
|      SMTP Server: [                ] [CLR] [DEFAULT] |
|
|      SMTP Domain Name: [                ] [CLR] [DEFAULT] |
|_____

                                     [USE] [SAVE] [SAVE AS] [CANCEL]
=====

```

When this page is first called up, values from the  
Tool Types  
or the current  
configuration file

(which ever takes precedence) will be displayed in each of the string gadgets.

Appropriate information can be entered into each of the string gadgets. Up to 99 characters can be entered in each of the string gadgets.

The buttons to the side of each string gadget perform the following actions:

[CLR] will cause the string gadget to be cleared.

[DEFAULT] will cause default information to be loaded into the string gadgets as follows:

POP3 UserID: information from the  
USERID=  
Tool Type.

From Address: information from the  
FROM=  
Tool Type.

Reply To Address: information from the  
REPLYTO=  
Tool Type or,  
if missing, the From Address.

Real Name: information from the  
REALNAME=  
Tool Type.

Organization: information from the  
ORGANIZATION=  
Tool Type.

SMTP Domain Name: Information from the  
DOMAIN=  
Tool Type.

POP Server: information from the  
POP\_SERVER=  
Tool Type if  
present; otherwise , if a Domain Name is present,  
this will be the domain name with pop. prepended  
to it.

SMTP Server: Information from the  
SMTP\_SERVER=  
Tool  
Type if present; otherwise, if a Domain Name is  
present, this will be the domain name with smtp.  
prepended to it.

If a Tool Type was the only default and it is missing, nothing is loaded into the corresponding string gadget.

---

The [CHANGE PASSWORD] button gadget will bring up a special window which will allow you to add or change your password. This window looks like the following:

```

|=====|
|0|Enter Password |
|-----|
|          |
|   Enter your new password below   |
|          |
|   [                               ] |
|          |
|          |
| [START OVER]           [ CANCEL ] |
|-----|

```

The string gadget will be automatically activated when the window is displayed. You can type in your new password, but for each character you type an \* will appear. After hitting return, the heading:

Enter your password below

will be replaced by the following heading:

For verification, re-enter your password

You must re-enter your password and, when you hit return, if the re-entered password matches the first password, the password window will close. The new password will not take effect until you hit the [USE] or [SAVE] buttons at the bottom of the window.

If the re-entered password does not match, the following will appear below the password entry string gadget:

Password failed Validation!

and the Enter your password below heading will re-appear.

If at any time you want to start over with entering the new password, you can click on the [START OVER] gadget. If you want to cancel the password entry process you can either click on the close gadget at the top left of the window or on the [CANCEL] gadget in the window.

Only 30 characters can be entered into the password string gadget.

## 1.37 CONFIGURATION: Configuration Screen/TCP/IP Page

TCP/IP Page

The TCP/IP page appears as follows:

```
=====
```

## AEMAIL Configuration Screen

```

-----
_____ [ TCP/IP ] _____
|
| Start Net Call: [                ] [REQ] [CLR] [DEFAULT] |
|                [ ] Start Net Opens on the Workbench   |
|
| Stop Net Call: [                ] [REQ] [CLR] [DEFAULT] |
|                [ ] Stop Net Opens on the Workbench     |
|
| [ ] Automatic connection to Internet Provider on AEMAIL Start Up |
| [ ] Display disconnect check on AEMAIL exit             |
|
| Disable Queued Mail Chk [ ] on connection establishment [ ] at AEMAIL exit |
|   Disable New Mail Chk [ ] on connection establishment [ ] at AEMAIL exit |
|
|                Check for new mail every [ 2 ] minutes   |
|_____
|
|                                     [USE] [SAVE] [SAVE AS] [CANCEL]

```

The Start Net Call and Stop Net Call are required if you are going to start up or stop your TCP/IP connection from within AEMail with a script. If you are using

```

    AmiTCP
    , this is normally either the file startnet or
stopnet in the AMITCP:bin directory. If you are using
    Miami
    , two AREXX
scripts, called startnet.miami and stopnet.miami have been provided
with the AEMail archive located in the AEMail program directory.

```

When first presented, these two string gadgets will contain the values given in you

```

    STARTNET
    and
    STOPNET
    Tool Types or what was last stored in your

```

```

    configuration file
    . If these two Tool Types are not present, these two
string gadgets will be blank unless a previous configuration file is present
and has these calls.

```

If you do not want what is presented as the default in these two string gadgets, you can enter the correct path and script name in the string gadgets. A full path name to that script must be entered. If the script is an AREXX script it should be preceded with "rx " (a space is between the rx and the script name). The standard AmiTCP startnet script is NOT an AREXX script even though it uses AREXX commands. It is an AmigaDOS script. The Miami script which comes with AEMail, on the other hand, is an AREXX script.

The [REQ] button will call up a file requester to allow you to find the script you want and [CLR] will clear the string gadget.

[DEFAULT] will place the script path and name from your Tool Types in the appropriate string gadget.

If you need the Start Net script or the Stop Net script to open on the workbench screen, click on the appropriate check mark gadget for the particular script. When the TCP/IP Configuration page first opens the Start Net Opens on the Workbench item will be checkmarked.

#### SPECIAL NOTE FOR USERS OF TERMITE TCP

If you are using a TCP/IP stack that does not have a Start Net or Stop Net script (such as

TermiteTCP

), you should use the [CLR] button to clear these

two string gadgets. Starting and stopping your Internet connection is then done manually. Then, when you use the

Start Net

or

Stop Net

menu item, the

action that is performed is to

iconify

AEMail. You can then perform the

network connection in whatever manner was provided by your TCP/IP stack software. Once the connection is made, un-iconify AEMail and AEMail will then check your POP Server for any available messages if that option was selected (see below).

The Automatic connection to Internet Provider on AEMAIL Start Up check box provides the same capability as the

AUTOCONNECT=YES

Tool Type. When

AEMail is first activated it attempts to determine if you are connected to your Internet provider. If you are not and this item is checked, AEMail will automatically run your Start Net script. However, the AUTOCONNECT function will be disabled if you do not have a Start Net script.

Except when you are using AEMail as a

mailto:

agent, when AEMail terminates

and you are still connected to your Internet provider, the following Requester will be displayed:

Do you wish to terminate your Host connection now?

You will be given the opportunity to reply with either a [YES] or [NO]. If you never want your Internet connection to be terminated when you exit from AEMail, you can prevent the above requester from being displayed by NOT checking the Display disconnect check on AEMAIL exit box. By default, this box WILL BE CHECKED, so, to disable the function, you would have to click in this box. However, this function will automatically be disabled if you do not have a

Stop Net script.

Please Note: The way AEMail determines if you are still connected is to check if the `bsocket.library` is present. This library may become present when you load your TCP/IP stack software. Even though you may not be connected the `bsocket.library` will then be present, so you will get the above notification even though you are not actually connected. In this event replying with either [YES] or [NO] to the requester will have no effect.

Whenever AEMail is first loaded and is connected to your Internet Provider or if you select

```
Start Net
from the
TCP/IP
```

menu, a check will be made for any mail on your POP Server or any mail that must be sent from your QUEUED folder. Except when you are using AEMail as a `mailto:` agent, this same check is performed when you quit AEMail. You can disable any of these checks by checking the appropriate box in the following lines:

```
Disable Queued Mail Check  on connection establishment  at AEMAIL exit
Disable New Mail Check  on connection establishment  at AEMAIL exit
```

AEMail also has the capability for checking for mail periodically on your POP Server. This function is performed in the background so you can be doing other activities while this check is going on. When mail is found, the following requester will pop up on your screen:

YOU HAVE MAIL!!

n Messages available on the POP Server

Do you wish to receive these messages now?

Replying [YES] to the above requester will start the retrieval of the messages. If you are in iconify mode when this occurs, the retrieval will occur in the background without bringing up the AEMail screen.

You can set the time interval for this check by entering the appropriate number of minutes in the following numeric gadget:

Check for new mail every [ ] minutes

The default time interval is 2 minutes. If you enter a zero in this numeric gadget, no check will be made.

## 1.38 CONFIGURATION: Configuration Screen/Path Page

Default Path Page

---

The Default Path page appears as follows:

```

=====
AEMAIL Configuration Screen
-----

_____ [ PATHS ] _____
|
|           Mailcap Directory: [                ] [REQ] [CLR] [DEFAULT] |
|
|           TCP Logging File: [                ] [REQ] [CLR] [DEFAULT] |
|           [ ] TCP Logging Active on AEMAIL startup |
|
| Retrieve Mail from Directory: [                ] [REQ] [CLR] [DEFAULT] |
|
|           Save Mail to Directory: [            ] [REQ] [CLR] [DEFAULT] |
|
| Add Attachments from Directory: [            ] [REQ] [CLR] [DEFAULT] |
|
| Save Attachments to Directory: [            ] [REQ] [CLR] [DEFAULT] |
|_____
|
|                                     [USE] [SAVE] [SAVE AS] [CANCEL]
|
=====

```

String gadgets are provided for giving the full path for each of the default directories and or file. The directory paths that can be specified are:

Mailcap Directory: This is the directory that contains your mailcap file. The file will always be named mailcap. The default entry for this is AEMAIL:.

TCP Logging File: This allows you to enter a file name as well as a path. The default path and file name is tcplog in the AEMail program directory. If this field is cleared, no TCP logging can take place. When the [SAVE], [SAVE AS] or [USE] gadgets are selected, if TCP Logging was

Active  
and  
the

TCP logging File name that was entered is different from the current log file, the current log file will be closed and a new file opened. If you clear this field TCP logging will stop since there is no file to log to.

Whether logging takes place or not should depend on the

TCP/IP/TCP Logging File/Active menu item (checkmarked flag).

You can cause TCP logging to be active when AEMail starts up by



checking the TCP Logging Active on AEMAIL startup check mark gadget below the TCP Logging File string gadget. If this item is checked, the logging will become Active when you exit from the Configuration screen. You will have to turn off the Active flag in the TCP/IP/TCP Logging File menu item to stop logging.

Note: none of the actions mentioned above will take place until you select [USE], [SAVE] or [SAVE TO] at the bottom of the Configuration screen. If you select [CANCEL] no change will be made in your TCP logging activity.

Retrieve Mail from Directory: This is the initial path that will appear in the file requester when you

Retrieve mail from a file  
rather

than your POP Server. The default directory for these files is PROGDIR: which is your current AEMail program directory. If you regularly are trying to bring in mail that was previously transferred using another mail user agent such as AmiPOP, AirMail, or Voodoo, you should use the directory that was used for these agents for storing mail. You can specify any directory of your choosing as the default path for the Retrieve Mail file requester. You enter that default in this string gadget.

Save Mail to Directory: This is the initial path that will appear in the file requester when you select the

Save Message to File  
icon in the  
command icon strip

. The default directory for this path is PROGDIR:, which is your current program directory. However, you can specify any other path of your choosing as the default path for the Save Mail file requester. You enter that default in this string gadget.

Add Attachments from Directory: This is the initial path that will appear in the file requester when you select the [REQ] button in the

Add Attachment requester

. The default directory for this path is PROGDIR:. However, you can specify any other path of your choosing as the default path for the Add Attachment requester. You enter that default in this string gadget.

Save Attachments to Directory: This is the initial path that will appear in the file requester when you select the [Save] or [View & Save] buttons in the

Attachment requester  
. The default

directory for this path is RAM:. However, you can specify any other path of your choosing as the default path for the Attachment file requester. You enter that default in this string gadget.

When this this page is first activated, the values that were last saved in the current

configuration file  
will be displayed.

The buttons to the side of each string gadget perform the following actions:

[CLR] will cause the string gadget to be cleared.

[DEFAULT] will cause default information, as described above, to be loaded into the appropriate string gadget.

[REQ] causes a file requester to appear for selecting the appropriate directory and file name ( TCP Logging File only) to be loaded into the appropriate string gadget. The file requester will start out with the last path that was used for that particular string gadget. If no path was last used, a dummy name of VOLUMES will be used, the requester will flash, and the volumes and assigns will be displayed.

### 1.39 CONFIGURATION: Configuration Screen/General Parameters Page

#### General Parameters Page

The General Parameters page appears as follows:

```

=====
AEMAIL Configuration Screen
-----

_____ [ GENERAL ] _____
|
|Printer Device: [PRT:          ] [REQ] [CLR] [DEFAULT]  Top Margin:[4  ] |
|          [ ] Include Attachment List in Print Out |
|
|    [ Printer Setup ]                      [Set Screen Mode] |
|                      [Set Minimum Headers] |
|
|    [ ] Delete Mail from Server      [ ] Display Full Header |
|    [ ] Strip Duplicate Messages     [ ] Include Header in Reply |
|
| EditCall: [          ] [REQ] [CLR] [DEFAULT] |
|          [ ] Editor Opens on the Workbench |
|
|                      Default Reply to Message Parameters |
|
|    [ ] Quote Original Message Text  Quote Prefix[>      ] |
|
| Quote Header: [          ] |
|
|_____
[USE] [SAVE] [SAVE AS] [CANCEL]

```

=====

The General Parameters screen allows you to set up certain general type parameters such as specifications for your printer device, the screen mode that you want your AEMail screen to open on, the list of minimum headers you want displayed in a message, certain default menu checkmarked items, the specification for your editor, and the specifications for the default message reply headers.

For the Printer Device you can specify the device that you want to do your printing on. By default this is PRT:, but you can specify a file if you care to. If you specify a file, your printer output will be sent as standard ASCII text with form feeds and margin spacing included in the output. The [REQ] button will call up a file requester through which you can enter the path and file name of this printer file. [CLR] will clear the string gadget and [DEFAULT] will enter PRT: into the gadget. When this screen is first displayed, the PRT: default name will be in the gadget.

You can also specify the Top Margin of the printout with the numeric string gadget to the right of the Printer Device. The default top margin is 4.

If you do want the list of attachments to appear on the last page of your printout, you can check the Include Attachment List in Print Out box. By default, this box is checked when you first call up the General Parameters page.

If you want to modify your printer setup parameters that are normally set with your PRINTER PREFERENCES, you can click on the [Printer Setup] button. This will call up the standard Printer Preferences program so that you can change your printer setup. Please Note that, if you change the printer preferences, the new preferences will remain in effect when you quit AEMail.

If you want to set your screen mode for AEMail, you can click on the [Set Screen Mode] button. This will call up a standard Screen Mode Requester which will allow you to set whatever screen mode you wish. Your overscan mode can also be set. This defaults to OVERSCAN-TEXT. When you save your configuration settings, the screen mode you selected and the overscan setting are saved in the

```
aemail.cnfg
file and will be used the next time you load
```

AEMail.

The minimum header set that you want displayed in your message can be set by clicking on the [Set Minimum Headers] button. This will bring up a requester that looks like this:

```
|=====|
|[o] Set Minimum Headers      |
|=====|
|           Select/Deselect Headers           |
|                   to be displayed           |
```

```

|=====|
|| *bcc:           | ||
|| *cc:           | ||
|| Content-Transfer-Encoding: | ||
|| Content-Type:  | ||
|| *Date:         | ||
|| *From:         | ||
|=====|
|           Enter New Header           |
|[                                     ]|
|                                     |
|           [OK]                       |
|=====|

```

A list of possible message headers is displayed in the scrollable list. An asterick (\*) in front of a header indicates that it has been selected for inclusion in the minimum header list. Clicking on an item in the list will select it with an (\*). If it is already selected, it will be deselected (the asterick will change to a blank).

The string gadget at the bottom of the requester is used to enter a header that is not in the list. Be sure to end the header with a colon (:). After entering the header, press return and the header will be placed properly in the scollable list. It will be deselected when it is first entered in the list. You will have to click on it to select it.

When you are through entering items in the list, click on [OK] and you will be returned to the General Parameters page. Clicking on the close gadget at the top of the requester has the same effect as clicking on [OK].

Please NOTE: anything you enter in the list or select/deselect will remain in the list in that state during the current run of AEMail even if you click on [CANCEL] in the main Configuration screen. In other words, [CANCEL] for the minimum header list has the same effect as [USE]. Clicking on [SAVE] or [SAVE AS] at the bottom of the screen will permanently save the headers you have selected.

There is no way to delete a header once it has been entered in the list and saved except by deleting the  
.headers  
file in the AEMAIL: directory.

This is really not a problem, however, since, if you entered an incorrect header and haven't selected it, it will have no effect on the program.

The four check boxes:

```

[ ] Delete Mail from Server
[ ] Display Full Header
[ ] Strip Duplicate Messages
[ ] Include Header in Reply

```

have the same effect as the Tool Types

```

DELETEMAIL=
,
FULLHEADER=
,

```

STRIPDUPS=  
, and  
HDRINREPLY=  
. A checked condition is the same as a YES  
in the tool type. When you exit from the  
Configuration screen  
with either  
[USE] [SAVE] or [SAVE AS], the corresponding menu items will be checked  
or unchecked depending on the state of these check boxes.

For the EditCall string gadget you must use the full path name of the editor of your choice plus any parameters you want to use on the call. To specify where the file name you are editing goes use %s. An example would be:

```
c:ed %s
```

Below the EditCall: string gadget is a checkmark gadget which is used to tell AEMail that your editor will open on the Workbench screen. If your editor of choice does not open on it's own screen, you must check this item. The AmigaDos editor, ed, does NOT open on it's own screen; therefore you must check this item if you are using ed.

The [DEFAULT] for the EditCall is the information from the EDITOR= Tool Type. If the key word WB; precedes the editor call information in the tool type, the Editor Opens on Workbench item will be checkmarked. WB; will NOT appear in the EditCall string gadget.

If the EDITOR= Tool Type was not provided, the following will be the default EditCall:

```
c:ed %s
```

and the Editor Opens on Workbench item will be checkmarked. This uses the default AmigaDos editor, ed.

If you need to find where your editor is located, [REQ] causes a file requester to appear for selecting the appropriate program file to be loaded into the EditCall string gadget.

The section below the heading Default Reply to Message Parameters is used to set up the default actions when you are replying to a message. The Quote Original Message Text box sets up the default action for quoting the original text in a message. Even though you take the default of not quoting text, you will given an opportunity to change you mind about this when you compose the message.

The Quote Prefix: string gadget indicates what is to be placed in front of each quoted line if an original message is quoted. This, by default, is >; however, you can use any other prefix as the default that you like.

A Quote header: will be placed on the line in front of the quoted material. You can choose what you would like as the default heading and enter it in this string gadget. By default, the header which will initially appear in the Quote Header: string gadget is:

On `&(week)`, `&(date2)`, at `&(time)`, `&(name)` wrote:

The `&` followed by a field name in parenthesis indicates substitution of data from the original message's headers. The values that can be substituted are:

- `&(name)` The Real Name of the sender of the original message. If the Real Name is not available, the sender's UserID will be used instead
- `&(subject)` The subject from the original message. Any RE: or (fwd) will be stripped.
- `&(week)` The day of the week that the original message was sent.
- `&(date)` The date the original message was sent in the form `dd mmm yyyy`, where `dd` is the day of the month, `mmm` is month in the form Jan, Feb, Mar, etc, and `yyyy` is the full 4 digit year.
- `&(date1)` Same as `&(date)`.
- `&(date2)` The date in the form `mmm dd, yyyy`.
- `&(time)` The time the original message was sent in the form `hh:mm xM` where `hh` is the hour on a 12 hour clock, `mm` is the minute, and `xM` is AM or PM.
- `&(to)` The email address the message was sent to. For mailing lists this could be the name of the mailing list if that is what appeared in the To: header.

The Quote Header is designed to be modified by the user and can be changed with this string gadget. This is a permanent change if you select [SAVE] to save the Configuration data, or it can be in effect as the default for only this running of AEMail if you select [USE]. You can always change this default, however, when you  
compose  
a message.

## 1.40 STARTING AEMAIL

### Starting AEMail

AEMail can be started either from the Workbench by double clicking on it's icon or from the shell. It is recommended that AEMail be normally run from the Workbench. The shell invocation is primarily designed for

`mailto:`  
agents in WWW browsers or to call AEMail from another program that passes a message to it.

---

To see how AEMail is invoked from the shell, click  
here

.

AEMail can be run either in an offline or online mode. This means that you do not have to be connected to your Internet provider when AEMail is activated. However, to actually receive or send mail via your Internet provider, you must have your TCP/IP stack (AmiTCP, TermiteTCP, Miami, etc) running and connected to your provider. You can activate AEMail before connecting to your provider or after; it makes no difference.

A convenient menu item have been provided in AEMail to  
Start Net  
, for  
connecting to your provider after AEMail is up and running. A menu item has also been provided to stop your network connection (  
Stop Net  
).

If a specific script is not provided for this purpose, the Start Net and Stop Net menu items can still be used to start and stop your connection to your Internet Service Provider. If you had cleared the script names in the

Configuration screen

,

TCP/IP page

, AEMail will iconify and allow you

to start and stop your network connection manually.

Two command icons have also been provided in the Command Icon tool bar to also perform

Starting and Terminating  
your TCP/IP Network Connection.

You can also automatically activate your Internet connection at program startup by providing the

AUTOCONNECT=YES

Tool Type or by check

marking the Automatic connection to Internet Provider on AEMAIL Start Up in the

TCP/IP Page

of the

Configuration screen

. WARNING: for this to

work, you will need to be able to activate your TCP/IP stack automatically by a script.

To activate AEMail from the Workbench simply double click on the AEMail icon. You can also activate AEMail from the shell, but, if activated in this manner, it will not have access to the configuration information provided by

Tool Types

. It does, however, have access to the

configuration information in the specified AEMail configuration file (either

s:aemail.cnfg

or the file specified with

config=  
in the shell  
calling argument).

AEMail opens on it's own 16 color Public Screen. The Public Screen name is AEMAIL-1. 4 of the colors are defined by the first four colors of the Workbench screen. The following 8 colors are pre-defined with the following colors: Red (13R, 0B, 0G), Green (0R, 15G, 0B), Blue (0R, 0G, 15B), Magenta (15R, 0G, 15B), Yellow (15R, 15G, 0B), Orange (15R, 10G, 0B), Brown (10R, 5G, 0B), and Purple (9R, 3G, 9B). These colors have been preset to provide a consistant color scheme for displaying icons and folder tab colors. Under consideration is the possibility of allowing these colors to be user settable in the future.

Click

here  
for a description of the main AEMail screen.

Since multiple windows are opened by AEMail, the program opens on it's own screen to allow uniformity in being able to push the screen to the back (with all of it's member windows) and back again to the front. The LEFT-AMIGA-M key can be used for this purpose.

You can also iconify AEMail with an iconify bar on the Workbench screen. A menu item in the

Project menu  
has been provided to perform the  
iconify  
action.

When this menu item is selected, the AEMail screen will disappear and a button bar will appear on the Workbench screen with

AEMAIL (Click on Close or with RMB to restore)

in the title. When the iconified bar is selected, clicking either on the close gadget or with the Right Mouse Button (RMB) will restore the AEMail screen.

There is also a hotkey provided for iconifying AEMail. This is RIGHT-AMIGA-I. This same hot key will also take AEMail out of iconify mode. The LEFT-AMIGA-I key will also accomplish this.

Periodically during the running of AEMail, the program will automatically switch to the Workbench screen for executing certain functions and then switch back when the function is complete.

The first thing AEMail does when it is activated is check to see that certain configuration information has been provided. The necessary items are:

POP3 UserID  
Password  
Your email address  
Domain Name  
Edit Call



If any of these items have not been provided, the following requester will be displayed:

The following Configuration items are empty

list of empty items

They are required items!

The Pop Server call and the SMTP call will also be included in this list if the Domain Name is missing.

If this requester is displayed, you will be given the following choices:

[Configure AEMAIL now]

[Cancel AEMAIL]

If you were to click on [Cancel AEMAIL], AEMail will terminate. You can not proceed any further until you have entered these items with the Configuration screen or by providing them as

Tool Types

.

Clicking on the [Configure AEMAIL now] will bring up the

Configuration screen

.

If the

PASSPROTECT=YES

Tool Type was provided (registered users only) the following window will be displayed:

```

|=====|
|0|Enter Password |
|-----|
|          |
|   Enter your new password below   |
|          |
|   [                               ] |
|          |
| [START OVER]           [ CANCEL ] |
|-----|

```

You must enter your password before you can proceed. You will be allowed three attempts to enter a correct password. If the correct password has not been entered after three attempts, AEMail will terminate. If the password is correct, AEMail will continue.

NOTE: since activating the password protection is done by a Tool Type,

password protection is not available when you activate AEMail from the shell. A later version will allow you to set this option with the configuration screens, but currently this feature is only available as a Tool Type.

After verifying that required configuration information has been provided and that correct password has been entered (if required), AEMail will check to see if you are connected to your Internet provider. If it is, connection will be made to your POP server to see if there are any messages available on the server in your mail box. If there are, the following requester will appear:

n Messages Available on the POP Server

Do you wish to receive these messages now?

If you click on the [YES] button, those message will be retrieved at this point. See the

RETRIEVE MESSAGES  
command for details on this process.

If you click on [NO], no message retrieval will take place at this time. You will need to retrieve these messages later using the RETRIEVE MESSAGES command icon.

After AEMail checks to see if any messages are available on the POP Server, it also checks to see if any messages are in the QUEUED folder (messages queued to be sent). If there are, the following requester will appear:

You have n messages queued to be sent

Do you wish to send these messages now?

If you click on the [YES] button, all of the messages in the QUEUED folder will be sent immediately. This is the same as selecting the

Send Queued Mail  
item under the  
Project  
menu or selecting the QUEUED FOLDER and clicking

on the

Send Message Immediately  
command icon.

If you click on [NO], the queued messages will not be sent at this time. You will need to send these messages later using either the Send Queued Mail item under the Project menu or selecting the QUEUED FOLDER and clicking on the Send Message Immediately command icon.

If you successfully connected at program startup the following message will appear in the Title bar of the AEMail screen:

---

TCP/IP session started with Your-POP-Server-Name

If you were not connected the following message will appear in the Title bar:

Not Connected to Your-POP-Server-Name Host

You can disable either or both the POP mail check or the queued mail check at startup by checkmarking the appropriate items in the

TCP/IP Parameters  
page of the  
Configuration screen

.

When AEMail is first activated and you are online and have mail and accept it's transfer, the

message list  
for the INBOX folder will be displayed. As each  
mail message is received you will see it added to the message list of the  
INBOX.

If you are offline or there is no mail or mail is not being checked, the

folder list  
will be displayed. Double clicking on either the name of a  
folder in the list or one of the folder icons will cause the message list  
for that folder to be displayed.

Double clicking on a message in the message list will cause that  
particular

message  
to be displayed.

If you have selected a time increment in the TCP/IP Parameters page of the Configuration screen (the default is 2 minutes), a background process will be started which checks your POP server every few minutes (as specified by the interval) for messages. If there are any messages, the following requester will pop up:

YOU HAVE MAIL!!

n Messages available on the POP Server

Do you wish to receive these messages now?

Replying [YES] to the above requester will start the retrieval of the messages. This requester will only pop up when you are not in the middle of some function such as composing a message, transferring or saving a message, printing a message, or performing configuration changes. It will pop up on the Workbench screen if you have AEMail

iconified

.

NOTE: if you did not specify that you wanted messages deleted from your POP server as you transferred them to your Amiga, the YOU HAVE MAIL!! requester will pop up each time the system checks for mail.

## 1.41 MAIN AEMAIL SCREEN

### The Main AEMAIL Screen

When AEMail first starts, three windows are opened in horizontal bands on the AEMail screen. A window is displayed just below the screen menu/title bar and provides a contextual help title bar and a

Command Icon

Tool Bar. This Tool Bar provides icons for accessing the major functions

of AEMail and consists (from left to right) of the following icons:

Display Folder List

Display Address Book

Retrieve Messages

Display Previous Message

Display Previous Folder's Message List

Display Current Folder's Message List

Display Next Folder's Message List

Display Next Message

Compose a Message

Queue Message for Later Delivery

Send Message Immediately

Save Message To File

Print

Delete/Undelete Message

Copy Messages

Transfer Messages

Start TCP/IP Network Connection

Terminate TCP/IP Network Connection

The window below the command icon tool bar contains a folder strip

set of icons. An icon is provided for each folder with a colored tab to indicate the type of folder (of the user's own choosing - see

Folder Configuration Window  
).

Within each folder icon is a short name (not exceeding 9 characters) for that folder. Below this is the total number of messages minus any deleted messages. It may be followed by the number of un-read messages in parenthesis. If there are unread messages, both numbers will be displayed in red. These messages counts will be updated as messages are added or deleted from the folders.

The height of the folder strip is defined by the font size that is used for the folder name and the folder contents. The font and font size that is used can be selected by the user with the

FLDRFONT=  
and  
FLDRFONTSZ=  
Tool Types. The folder icons will adjust accordingly.

Four pre-defined folders are provided: INBOX for holding retrieved messages, PENDING which holds messages that the user is currently composing and has not decided to send as yet, QUEUED which holds completed messages for later transmission, and SENT which holds messages that have been sent and accepted by the SMTP Server. Since these folders must always be present, you can not delete or change the name of these folders.

A facility has been provided to allow the user to add as many additional folders of his own choosing that he wants to the list of folders (see

Folder menu  
).

As each new folder is created, an icon will be created and placed next to the last folder icon. Any number of folders can be created and the folder strip has the ability to scroll horizontally so that all of the folder icons can be viewed and accessed.

You can use the menu items  
Transfer...  
and  
Copy...  
under the

MESSAGE menu  
to transfer or copy messages between folders.

The last window is placed below the folder strip and is used to display either

folder lists  
,  
address books  
,  
message lists  
, or

messages  
themselves.

If a non-interlaced screen is provided, the message and address book displays will start below the Command Icon Tool Bar (overlying the folder strip) rather than below the folder strip. This is done to provide more room for the message or address book display since the number of displayable lines is limited.

Other

windows

are also provided which cover the entire screen below the title bar for the purpose of providing configuration information and for composing messages.

While the Command Icon Tool Bar and the folder strip are being displayed, a contextual help line is provided in the Command Icon Tool Bar window title bar below the screen's title bar. As you pass the mouse cursor over any command or folder icon, a description of that command or folder will be displayed in the window title bar. The main window menu bar should also be active whenever the mouse pointer moves to the folder strip or above.

All command and folder icons are surrounded by a raised box. Whenever a command or folder is selected, the box will become depressed.

## 1.42 INVOKING AEMAIL FROM THE SHELL

### Invoking AEMail from the Shell

The shell invocation is primarily designed for

MailTo:

agents in WWW

browsers or to call AEMail from another program that passes a message to it. When AEMail is invoked from the shell, there are six optional argument that can be used as follows:

```
AEMail [email-addr-of-recipient-of-email] [config=configuration_file]
      [pubscr=browser-screen-name] [mail_dir=full-path-to-mail-directory]
      [message=full-path-name-of-message-to-send] [CONT]
```

If either the recipient's email address is present or the message= argument is present, AEMail assumes that we are using AEMail as a MailTo agent or you are trying to queue or send a message composed outside of AEMail. AEMail will load and immediately display the

Compose message  
window.

If the message= argument was used, you will be in the edit mode of the compose screen. You can either edit the supplied message or immediately [Save in Pending], [Queue Message], [Send Message Now], or [Cancel Message]. You can also perform any other action on the message including adding headers, adding attachments, or adding your signature block (see Compose Message Window).

The message that the message= argument points to must be a complete message with at least one header. It is suggested that you include at least a To: and Subject: header. These should be followed with at least one blank line before the body of the message.

If both the mail address of the recipient argument and the message= argument are used, the mail address will take precedence over the To: header in the message.

The recipient's name in either the mailto argument or the To: header in the message referenced by the Message= argument, can be a nickname present in your

Address Book

. This is a convenient way to send messages to groups where you are periodically adding or deleting members from the group. Just use the group nickname in the To: address to send the message to the entire group.

If the message= argument is not present but a recipient's email address is present, you will enter the compose window in a new message mode. You must compose a message or Cancel the operation in order to proceed.

When you exit from the Compose window by clicking on one of the action requesters at the bottom of the window, AEMail will terminate automatically unless the CONT keyword was present in the argument stream. If CONT is used, AEMail will continue so that you can perform other AEMail functions. You will then have to quit using the

Quit...

menu item in the

Project Menu

.

The config= keyword parameter is used to specify a configuration file

other than the normal s:aemail.cnfg file. All permanent data on the ←

AEMail configuration to be used will be in this file. If you wish to invoke AEMail from the shell and have it run normally (not as a MailTo agent), you can use the config= parameter to direct AEMail to use a different configuration file on startup. To use AEMail in this manner, you could simply type:

```
AEMAIL config=name_of_configuration_file
```

The mail\_dir= is used to override the AEMAIL: assignment for the mail directory. You must specify a full path name for this alternate mail directory.

If AEMail is used as a mailto: agent for your browser and that browser passes its public screen name along with the userid, you can use the keyword argument pubscn= to specify that public screen. AEMail will then bring the browser's screen to the front when AEMail terminates. If this argument is missing and the browser opens on its own screen but does not, itself, bring the screen to the front when it returns from the mailto: command, you might have to manually bring the browser's screen to

the front with the LEFT-AMIGA M key.

When you invoke AEMail from the shell with an email address parameter or a message= argument, you normally will not be able to use any of the AEMail menus or commands unless the CONT key word was used. However, AEMail will always check for Mail on your POP Server and for Queued messages to send before displaying the Compose message screen (see

```

        initial AEMail action
        ) and ask for configuration data if required
parameters are not present in the s:aemail.cnfg file or the config=
configuration file.
```

If you invoke AEMail from the shell without any parameters, AEMail will behave the same as if it was invoked from the Workbench by clicking on it's icon except that tool types will not be utilized. (See

```

Starting AEMail
.
```

## 1.43 USING AEMAIL AS MAILTO AGENT

### USING AEMail AS A "MailTo" AGENT

A number of Amiga WWW Browsers allow you to select an external Mail agent to be used for sending email when a mailto: HTML link is specified. AEMail can be used as such a mail agent.

On the configuration screen for your browser specify AEMail as your mailto: agent by using the full path name of AEMail and the token for specifying the mailto: email address.

As an example, for

```

    Voyager
you can specify the following:
```

```

Work:AEMail/AEMail %h           or
AmitTCP:bin/AEMail %h          (if you are using AmitTCP)
```

as the mailto: helper application in the Network Settings: Other Voyager menu or when you install Voyager. Be sure and save your Voyager settings once you make the change.

The %h in the above specification is Voyager's token for where to place the email address. The specification also assumes that AEMail was installed in either the Work:AEMail or the AmitTCP:bin drawer. Use the correct full path for where you installed AEMail. Voyager does not require a pubscr= argument.

Other browsers, if they use this capability, may have a different way to specify the mailto: user agent and the token for specifying where to place the email address. The token may change from version to version of your browser.. Consult your browser documentation for how to do this.



In early versions of AWeb, for instance, you would bring up the Change Settings menu and select External programs in the cycle gadget. You entered the mailto: application call with two string gadgets. The first string gadget specifies the Command string which would be Work:AEMail/AEMail (again the full path name) and the second string gadget specifies the Argument string which would be %s pubscn=%s. AWeb does use the public screen argument. Later versions of AWeb used different tokens for these specifications. Consult your AWeb documentation for what should be used.

The documentation for IBrowse, unfortunately, does not provide any information on how to set up an external mailto: agent. However it can be done. Follow these steps:

```
Select the Preferences menu in IBrowse
Select Network
Select "Email & Telnet" tab
Under "Mailto:" Set the External mode
For the command give the full path name of the AEMail program and
follow it with %h (like in Voyager)
```

```
example: Work:AEMail/AEMail %h
```

```
Select O.K.
```

```
Be sure to "Save Settings" under the Preferences menu
```

In order for the mailto: agent to work properly, AEMail must NOT be running when you start up your browser. When you click on the mailto: link, AEMail will be loaded, the Compose message window will be displayed, you will then be able to compose and send the message, and AEMail will terminate.

If you have a custom configuration file, you should also add the argument config=name-of-config-file to the mailto calling argument. As an example, using Voyager:

```
Work:AEMail/AEMail %h config=name-of-file
```

```
See
```

```
Invoking AEMail from the Shell
```

```
.
```

## 1.44 EDITING STRING ENTRY GADGETS

Editing String Entry Gadgets

A number of windows in AEMail use string entry gadgets for entering data. These gadgets look like long rectangles with a cursor which allows you to type in the data you want. There are a number of special key combinations that can aid you in the entry process. These are:

Cursor Left	Move cursor to previous character
Shift Cursor Left	Move cursor to the beginning of the string
Cursor Right	Move cursor to next character
Shift Cursor Right	Move cursor to the end of the string
Del	Delete the character under the cursor
Shift Del	Delete from the character under the cursor to the end of the line
Backspace	Delete the character to the left of the cursor
Shift Backspace	Delete from the character to the left of the cursor to the start of the line
RETURN or Enter	Terminate input and deactivate the gadget
Tab	Terminate input and activate the next string gadget
Shift Tab	Terminate input and activate the previous string gadget
Right Amiga q	Undo (cancel) the last editing change to the string (Note: either q or Q will work)
Right Amiga x	Clears the string (either x or X will work)
Right Amiga v	Paste the contents of the current clipboard unit to the string (either v or V will work)
Right Amiga c	Copy the string to the current clipboard unit (either c or C will work)
Right Amiga u	Change the current clipboard unit
Right Amiga U	Display a list of the current active clipboard units and their contents

In addition, the following editing functions are available if the IControl preferences editor has "Text Gadget Filter" selected.

Note: either the upper or lower case alphabetic character will work.

Ctrl A	Jump cursor to the start of the string
Ctrl H	Delete the character to the left of the cursor
Ctrl K	Delete from the character under the cursor to the end of the line
Ctrl M	Same as Return or Enter
Ctrl W	Delete the previous word
Ctrl U	Delete from the character to the left of the cursor to the start of the line
Ctrl X	Clears the string
Ctrl Z	Jump cursor to end of the string.

All of the above characteristics of string editing are standard with the Amiga with the exception of those keystrokes that involve the clipboard. The clipboard functions are specific to AEMail, although other programs may have similar functions using the same key combinations built into them. For more information on using the clipboard see

Using the Clipboard with AEMail

## 1.45 USING THE CLIPBOARD WITH AEMAIL

### Using the Clipboard with AEMail

On the Amiga, the clipboard provides a facility for passing information from one program to another, or for saving information for re-use in the same program. AEMail utilizes the clipboard in several ways:

Each

```

        string entry gadget
        has the ability of copying the current contents
of the string to the clipboard or of pasting the contents of the clipboard
to the string gadget. In that manner information can be saved and re-used
at a later time.
```

You can also obtain a line from a message, edit it, and save that to the clipboard; or you can save the entire contents of the message body to the clipboard. If you are using an editor that also supports the clipboard, you can retrieve information that you previously copied to the clipboard and insert it into a message you are composing.

If your browser supports the clipboard, you can use the above method to capture a URL that is embedded in a message and then paste it into the browser's URL string.

AEMail supports the use of multiple clipboards (up to 256 separate clipboard units), so different information can be copied to separate clipboard units and retrieved later. If other external programs also support multiple clipboard units you can pass separate pieces of information to those programs.

With each string entry gadget in AEMail you can use Right Amiga C or Right Amiga c (either upper or lower case c) to copy the information from a string to a clipboard unit. Likewise, you can use Right Amiga V or Right Amiga v (upper or lower case v) to paste the information into the string gadget. This works with all string gadgets except the

```

        Enter Password
        or
"Change Password" (in the
        Identity Page
        of the
        Configuration Screen
        )
string gadgets.
```

Generally speaking when you use the paste operation in a string gadget, it will replace the contents of the string gadget with the contents of the clipboard. The exception to this is with the To:, cc:, and bcc: string gadgets on the

```

        Compose Message Window
        and when editing a string that is
captured from a message (see below).
```

For the To:, cc:, and bcc: string gadgets, the clipboard data will be ADDED to what was previously in the string gadget. Any added email addresses added with the paste operation will be separated from the

previous addresses with a comma.

If you double click on a line in a message that is being displayed, a special window will open at the top of the screen which looks like this:

```

|=====|
|o| Edit and save message line to clipboard |
|-----|
|
| [Message line appears here                ] |
|
| [ SAVE CLIP ]           [CHANGE CLIP UNIT]   [ CANCEL ] |
|_____|

```

You can use the copy and paste to and from the clipboard unit while you are editing within the string entry gadget above. However, if you paste to the string, the data in the clipboard will be inserted at your cursor position. This is different from all other string entry gadgets where the pasted data replaces whatever was in the string gadget before. This feature for the editing and saving of a line from a message can facilitate building a clipboard line from different lines in the message. To do this, edit the first line so that just the portion that you want added or inserted to a second line remains in the string. Copy this to a clipboard unit ([SAVE CLIP]). Then double click on a second line. Position the cursor where you want the first clipboard data to appear and perform the paste operation. The previously copied data will be inserted at that point.

When you click on either the [SAVE CLIP], [CANCEL], or the close gadget at the top of the window, the edit window will disappear. Clicking on the [SAVE CLIP] will save the edited string to the current clipboard unit and clicking on the [CANCEL] or close gadget will exit without saving.

Warning: using the copy function from within the string gadget will always copy the current contents of the string to the clipboard whether or not you click on the [CANCEL] or the close gadget later. There is no way to undo this operation. However, using the copy function from within the string gadget will not close the edit window.

Clicking on the [CHANGE CLIP UNIT] in the edit window or typing Right Amiga u (lower case u only) from any string gadget will bring up a special window that will allow you to change the current clipboard unit. This window looks like this:

```

|=====|
|o|Enter Clipboard Unit |
|-----|
|
| [          ] (0 - 255) |
|
| [ OK ]       [CANCEL] |
|_____|

```

You can enter any clipboard unit between 0 or 255 in the numeric gadget. If you type RETURN after entering the number or click on [OK], the clipboard unit you entered will become the new clipboard unit and the window will close. Clicking on the [CANCEL] gadget or the close gadget will close the window without changing the current clipboard unit.

Since you may have data stored in multiple clipboard units and may forget which clipboard unit has what data, another feature has been provided. If you type Right Amiga U (upper case U - shift and u) while you are editing a string, the Clipboard Display window will be shown which looks like this:

```

|=====|
|o| Contents of Clip List |
|-----|
| Clip Contents |
| ===== |
| | 0 Contents of clip 0 | | |
| | 2 Contents of clip 2 | | |
| | | | |
| | | | |
| | | | |
| | | | |
| ===== |
| | | | |
| [ OK ] [NEW CLIP UNIT] [CANCEL] |
|-----|

```

This shows all of the clipboard units that have data stored in them and the contents of each clipboard unit in a listview. Clipboard units may be skipped as shown in the illustration above. Since the contents of a clipboard can be a complete file, the first non-blank line will be displayed and leading spaces will be stripped. Only text clips will be displayed. Only 40 characters can be displayed. If the line is longer than 40 characters, the first 30 characters will be shown followed by three periods and the last 7 characters.

Only clips with data will be shown. The current clipboard unit will be highlighted if it contains data. Since it is possible to have a clipboard unit assigned WITHOUT any data, you may see none of the units highlighted. You can change to one of the clipboard units shown by clicking on it (it will become highlighted) and then clicking on [OK]. You can also change to a clipboard unit not shown by clicking on [NEW CLIP UNIT]. [CANCEL] and the close gadget will close the window without any changes taking place.

A further feature of this window is to provide an automatic paste capability by double clicking on one of the units being displayed. That will automatically paste the contents of the selected unit to the string. If the selected clip is a file, only the first non-blank line will be pasted and leading spaces will be stripped. The Right Amiga V method of pasting from within a string gadget also has this feature for multiple line files.

Another clipboard feature of AEMail is the ability to save the body of messages and text attachments to the clipboard. When you click on the

[SAVE TEXT]

or  
 [ATTACHMENT]  
 button when you are displaying a message you  
 will be given the chance to save the text as a CLIP and also to change the  
 clipboard unit. See also the  
 Message Display Window

## 1.46 FILTERING MESSAGES WITH AEMAIL

### Filtering Messages with AEMail

What is message filtering? Message filtering is the ability to direct incoming messages to specific folders or to automatically exclude certain messages from being stored in the system.

AEMail has a very powerful message filtering system. It can direct (or exclude) messages based upon information in the To:, From:, Reply-To:, Subject:, cc:, bcc:, or Date: headers and (for registered users only) any other header or text in the body of the message. It can also use the fact that a message is a reply, has attachments, or is forwarded as filtering criteria. Information in the header or body text that is checked can be a word or phrase and wild cards can be used. Information can also be case sensitive or insensitive as the user desires.

AND and OR relationships can also be made with information coming from different headers.

Filtering criteria is defined in the folder description which can be modified or created by using either the

Edit  
 or  
 New  
 sub-topic under

the

Folders menu  
 . The description under the  
 Filter Selection Window  
 gives a complete description on how to set up the filtering ←  
 criteria.

Setting up the appropriate filtering criteria for any folder designed to receive incoming messages will cause incoming messages (either from your POP server or from files) to be stored in that folder rather than the INBOX.

Setting up filtering criteria for the INBOX will automatically exclude any message meeting that criteria from being stored in the INBOX. In other words, filtering criteria in the INBOX is used to prevent certain messages from being stored on your system.

Filtering criteria can not be set up for folders designed for messages sent out of your system. Only messages as they are being received are checked. Filtering is done "on the fly" as a message enters the system.

## 1.47 COMMAND ICON TOOL BAR

### COMMAND ICON TOOL BAR

This Command Icon Tool Bar provides icons for accessing the major functions of AEMail and consists (from left to right) of the following icons:

Display Folder List

This icon looks like a file cabinet.

Display Address Book

This icon looks like a closed book with the letter A on its cover. ←

Retrieve Messages

This icon looks like an envelope with an arrow coming in.

Display Previous Message

This icon is a long yellow backward arrow.

Display Previous Folder's Message List

This icon is a short backward arrow.

Display Current Folder's Message List

This icon looks like a folder.

Display Next Folder's Message List

This icon is a short forward arrow.

Display Next Message

This icon is a long yellow forward arrow.

Compose a Message

This icon looks like a sheet of paper with a pen on it.

Queue Messages for Later Delivery

This icon looks like a mailbox.

Send Messages Immediately

This icon looks like an envelope with an arrow going out.

Save (Export) Message To File

This icon looks like a diskette.

Print

This icon looks like a printer.

Delete/Undelete Messages

This icon looks like a garbage can.

Copy Messages

This icon looks like two sheets of paper, one laying over the other. ←

Transfer Messages  
This icon looks like a sheet of paper with arrows pointing to the right. ←

Start TCP/IP Network Connection  
This icon is a horizontal jagged line

Terminate TCP/IP Network Connection  
This icon is a horizontal jagged line with a red slash through it. ←

Click on the links above for a description of each of the Command Icons and the functions that it performs. Clicking on the Command Icon while in AEMail will activate the function described.

## 1.48 COMMAND ICON TOOL BAR/Display Folder List

### DISPLAY FOLDER LIST

Clicking on the Display Folder List icon will cause the folder list to be displayed in the lower window. This list shows each folder with its short name (INBOX, PENDING, etc), a description of the folder, the number of unread messages in the folder, and the total number of messages in the folder.

Unlike the count displayed in the folder icon, the total number of messages includes any messages marked for deletion.

## 1.49 COMMAND ICON TOOL BAR/Display Address Book

### DISPLAY ADDRESS BOOK

Clicking on the Display Address Book icon will display the

Address Book window

Each address book entry contains three fields: Nickname, Real Name, and UserID (Address). In addition, entries can be provided for groups with a distribution list. The group is identified with the heading DISTRIBUTION LIST along with the number of items in the list in the top most UserID field. The UserID's for the members of that list are shown below that heading.

---



For items in the distribution list, real UserID's or Nicknames can be used. An item in the distribution list can also be another distribution list (In this case, only a Nickname can be used). All nicknames are expanded to Real Name and UserID when mail is sent.

A checkbox item, called Expand to the right of the Address Book headings allows the user to either expand and show all members of the group or shrink the address book so that only the group header is displayed. This item is normally checked indicating the groups are in expanded mode. If the check mark is removed, the group entries will shrink showing only the group headings. This feature is only available to registered users.

Currently, Address Book entries are sorted by Nickname and group entries are interspersed with single entries. Also Real Names are presented as first name followed by last name rather than last name, first name.

If you are displaying a message, or have a message selected, when you click on the Address Book icon, the Reply-To: address, if present, will be transferred to the UserID address in the Address Book. If the Reply-To: address is not present, the From: address will be used. If a Real Name is present in the address it also will be transferred. You can force the From: address to be transferred by holding down the shift key when you click on the Address Book icon. This process facilitates transferring names and UserIDs to the Address Book. Please keep in mind that Reply-To: addresses normally do not have real names associated with them, but From: addresses many times do. If you want the real name you may have to hold down the shift key when you click on the Address Book icon.

The first time AEMail is loaded, a special Address Book entry with a Nickname of AEMAIL is created. This entry can be used to send bug reports and messages about AEMail to my email address.

Address Book data is stored in a file in your AEMAIL: directory called

```
.addrbook
```

```
.
```

## 1.50 COMMAND ICON TOOL BAR/Display Previous Message

### DISPLAY PREVIOUS MESSAGE

When you are

```
    displaying a message
```

```
    , clicking on this icon will display the
```

previous message in the

```
    message list
```

```
    . If you are at the first message in the
```

list, a requester will be displayed informing you of this.

---

## 1.51 COMMAND ICON TOOL BAR/Display Folder's Message List

### DISPLAY PREVIOUS FOLDER'S MESSAGE LIST

Clicking on this icon will display the previous folder's message list

.

### DISPLAY CURRENT FOLDER'S MESSAGE LIST

Clicking on this icon will display the current folder's message list. This is one way to get back to the current message list when you are displaying a message and the folder list is obstructed.

### DISPLAY NEXT FOLDER'S MESSAGE LIST

Clicking on this icon will display the next folder's message list.

## 1.52 COMMAND ICON TOOL BAR/Display Next Message

### DISPLAY NEXT MESSAGE

When you are

displaying a message

, clicking on this icon will display the next message in the

message list

. If you are at the last message in the list, a requester will be displayed informing you of this.

## 1.53 COMMAND ICON TOOL BAR/Save (Export) Message to File

### SAVE (EXPORT) MESSAGE TO A FILE

This function can be activated from either the icon strip or the Export... sub-item in the

Messages menu

. A message must be selected before activating this function and

multiple messages can be selected

. A message that is currently being displayed is considered a selected message.

You can save multiple messages as a block of messages or as individual messages. If you have selected multiple messages a requester will be

displayed as follows:

More than one message marked to save

Do you want to save them as a group  
or Individually

If you select Individually  
a File Requester will appear  
for each message

[Save as Group]            [Save Individually]

Unless you are saving the messages as a group, a requester will also be displayed for each message which will describe the message as to Date, From, To, and Subject and ask you if you want to perform the requested action. Selecting [SAVE] will display a file requester in which you will be asked to enter the file name you want the message saved as, and selecting [CANCEL] will not save the current message.

If you are saving the message as a group, only the file requester will appear.

The complete message, including all attachments, is saved in the format in which the message was received from the POP server except that CARRAGE-RETURN/LINEFEED sequences are stored as LINEFEEDs alone. Also, the message ending sequence (.<CR><LF>) is eliminated and any embedded ..<CR><LF> are changed to .<LF> as they would normally appear in a message.

If the messages are saved as a group, each message will have a special header separating it from the following message. This header consists of a line feed followed by:

From [your UserID]@[Your POP Server name] [date]

Only the special header (not the line feed) will appear for the first message.

This facilitates importing a group of messages back into AEMail. (See the

Retrieve Messages  
command and the menu item  
From Local File...  
under

the

Retrieve Msgs  
menu.)

If you want to save the body of the message or an attachment in its converted format, you can do that with either the [SAVE TEXT] gadget in the

message display window  
or with the  
Attachment Requester  
that can be

brought up when you display a message with attachments.

## 1.54 COMMAND ICON TOOL BAR/Print

### PRINT

This function can be activated from either the icon strip or the Print sub-item in the

Messages menu

. You must select the messages you want printed prior to selecting this function.

Multiple message selection

works with

this function. If you don't select any messages you will print a list of the this command. If no messages have been selected, you will be asked if you want to print a list of the messages in that folder. Also, if this icon is selected while you are in the Address Book, the address book contents will be printed.

Each of the messages will be printed in the order that they appear in your

message list

. All selected messages will be printed whether they are marked for deletion or not.

A progress indicator will appear as each message is being sent to your printer which shows the percent being printed and the total bytes being printed. This progress indicator has an [ABORT] button which allows you to terminate the printing. However, beware, most printers have a substantial buffer which will probably receive all of your messages quite quickly. Once the messages are in the printer's buffer, the printing can not be cancelled without turning your printer off.

A heading line will be printed on each page of the listing which contains the following information:

Message Sent on mm/dd/yy (dow) at hh:mm [AM/PM], [from/to] [name] Page n

where

mm/dd/yy is the date the message was sent (received) or composed,

dow is the day of the week the message was sent (received) or composed,

hh:mm is the hour and minute the message was sent (received) or composed using a 12 hour clock,

[AM/PM] is either AM or PM.

[from/to] if the message was received you will see "from", and if you composed or sent the message you will see "to",

[name] is the full name of the sender or nickname of recipient,

n is the page number.

On the first page only, if there are attachments, the following line will appear below the heading line:

This message has attachments (See last page for list).

On a separate page, after the message, the attachment list will appear, providing the "Include Attachment List in Print Out" item is checkmarked in the

General Parameters  
portion of the  
Configuration  
screen. Printing

the attachment list is the default action.

If attachments are a Text or Message type and are either 7-bit, 8-bit, or quoted-printable encoding format they will be printed following the body of the message. Other types of attachments you will have to save to a file and print the file with an appropriate printing program.

Note: no check is made whether a selected message is deleted or not. If a deleted message is selected it will be printed anyway (this is probably desirable in certain circumstances). If you don't want to print it, de-select it!

This function can also print a list of all messages in a folder. To do this, DO NOT select any messages in the folder. A requester will appear when you select either the printer command icon or the Print menu item which says:

No messages selected to print!

Do you want to print a list  
of all the messages in the  
[name of folder] folder?

[YES]

[NO]

By selecting [YES] you will print a list of the messages. Messages will be printed in the order that they appear in the message list.

Selecting [NO] will terminate the printing function.

Printing uses your Preferences Printer. You should set it up properly before executing AEMail, or you can set it up while in AEMail by using the

General Parameters  
page on the  
Configuration  
screen. You can also

specify a print file that the output will be directed to.

---

As a default AEMail will space 4 lines down before starting to print. This Top Margin, however, can be changed in the General Parameters section of the Configuration screen.

## 1.55 COMMAND ICON TOOL BAR/Delete/Undelete Messages

### DELETE/UNDELETE MESSAGES

This function can be activated from either the icon strip or the Delete/Undelete sub-item in the

Messages menu  
. It will delete OR undelete all messages that have been selected in a message list  
.

Whether deleting or undeleting takes place depends on the current status of the message. If it is currently marked for deletion, it will be undeleted.

This function only marks (or unmarks) messages for deletion. The messages will actually be deleted only when AEMail exits. The message counts in the folder icons, however, will only represent undeleted messages. You can also suppress the display of deleted messages in the message list by unchecking the

Show/Deleted Messages  
item under the  
Messages  
menu.

## 1.56 COMMAND ICON STRIP/Compose a Message

### COMPOSE A MESSAGE

The Compose a Message function brings up the  
Compose Message window  
so that

you can enter information about the message you are about to compose. The information you enter includes the Nickname or UserID of the recipient of the message, the subject and whether or not you want to send cc's to anyone.

A special [Call Address Book] button is provided that allows you to call up an abbreviated version of the  
Address Book

. By clicking on an address book name you can transfer the nickname for that address to any of the To:, cc:, or bcc: fields. You select the field you want to transfer the nickname to by a special cycle gadget in the address book display.

---

When the Address Book is displayed from the Compose window, all groups will show as the group header and number of entries in that group. For AEMail registered users, an [Expand] checkmarked gadget will allow you to expand the groups so you can see all of the entries. Exiting from the Address Book display is accomplished by double clicking on an address (it will be transferred to the appropriate field and then the Address Book will be closed) or by clicking on the Close gadget in the window border or at the bottom of the window.

To compose the message text you would click on the [Compose/Edit Message] which will call up your editor. When you save and exit from the editor, you will be brought back to the Compose Message window.

You can specify the format that you want your text to be sent as. You can select between 8-bit, 7-bit, quoted-printable, or encoded binary (BASE64). This facilitates sending messages with foreign character sets through gateways that only handle 7 bit data. The default is 8 bit. Both quoted-printable and encoded binary are 7 bit schemes for representing 8 bit data. When you display a message which is in either quoted-printable or encoded binary, it will be displayed correctly.

You can also specify any attachments you want to send with the message through the

Add Attachment Requester  
or you can specify a signature file

or additional headers.

After supplying the required information, you can then save your message into either the PENDING or QUEUED folder or send it directly. If you select [Send Message Now] you MUST be connected to your Internet provider.

If a message has been selected in any folder, except the PENDING, QUEUED, or SENT folders, before clicking on the COMPOSE MESSAGE icon, the compose will be treated as a reply to the selected message. The original Reply-To address for the message you are replying to will appear in the To: field on the Compose window. If the Reply-To: address is not present the From: field will be used as recipient of the reply. You can force the From: field to be used by holding down the shift key when you click on the Compose icon.

If you are not interested in creating a reply, you can change to creating a new message to be sent to the same (or different) recipient, or you can forward the message to a different recipient.

If the message selected was in the PENDING or QUEUED folder, you will be allowed to either edit the selected message or create a new message. If you edit the message it will be stored back into the folder you selected or will be sent (if you click on [Send Message Now]). The old message will be automatically removed from the system.

If the message selected was in the SENT folder you will only be able to create a new message.

---

## 1.57 COMMAND ICON TOOL BAR/Send Message Immediately

### SEND MESSAGE IMMEDIATELY

With the Send Message Immediately function an attempt will be made to send the Selected Message(s) to their recipients. The messages to be sent must be in either the PENDING or QUEUED folder. The messages will be sent from the PENDING folder only if the PENDING folder is selected; otherwise they will be sent from the QUEUED folder.

If messages are selected (see  
Multiple Selection  
) , a requester will appear  
that asks:

Do you wish to send the entire [pending/queued] folder  
or just selected messages?

The choices available are:

[ENTIRE FOLDER]      [SELECTED MESSAGES]      [CANCEL SEND]

If no messages have been selected or all of the messages in the folder are selected, the entire selected folder will be sent without a requester appearing. Deleted messages are never sent.

If there are no undeleted messages in the selected folder a notification requester will appear that indicates that "No messages available to send".

A check will then be made to see if you have an active connection to your Internet provider. If you do not, a requester will be displayed which informs the user that we are in offline mode and that the messages can not be sent.

If you are connected to your Internet provider, a message will appear in the top title bar that says "Connecting to SMTP Host to send mail". Once the connection is made. AEMail will display "Starting to send n messages" where n is the number of messages selected to send. If we are unable to connect or an error is reported back from your Internet provider, a message will appear in the title bar showing the nature of the error and the messages will not be sent.

Sometimes, if the error message is from your Internet Provider, you will not be able to see all of it. If your  
TCPLOG  
is active, you will be able  
to see it on the Log File, however.

A progress window will also be displayed which will show the current number of the message being sent, the total number of messages being sent, the percentage of the current message already sent and the total bytes in the current message being sent. The percentage will be shown as both a number and on a graphic slider.

If there is more than one recipient for the message, the progress



indicator will also show Sending to n of n recipients of message as each recipient of the message is contacted. This way you will see the progress of contacting recipients for large groups of recipients.

This progress window also has an [ABORT] button which allows you to terminate the sending of the current and all remaining messages to your SMTP Server.

All nicknames used in To:, cc:, and bcc: header fields will be expanded to the form: Real Name<userid>. Group nicknames will be expanded to the Real Names and userids of all members of the group, or, if Send Header Only is set for that group, only the group header will be displayed in the To: field.

When each message is successfully sent, the following message will be displayed in the upper title bar:

```
Mail n of n successfully sent to [To: addressee]
```

The n in the above message indicates the message number and the total messages to be sent. The [To: addressee] indicates who the message was addressed to. If it was addressed to multiple addressees, the first addressee will appear followed by , et al....

The message will also be placed in the SENT folder and marked as deleted in the PENDING or QUEUED folder.

In the current version of AEMail, the send process operates in the same execution mode as AEMail. This means that you can not perform any other AEMail operation until the message is either rejected by your Internet provider or successfully received by your provider (unless you abort the process). In a future version, this process will be moved to a background process so that you can perform work in AEMail while the sending of the message proceeds.

## 1.58 COMMAND ICON TOOL BAR/Queue Message for Later Deliverly

### QUEUE MESSAGE FOR LATER DELIVERY

This function is provided to allow the user to mark messages that you want sent later. Normally, NO MORE EDITING OF THESE MESSAGES should occur once they are moved to the QUEUED folder. However, AEMail does allow this to occur. Messages can be moved back to the PENDING folder with the

```
Transfer...
```

```
item in the
```

```
Messages
```

```
menu. Messages for queuing must come
```

from the PENDING folder. The messages can also be placed in either the PENDING or QUEUED folders (or sent) by the

```
Compose Message
```

```
window.
```

You can send these messages manually from the QUEUED folder any time you want by either sending the entire folder or individual messages in the folder. This is done by selecting the QUEUED folder and clicking on the

```
SEND IMMEDIATE
icon or by selecting the
Send Queued Mail
item under the
Project
menu.
```

AEMail also allows the user the option of sending queued messages automatically when AEMail is first activated, or when the program terminates provided you are connected to your Internet provider (see

```
STARTING AEMAIL
). AEMail will also perform this check when you make
connection to your Internet provider through the StartNet script unless
you have disabled this feature with the
TCP/IP Parameters
page of your
Configuration screen
.
```

With this option you can compose messages when you are in an off-line mode, save them in PENDING while you are working on them, and then QUEUE them when you are satisfied with the message you want to send. The Queued messages are then automatically sent when you log onto your Internet Provider by the StartNet command.

If messages are selected in the PENDING folder when you click on the QUEUE MESSAGE icon, a requester will appear that asks:

```
Do you wish to queue the entire pending folder
or just selected messages?
```

The choices available are:

```
[ENTIRE FOLDER]      [SELECTED MESSAGES]      [CANCEL QUEUING]
```

If no messages have been selected, the entire PENDING folder will be queued without a requester appearing. Deleted messages in the PENDING folder are never queued.

If there are no undeleted messages in the PENDING folder a notification requester will appear that indicates that "No messages available to queue".

The messages that are selected will be placed in the QUEUED folder and removed from the PENDING folder.

## 1.59 COMMAND ICON TOOL BAR/Retrieve Messages

---

## RETRIEVE MESSAGES

When the Retrieve Messages function is selected, AEMail will attempt to connect to the POP host server and transfer any mail at the server to your AMIGA.

If you are in offline mode (you are not connected to your Internet Service Provider or AEMail can not connect, for some reason, to your POP server), see

Retrieving Messages from Files

If you are online with your Internet provider and connection can be made to your POP mail server, all messages stored on the server will be transferred to the AMIGA. They will be stored as individual messages in the AEMAIL: directory with cryptic file names (see  
messages  
file).

A progress window will also be displayed which will show the number of the current message being received, the total number of messages being received, the percentage of the current message already received and the total bytes in the message being received. The percentage will be shown as both a number and a graphic slider.

This progress window also has an [ABORT] button which allows you to terminate the receipt of the current and all remaining messages from your POP Server.

PLEASE NOTE: The abort process only aborts the receipt of messages into the AMIGA, It does NOT abort the transfer of data from the POP Server. While AEMail disconnects from the server, the server may be unaware of this and continue to send the remainder of the message. If AEMail attempts to re-establish contact with the Server while it is still sending the message AEMail may start to receive the middle of the previously requested message. AEMail has been programmed to recognize this and will temporarily report that the POP connection could not be established. Once the POP Server finishes transferring the message, it should become available for another connection.

The progress window will be shown both when retrieving messages from your POP server and from files, however, if you are retrieving a message stream, AEMail will not be able to correctly determine the number of messages being retrieved. Therefore the "n of n" indicator will be incorrect.

If mail on the server is to be deleted, the

Delete Host Mail  
item in the

Retrieve Messages

menu must be checked. If this menu item is not checked, mail will NOT be deleted on your POP server. This has no effect when you are retrieving messages from a file. NOTE: the AEMAIL

Installation

script automatically defaults to deleting host mail. You will have to un-check this item if you want to keep mail on your POP Server. ←

Since old mail may not be deleted on your server, a menu item has been provided under the

- Retrieve Messages
- menu called
- Excl Dup Msgs
- . When

this item is checked duplicate messages from the mail server which are currently stored in any incoming folder will not be stored again. The only folders not checked for duplicate messages are the PENDING, QUEUED and any folder designed to hold SENT messages. Again, the default action with the installation script is to delete duplicate messages.

Currently, like sending messages to your Internet provider, the retrieval process is run in the same execution mode as AEMail. This means that all of the messages must be received from the POP Server before any other AEMail process can take place. Again, a future version will move the retrieval process to a background process so you can proceed with other AEMail functions while retrieval takes place.

You can be running another program on your Amiga, however when the message retrieval takes place. If you are in iconify mode when retrieval takes place it will be done totally in the background although you will see the You have mail requester (see below).

Every time a new message is retrieved AND stored, the total and new message counts in the folder list AND the folder icon strip will be updated. Also the top title bar will display the following message:

```
Message n of n retrieved[/deleted] from [POP server/file], [not] saved
```

The first n indicates the current message number and the second n indicates the total number of messages being retrieved. (NOTE: This message will also appear when local mail files are being transferred, but the counts may not be accurate if you are retrieving from a message stream. Also, the retrieval process from local files is so fast, you may only see the message for the last retrieval.)

The /deleted will appear if the message has been deleted on the POP server and not will appear if the message was a duplicate and was not saved.

You can check for messages on your POP server and retrieve these messages manually any time you wish by clicking on the RETRIEVE MESSAGES icon. Also, the user has the option of retrieving messages automatically when AEMail is first activated (provided you are connected to your Internet provider), each time you execute your

- StartNet
- script from within

AEMail (see the

- TCP/IP menu
- ), and when you quit AEMail.

You can also set a time interval in minutes in which AEMail will

---

periodically check for new mail (see  
TCP/IP  
parameters on the  
Configuration screen  
) . This function is done in the background and if  
one or more messages are on your POP server, the following requester will  
pop up:

YOU HAVE MAIL!!

n Messages available on the POP Server

Do you wish to receive these messages now?

Replying [YES] to the above requester will start the retrieval of the  
messages. This requester will only pop up when you are in the main AEMail  
screen and are not in the middle of some function such as composing a  
message, transferring or saving a message, printing a message, or  
performing configuration changes.

NOTE: if you did not specify that you wanted messages deleted from your  
POP Server as you transferred them to your AMIGA, the YOU HAVE MAIL  
requester will pop up each time the system checks for mail.

## 1.60 COMMAND ICON TOOL BAR/Retrieve Messages (From Files)

### Retrieving Messages from Files

If you are in offline mode (you are not connected to your Internet Service  
Provider or AEMail can not connect, for some reason, to your POP server),  
you will see a requester that asks:

!! We are running in Offline mode !!

Do you wish to receive messages from files?

Clicking on [NO] will terminate the retrieval process.

Clicking on [YES] will bring up a file requester which will allow you to  
select one or more files. The default directory for these files is  
AMITCP: since it is assumed that you are trying to bring in mail that  
was previously transferred using another mail user agent such as AmiPOP,  
AirMail, or Voodoo; however, you can switch to any other directory and  
bring in any file that is in email text format. You can also change the  
default directory for retrieving off-line mail with the

Path Parameters  
page on the  
Configuration screen

.

AEMail automatically recognizes mail stored as individual messages or as message streams (such as stored by AmiPOP). The only requirement is that the message stream must separate messages with data beginning:

```
...<LF><LF>From UserID
```

where UserID is your own UserID as specified in the  
USERID=

```
tool type  
or with the  
Required Parameters  
page on the  
Configuration screen
```

.

This also works with message streams saved by the  
Save Message to File  
or the Export.. item in the  
messages menu

.

It is also assumed that lines have been stored in the file ending in <LF> and not <CR><LF> (<CR> is \$0D and <LF> is \$0A).

If you encounter a message stream that does not use the above to separate messages, please report what was used and what product was used to create the message stream. A copy of the message stream on floppy or sent to me as an email attachment would be very handy. (see

```
Bug Reports and Suggestions  
)
```

## 1.61 COMMAND ICON TOOL BAR/Start/Terminate Network Connection

### Start TCP/IP Network Connection

This will start your network connection to your Internet Provider using your StartNet script. It performs the same function as the

```
Start Net  
item under the  
TCP/IP  
menu.
```

### Terminate TCP/IP Network Connection

This will terminate your network connection to your Internet Provider using your StopNet script. It performs the same function as the

```
Stop Net  
item under the  
TCP/IP
```

---

menu.

## 1.62 COMMAND ICON TOOL BAR/Copy Messages

Copy Messages to a New Folder

Clicking on this icon copies all  
selected messages  
from the

selected folder

to a new folder. When you select this icon, a

Notification window appears which says:

Select Folder to Copy Messages To!

[CANCEL]

When the window appears, click on the folder icon that represents the folder you want the messages copied to. The window will automatically disappear at that time.

The selected messages will be copied to that folder. Messages will remain in both folders.

Clicking on [CANCEL] before clicking on a folder will cancel the operation.

As the messages are being copied, the folder message list that the the messages are copied to will be displayed. Once the copy is complete, the folder message list from which the messages are copied will be displayed.

## 1.63 COMMAND ICON TOOL BAR/Transfer Messages

Transfer Messages to a New Folder

Clicking on this icon moves all  
selected messages  
from the

selected folder

to a new folder. When you select icon, a Notification

window appears which says:

Select Folder to Transfer Messages To!

---

[CANCEL]

When the window appears, click on the folder icon that represents the folder you want the messages transferred to. The window will automatically disappear at that time.

The selected messages will be copied to that folder, and the messages in the folder from which the messages are copied will be marked as

deleted

.

Clicking on [CANCEL] before clicking on a folder will cancel the operation.

As the messages are being transferred, the folder message list that the the messages are transferred to will be displayed. Once the transfer is complete, the folder message list from which the messages are copied and deleted will be displayed.

## 1.64 AEMAIL MENUS

### AEMAIL Menus

When ever your are displaying folder lists, message lists, or messages themselves a menu strip is active and will be displayed when you press the right mouse button.

Below is a list of all the current menus in the AEMail menu strip. Clicking on a menu item in this list will bring up a list of the menu sub-items and clicking on a sub-item will bring up a description of the sub-item's functions:

Project menu

Folders menu

Messages menu

Retrieve Msgs menu

TCP/IP menu

## 1.65 AEMAIL MENUS/Project menu

### Project menu

The Project menu consists of the following items:

---



```
Configuration...  
  
Send Queued Mail  
  
Iconify AEMAIL  
  
About...  
  
Quit...
```

## 1.66 AEMAIL MENUS/Project menu/CONFIGURATION...

Configuration...

This has five submenu items for controlling your configuration. These sub-menu items are:

Open...

This brings up a file requester which allows you to specify a configuration file other than the standard  
s:aemail.cnfg  
file.

Once you have opened this configuration file it becomes your current active configuration.

Edit...

The  
Configuration screen  
will be activated allowing complete  
configuration data to be entered for the current active  
configuration file.

Save

This will save the current configuration settings in the currently active configuration file. It serves the same purpose as the previously Save Settings menu item (versions prior to 1.13) in which all of the current settings including the current state of the

```
Display Full Hdr  
,  
Incl Hdr in Resp  
,  
Excl Dup Msgs  
and  
  
Delete Host Mail  
menu items.
```

Save As...

---

This is the same as Save except that a file requester will be brought up which allow you to rename the current active configuration file. The new name becomes the new current active configuration file.

#### Restore Default

This reads in the s:aemail.cnfg file OR the file specified in the

```

CONFIG=
Tool Type OR the
config=
parameter on the Shell call to
AEMail. The particular file that is used is referred to as your
base configuration. The base configuration now becomes your
currently active configuration file.
```

## 1.67 AEMAIL MENUS/Project menu/SEND QUEUED MAIL

Send Queued Mail

This will send all messages in the QUEUED folder. (See the

```

SEND MESSAGE IMMEDIATELY
command in the
COMMAND ICON STRIP
.
```

This action will also occur automatically when you first load AEMail and when you exit AEMail provided you are connected to your Internet provider.

## 1.68 AEMAIL MENUS/Project menu/ICONIFY AEMAIL

Iconify AEMail

You can iconify AEMail with an iconify bar on the Workbench screen with this menu item. When this menu item is selected, the AEMail screen will be closed and a button bar will appear on the Workbench screen with

```
AEMAIL (Click on Close or with RMB to restore)
```

in the title. When the iconified bar is in selected mode, clicking either on the close gadget or with the right mouse button will restore the

```
AEMail screen
.
```

Initially the iconify bar will open at the top center of the Workbench screen, but it can be dragged anywhere on the screen. AEMail remembers where you dragged the bar so the next time you iconify, the bar will be at that new position.

There is also a hotkey provided for iconifying AEMail. This is RIGHT-AMIGA-I. This hot key, and also LEFT-AMIGA-I, will also restore the AEMail screen when in the iconify mode.

When in iconify mode, periodic checking of mail on your POP server is still done. If mail is found, the YOU HAVE MAIL requester will pop up on the Workbench screen. You can retrieve the mail immediately by clicking on the [YES] gadget. The requester will disappear and retrieval of messages will occur in the background and no progress indicator will appear. When you return to the AEMail screen, the new messages will be in your INBOX folder.

You can also push the AEMail screen to the back exposing the screen immediately behind the AEMail screen or the WorkBench screen by hitting LEFT-AMIGA-M when the AEMail screen is being displayed. This is standard Amiga action.

If the AEMail screen has been pushed to the back, hitting LEFT-AMIGA-M will bring the screen forward. Note: if other screens, besides the Workbench screen, are also present, they may be moved to the front first so that you may have to hit LEFT-AMIGA-M several times before the AEMail screen appears.

Since there is no screen to bring forward, this will not work if the iconify action has been taken.

## 1.69 AEMAIL MENUS/Project menu/ABOUT

About...

This will display the name, version, and date of the program followed by information as to whether or not the shareware registration message has been received and who the version is registered to (with serial number).

Below that is information on how to contact the author of the program.

## 1.70 AEMAIL MENUS/Project menu/QUIT

Quit...

Exits AEMail.

When this menu item is selected, AEMail first checks to see if you are connected to your Internet provider. If you are, a connection will be made to your POP Server to see if there are any messages available on the server. If there are, the following requester will appear:

---

n Messages Available on the POP Server

Do you wish to receive these messages now?

If you click on the [YES] button, those message will be retrieved at this point. If you click on [NO], no message retrieval will take place.

After AEMail checks to see if any messages are available on the POP Server, it also checks to see if any messages are in the QUEUED folder (messages queued to be sent). If there are, the following requester will appear:

You have n messages queued to be sent

Do you wish to send these messages now?

If you click on the [YES] button, all of the messages in the QUEUED folder will be sent immediately. If you click on [NO], the queued messages will not be sent.

After checking for POP messages and QUEUED messages, the following requester will appear:

Do you wish to terminate your Host connection now?

Selecting the [YES] button will cause the stopnet script to be executed terminating your TCP/IP connection to your Internet provider.

You can disable all of these requesters with a checkmarked item in the

TCP/IP  
display on the  
Configuration screen  
. If they are disabled,

the [NO] action will be assumed which each of the requesters.

Finally, a requester will be displayed that asks:

Do You Really Want to Quit?

Clicking on [YES] will terminate the program and [NO] will return to the program.

When AEMail exits, all messages marked for deletion will be deleted and any configuration files in which data has been updated will be re-written. You will probably see a great deal of disk activity at this time. While this disk activity is going on, a window will be displayed on the Workbench screen saying:

---

Updating all AEMail Configuration Files!

When updating is complete, this window will disappear. **WARNING: DO NOT** turn your computer off while this window is being displayed. If you do your disk will be corrupted!

## 1.71 AEMAIL MENUS/Folders menu

Folders menu

The Folders menu consists of the following items:

- New...
- Edit...
- Delete...
- Set Sort Key...
- Remove DELETED msgs

## 1.72 AEMAIL MENUS/Folders menu/FOLDER MAINTENANCE

New...

The

Configure Folder window will be activated indicating that a new folder should be created. The Configure Folder window description details how to create a new folder.

Edit...

The Configure Folder window will be activated indicating that the current selected folder description should be edited. The current selected folder is the folder that has a depressed frame. You can change the selected folder by single clicking on the appropriate folder icon or selecting a folder from the

folder list  
. See the description of the  
Configure Folder window  
for details on how to change the folder description.

Delete...

This will delete the folder that has been selected. You will not be able to delete a folder that has active messages in it. If there are deleted messages in the folder, the messages will be immediately deleted along with the folder. There is no way you can get these deleted messages back.

### 1.73 AEMAIL MENUS/Folders menu/SET SORT KEY

Set Sort Key...

Activates the Set Sort Key window for the current selected folder. See the description of the

Set Sort Key window  
for details on how to set the folder

sort keys.

### 1.74 AEMAIL MENUS/Folders menu/Remove DELETED msgs

Remove DELETED Msgs

This will IMMEDIATELY delete ALL messages marked for deletion in the current active folder. This means that they will no longer appear in the message list for that folder and they will be physically deleted from your mail directory.

Before actually removing the messages the following requester will appear:

This will remove all deleted messages in the  
[folder\_name] folder  
If you continue you can not retrieve them!

You will given the option to either [CONTINUE] or [CANCEL]. If you select [CONTINUE] all the messages marked for deletion in the folder will be removed. [CANCEL] will abort the operation.

A busy pointer will be displayed while the messages are being removed.

### 1.75 AEMAIL MENUS/Messages menu

Messages menu

The Messages menu consists of the following items:

---

---

Show  
Compose...  
Reply  
Forward...  
Edit...  
Select None  
Select All  
Last Selected  
Export...  
Copy...  
Transfer...  
Print  
Delete/Undelete...  
Display Full Hdr  
Incl Hdr in Resp

## 1.76 AEMAIL MENUS/Messages menu/SHOW

Show

This has two checkmarked submenu items for controlling your message list display. These sub-menu items are:

Deleted Messages

If this sub-item is checked, deleted messages will be shown in the message list. If it is unchecked, deleted messages will not be shown. This sub-item is checked when AEMail first comes up.

UnRead Msgs Only

If this sub-item is checked, only unread messages will be displayed in the message list. If it is unchecked all messages will be displayed. This sub-item is unchecked when AEMail first comes up.

---

## 1.77 AEMAIL MENUS/Messages menu/COMPOSE...

Compose...

Activates the Compose Message window whether or not a message is currently selected. to create a NEW message to be sent

(see also the Compose a Message function)

Reply

Activates the Compose Message window to reply to the current selected message.

There are two sub-menus which are:

Use Reply-To...

The Reply-To: address of the selected message will be used as the recipient of the reply. If the Reply-To: address is not present, the From: address will be used.

Use From...

This forces the From: address to be used as the recipient of the reply.

If a message is not selected when one of the sub-menu items is activated an error requester will appear.

(see also the Compose a Message function)

Forward...

Activates the Compose Message window to forward the current selected message.

If a message is not selected when this menu item is activated an error requester will appear.

---



(see also the

Compose a Message  
function)

Edit...

Using this menu item will allow you to edit a message selected in either the PENDING or QUEUED folders. It has the same effect as clicking on the Compose icon when you have selected a message in either the PENDING or QUEUED folders.

If you have not selected a message in either the PENDING or QUEUED folder when this menu item is activated an error requester will appear.

(see also the

Compose a Message  
function)

## 1.78 AEMAIL MENUS/Messages menu/SELECT...

Select None

This menu item will de-select all messages in the selected folder.

(See also

Message Selection  
)

Select All

This menu item will select all messages in the selected folder. Selected messages will be marked with an asterick (\*) in the first position of the message in the

message list  
display.

(See also

Message Selection  
)

Last Selected

This menu item will re-select those messages that were last selected. If you did a multiple selection on a group of messages and then performed an operation on the group of messages (such as deleting, copying, saving the group to a file, etc.), the messages will be de-selected as the operation is performed on each message. The Last Selected menu item will allow

---

you to re-select the same previously selected messages so that you can perform another operation on the same group of messages.

(See also  
Message Selection  
)

## 1.79 AEMAIL MENUS/Messages menu/COPY

Copy...

This menu copies all  
selected messages  
from the  
selected folder  
to a new  
folder. When you select this menu, a Notification window appears which says:

Select Folder to Copy Messages To!

[CANCEL]

When the window appears, click on the folder icon that represents the folder you want the messages copied to. The window will automatically disappear at that time.

The selected messages will be copied to that folder. Messages will remain in both folders.

Clicking on [CANCEL] before clicking on a folder will cancel the operation.

As the messages are being copied, the folder message list that the the messages are copied to will be displayed. Once the copy is complete, the folder message list from which the messages are copied will be displayed.

## 1.80 AEMAIL MENUS/Messages menu/TRANSFER

Transfer...

This menu moves all  
selected messages  
from the  
selected folder  
to a new  
folder. When you select this menu, a Notification window appears which says:

Select Folder to Transfer Messages To!

[CANCEL]

When the window appears, click on the folder icon that represents the folder you want the messages transferred to. The window will automatically disappear at that time.

The selected messages will be copied to that folder, and the messages in the folder from which the messages are copied will be marked as deleted

.

Clicking on [CANCEL] before clicking on a folder will cancel the operation.

As the messages are being transferred, the folder message list that the the messages are transferred to will be displayed. Once the transfer is complete, the folder message list from which the messages are copied and deleted will be displayed.

## 1.81 AEMAIL MENUS/Messages menu/DISPLAY FULL HEADER

Display Full Hdr

This is a checkmarked menu sub-item. When checked, all message headers will be displayed in the message. Since many of these headers are somewhat cryptic and could be confusing and not always understood by the user, the normal action is display only certain header lines. The default action is to display the following headers: From:, To:, Date:, Subject:, cc: and bcc:, but you can control this default minimum header list with the

General Parameters  
display of the  
Configuration screen

.

This menu sub-item is very useful for debugging purpose to see all of the headers what any particular message carries.

The current state of this checkmarked item is saved in the  
aemail.cnfg  
file

whenever the

Save Settings  
item is selected from the  
Project menu

.

It can also be set or reset by the General Parameters display on the Configuration screen.

---

## 1.82 AEMAIL MENUS/Messages menu/INCL HDR IN RESP

### Incl Hdr in Resp

This is a checkmarked menu sub-item. When checked the minimum header lines (To:, From:, Date:, Subject, cc: and bcc:) will be included for the quoted message when composing a response. If it is not checked, no header information will appear.

The current state of this checkmarked item is saved in the  
 aemail.cnfg  
 file

whenever the

Save Settings  
 item is selected from the  
 Project menu

It can also be set or reset by the  
 General Parameters  
 display on the

Configuration screen

## 1.83 AEMAIL MENUS/Retrieve Msgs menu

### Retrieve Msgs menu

The Retrieve Msgs menu consists of the following items:

From POP Host  
 From Local File...  
 Excl Dup Msgs  
 Delete Host Mail

## 1.84 AEMAIL MENUS/Retrieve Msgs menu/FROM ...

### Retrieve Messages

From POP Host

This will only retrieve messages from the POP Server. See the

RETRIEVE MESSAGES  
 command a full explanation of the retrieval process.

If AmiTCP is not active or connection to the POP Server can not be made, the RETRIEVE MESSAGES command will return silently with the information that connection to the POP Server could not be made in the title bar.

From Local File...

This will only retrieve messages from a local file. No attempt will be made to connect to the POP Server. See the  
 Retrieve Messages from Files  
 command for a full explanation of the retrieval process.

This menu sub-item allows you to retrieve messages from files even when online (connected to a host through AmiTCP).

## 1.85 AEMAIL MENUS/Retrieve Msgs menu/CHECKMARKED ITEMS

### Excl Dup Msgs

This is a checkmarked menu sub-item. When checked, duplicate messages (ones that were previously retrieved and stored in one of AEMail's folders), will not be stored. See the description under the

RETRIEVE MESSAGES  
 command for

the use and full explanation of the function of this item.

The current state of this checkmarked item is saved in the  
 aemail.cnfg  
 file

whenever the

Save Settings  
 item is selected from the  
 Project menu

It can also be set or reset by the  
 General Parameters  
 display on the

Configuration screen

### Delete Host Mail

This is a checkmarked menu sub-item. When checked mail retrieved from your POP server will be deleted after it is retrieved. If it is not checked, mail will not be deleted and you will have to use the Excl Dup Msgs checkmark item discussed above to insure that a duplicate message are not saved the next time you retrieve messages.

The current state of this checkmarked item is saved in the  
 aemail.cnfg

file  
 whenever the  
     Save Settings  
     item is selected from the  
     Project menu  
 .  
 It can also be set or reset by the  
     General Parameters  
     display on the  
  
     Configuration screen  
 .

## 1.86 AEMAIL MENUS/TCP/IP menu

TCP/IP menu

The TCP/IP menu consists of the following items:

Start Net  
 Stop Net  
 TCP Logging File

## 1.87 AEMAIL MENUS/TCP/IP menu/START NET

Start Net

This menu item makes connection to your Internet Provider. It executes the script that has been assigned by the

Start Net  
 Tool Type or the

TCP/IP  
 page of the  
 Configuration screen

. If no Start Net script  
 has been assigned, the action that is performed is to  
 iconify  
 AEMail.

You can then perform the network connection in whatever manner was provided by your TCP/IP stack software. Once the connection is made, un-iconify AEMail.

When this menu item is selected and a Start Net script has been assigned, the system will, by default, switch to the workbench screen and execute the Start Net script. This allows the initial dialing window to display. Once your Internet connection has been made the system will switch back to

the AEMail screen.

You can control the switching to the workbench screen by a checkmarked item in the TCP/IP Parameters page on the Configuration screen.

If you are using

AmitTCP

, the script that should be run is

AmitTCP:bin/startnet; although the user may specify a different script and path with the STARTNET Tool Type or in the TCP/IP Parameters page on the Configuration screen.

If you are using

Miami

, a "startnet.miami" script has been provided for connecting with your Internet provider. This is usually run from the AEMail program directory. This is an AREXX script so you will have to precede the script name with "rx " (refer to the CONFIGURATION links above for setting up your Start Net script). This is set up automatically with the AEMail

install

provided a Miami: assignment is present in the system.

If you are using a TCP/IP stack that does not have a Start Net script (such as

TermiteTCP

), you should be sure that the Start Net call gadget in the TCP/IP parameters page of the Configuration screen has been cleared. Your Internet connection is then done manually as explained above.

Once a connection is made to your Internet provider and you have returned to the AEMail screen, a connection will be made to your POP server to see if there are any messages available on the server. If there are, the following requester will appear:

Once a connection is made to your Internet provider and you have returned to the AEMail screen, a connection will be made to your POP server to see if there are any messages available on the server. If there are, the following requester will appear:

n Messages Available on the POP Server

Do you wish to receive these messages now?

If you click on the [YES] button, those message will be retrieved at this point. See the

RETRIEVE MESSAGES  
command in the  
COMMAND ICON STRIP  
for

details on this process.

If you click on [NO], no message retrieval will take place at this time. You will need to retrieve these messages later using the RETRIEVE MESSAGES command icon.

---

After AEMail checks to see if any messages are available on the POP Server, it also checks to see if any messages are in the QUEUED folder (messages queued to be sent). If there are, the following requester will appear:

```
You have n messages queued to be sent
```

```
Do you wish to send these messages now?
```

If you click on the [YES] button, all of the messages in the QUEUED folder will be sent immediately. If you click on [NO], the queued messages will not be sent.

After the connection is made, the following message will be displayed in the screen's title bar:

```
TCP/IP Session started with your-domain-name.
```

If for any reason the connection can not be made, the following message will be displayed in the screen's title bar:

```
TCP/IP connection to your-domain-name failed
```

## 1.88 AEMAIL MENUS/TCP/IP menu/STOP NET

Stop Net

This menu item terminates the connection to your Internet Provider. It executes the script that has been assigned by the

```
Stop Net
Tool Type or
```

the

```
TCP/IP
page of the
Configuration screen
```

. If no Stop Net script has been assigned, the action that is performed is to

```
iconify
AEMail. You
```

can then terminate the network connection in what ever manner was provided by your TCP/IP stack software. Once the connection is terminated, un-iconify AEMail.

When this menu item is selected and a Stop Net script has been assigned, the system will terminate the connection silently in the background. Since no action is required by the user (unlike

```
Start Net
), the screen display
```

will remain on the AEMail screen.

If you want to switch to the Workbench screen while the connection is being terminated, you can do this through a checkmarked item in the TCP/IP



Parameters page on the Configuration screen.

If you are using

AmiTCP

, the script that should be run is

AmiTCP:bin/stopnet; although the user may specify a different script and path with the STOPNET Tool Type or in the TCP/IP Parameters page on the Configuration screen.

If you are using

Miami

, a "stopnet.miami" script has been provided for terminating the connection with your Internet provider. This script is usually run from the AEMail program directory. This is an AREXX script so you will have to precede the script name with "rx " (refer to the CONFIGURATION links above for setting up your Stop Net script). This is set up automatically with the AEMail

install

provided a Miami:

assignment is present in the system.

If you are using a TCP/IP stack that does not have a Stop Net script (such as

TermiteTCP

), you should be sure that the Stop Net call gadget in the TCP/IP parameters page of the Configuration screen has been cleared. Your Internet connection is then terminated manually as explained above.

The following messages will be displayed in the screen's title bar when the connection is terminated:

TCP/IP session with your-domain-name terminated.

## 1.89 AEMAIL MENUS/TCP/IP menu/TCP Logging File

### TCP Logging File

This has three submenu items for controlling your TCP Logging file. See

TCP Trace Log File

for how to read the entries in this file.

The sub-menu items are:

Active

This is a checkmarked menu sub-item which indicates whether the TCP Logging is active or not. If a TCP Logging File has not been defined with the

Paths

page of the

Configuration screen

, this sub-item is

---

ghosted.

Clicking on this item when it is not checkmarked will activate TCP Logging. Clicking on it when it is checkmarked will deactivate logging.

#### Purge

This is a handy way to delete all previous TCP Logging entries. Purge will delete the current logging file and open another file with the same name if logging is active.

If logging is not active, the current logging file will be deleted, but a new file will not be opened until the Active sub-item is checkmarked.

This menu item can be used whether the logging file is currently active or not.

#### Display/Edit...

Display/Edit... will call your editor to display the current TCP logging file. The logging file MUST NOT be Active in order to display or edit it. If it is active you will get a requester that informs you that you can't display the file because it is active. If this happens, de-activate logging by turning off the Active checkmark and then try the Display/Edit... again.

If a TCP Logging file has not been defined in the  
Paths  
page of  
the  
Configuration screen  
, you will receive a requester saying  
that it is not present.

NOTE: The TCP logging file can become quite large and it may take some time for your editor to bring in the file. Some editors are slower than others in this regard. If you are using the AmigaDos editor (Ed), you will see a series of astericks (@) moving across the screen as the file is being read in. You might want to periodically purge the file (if it is always active), to prevent a very large TCP Log file from being created.

## 1.90 AEMAIL WINDOWS

### AEMAIL Windows

AEMail has the following window displays:

---

- Folder List Window
- Message List Window
- Folder Configuration Window
- Filter Selection Window
- Set Sort Keys Window
- Address Book Window
- Message Display Window
- Compose Message Window
- Configuration Screen

### 1.91 AEMAIL WINDOWS/Folder List Window

#### Folder List Window

The Folder List window will be displayed in the lower portion of the screen when AEMail is first loaded and whenever you click on the

```

DISPLAY FOLDER LIST
icon in the
Command Icon Strip
    
```

The Folder List window looks like the following:

```

=====
                                Folder List
Name          Description of Folder                                Not Read Total
-----
INBOX         Messages Received                                           nnnnn nnnnn| |
PENDING      Messages composed and pending for action                    nnnnn| |
QUEUED       Messages Queued to be sent                                  nnnnn| |
SENT         Messages that have been sent                                nnnnn| |
xxxxxxxxx    xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx  nnnnn nnnnn| |
xxxxxxxxx    xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx  nnnnn nnnnn| |
-----
                                | |
=====
    
```

The folder list is a scrolling list. Double clicking on any of the folders in the list will bring up the Message List window for that folder.

If the Folder Icon strip

is also being displayed, double clicking on any particular folder icon will also bring up the message list for that folder.

If there are too many folders to fit in the window, you can scroll the list by using the scroll bar, clicking on the up or down arrows below the scroll bar, or by using the up or down cursor keys.

Additionally the following keys can be used to move the list as follows:

- Home or Cursor Left moves the listview to the top.
- End or Cursor Right moves the listview to the botton.
- PgUp or Shift Cursor Up pages the listview one page up. The top line of the previous page will be displayed as the bottom line of the new page.
- PgDn or Shift Cursor Down pages the list view one page down. The bottom line of the previous page will be displayed as the top line of the new page.
- The cursor up/down keys on the keypad will have the same action as the normal cursor keys with the exception of the shift feature.

Single clicking on a item in the list or on a folder icon merely selects that folder. The selected folder is then the folder referenced by the

```

Folders Menu
group items (
Edit..
,
Delete...
,
Set Sort Key ...
)

```

and by such commands as

```

Message Delete/Undelete
,
Message Copy
,
Message Transfer
, or
Message Select ALL/NONE
.

```

One of the folders is always active (selected). On program startup, the active folder will be INBOX. You can always tell the current active folder by the depressed frame around the folder icon.

## 1.92 AEMAIL WINDOWS/Message List Window

### Message List Window

The Message List window will be displayed in the lower portion of the screen whenever you double click on either an item in the

---



F indicates the message is a forwarded message.  
D (in the same position as N) indicates the message is a deleted message.

- Date:** This is the message date from the DATE: header in the form of MM/DD/YY (2 digit month, 2 digit day, and the last 2 digits of the year).
- Time:** This is the time the message was received in the form of HH:MM (2 digit hour, 2 digit minute). Time uses a 24 hour clock.
- From:** Is the Real Name (if present) from either the From: or To: header. If the folder represents messages being sent from AEMail (PENDING, QUEUED, SENT) then this field will be headed To and the To: header will be used. If the Real Name is not present in the header, then the UserID will be used instead. If a Nickname is being used for a message being sent, then the Nickname will appear.
- Size:** This is the size, in bytes, of the message in the form nnn,nnn. If the size exceeds 999,999 bytes then \*\*\*,\*\*\* will appear. The size includes the size of the message with all its attachments.
- Subject:** Up to 39 characters from the Subject: header after RE: and (fwd) are stripped. You can tell if the message is forwarded or is a reply by examining the FLGS field. RE: and (fwd) are stripped from the Subject: header to allow sorting to place all messages with the same subject (whether original, replied, or forwarded) together. You can also control where 'replied' and 'forwarded' messages go in the list since these use separate sorting criteria.

An asterick (\*) in the first position indicates that the message is selected. This position will be blank if the message is not selected.  
See

Message selection  
for how to do multiple selection of  
messages.

The Message list can be sorted under a number of different categories (see

Set Sort Keys  
window).

Double clicking on any message in the Message List will bring up the

Message Display  
window for that message.

---

## 1.93 AEMAIL WINDOWS/Message Selection

### Message Selection

A single click will highlight and select the message. An asterick will appear in the first column of the line indicating the message is selected. You can click on another message to highlight and select that message. Clicking on a message that is already selected will deselect the message.

If you are running under AmigaDOS 3.0 or higher, you can also select (or deselect) a group of messages by drag selecting. Place the cursor over the message you first want to select or deselect and then, holding down the left mouse button, drag either up or down. Whether selecting or deselecting occurs depends on the state of the first message you select.

Only one message is highlighted. If that message is selected it will be considered the current message to reply to, forward, or edit when composing messages.

Other operations such as DELETE/UNDELETE MESSAGE, SAVE/EXPORT MESSAGES, COPY MESSAGE, TRANSFER MESSAGE, PRINT SELECTED MESSAGES, SEND MESSAGE IMMEDIATELY, and QUEUE MESSAGE FOR LATER DELIVERY will use the entire selected list of messages.

## 1.94 AEMAIL WINDOWS/Folder Configuration Window

### Folder Configuration Window

The Folder Configuration window will be displayed over the entire screen below the top title line when either the

```
New...
or
Edit...
menu items
```

are selected from the

```
Folders menu
```

.

The Folder Configuration window looks like the following:

```
=====
Folder Name: [          ] (1 - 9 Characters only) [SORT KEYS]
Folder Description: [          ]
Tab Color: [ @ | Red | |_____| [ ] Folder for Sent Messages
=====
|Filter Parameters for Selecting Messages|
=====
|
| [ ] Not [ ] Start Group           [ ] Ignore Case |
|
```







```

|
|           [ Add ] [Insert] [Modify] [Delete] |
|
|=====

```

The gadgets in the top half of the window are used to enter filtering parameters. The first two checkmark gadgets ( Not,  Start Group) and the  End Group checkmark gadget at the bottom of the group are currently disabled. They are designed to be used for advanced selection criteria that will be added to a future version of AEMail.

The cycle gadget which is prefaced with For is used to select the header that you want to check. This gadget has the following states:

```

To:
From:
Reply-To:
Subject:
cc:
bcc:
Date:
Msg is Reply
Msg w/Attachments
Msg is Forwarded
Other Message Hdrs      (Registered Users only)
Message Body            (Registered Users only)

```

Note: it is unlikely that you would see the bcc: header in an incoming message even though it is contained in the header list.

To the right of this is a cycle gadget which specifies the condition this header will be checked for. For the To:, From:, Reply-To: Subject:, cc:, and bcc: headers, Other Message Hdrs, and Message Body the condition can be either:

```

Contains, or
Does Not Contain

```

For the Date: header it can be one of the following conditions:

```

Equal
Not Equal
Greater Than
Greater Than / Equal
Less Than
Less Than / Equal

```

and for Msg is Reply, Msg w/Attachments, Msg is Forwarded it can be:

```

Is Present
Is Not Present

```

The argument to be searched against is entered into the string gadget that is titled Search. For the To:, From:, Reply-To:, Subject:, cc:, and Bcc: headers and the Other Message Hdrs and Message Body you can enter an argument that has wild cards. The wild cards that are used are as follows:

? matches any single character.  
c\* matches zero or more occurrences of character c. If an unknown character is to be matched you can use ?\*.  
c+ matches one or more occurrences of character c (at least one occurrence of c must be present).  
\? matches the character ?.  
\\* matches the character \*.  
\+ matches the character +.

Any other characters must match exactly (except that case can be ignored - see below). The match can occur anywhere in the header. The following are some examples of how the match occurs:

abc matches "abc", "abcdef", or "xxabc"  
ab\*c matches "ac", "abc", "abbc", or "abbbc", etc. Characters may be present either before or after the match.  
ab+c matches "abc", "abbc", or "abbbc", etc. Characters may be present either before or after the match. This will not match "ab+c". You would have to use "ab\+c" for this to occur.  
ab?\* matches a substring starting with "ab" and ending with "c". Characters may be present either before or after the match.  
ab\\*c matches "ab\*c" only. However characters may be either before or after the match.

**WARNING:** Please pay particular attention to the characters +, ?, and \*. If any of these characters appear in the information to be matched, you must use \+, \?, or \\* in the argument if you want an exact match to occur.

If Other Message Hdrs is used, you probably would want to use the Header designation as part of the search argument.

Searching on header data will search the entire string of characters contained within that header even though that header may span multiple lines. This means that if an address you want to locate is contained in the nth line of the To: header, it will be found.

When searching data in the message body, the entire argument must be found in a single line of the body. If you are searching for a multiple word phrase which may be broken up onto more than one line, you should specify multiple arguments with AND separating the arguments.

If you want to ignore the case of the header or message body data when the comparison is made check the Ignore Case item. The Ignore Case item will only ignore the case of the 26 alphabetic characters of the American/English alphabet. It will not ignore the case of special characters used in foreign alphabets although these special characters can be used in the Search criteria.

The Search argument for the Date: header can be of one or two formats. The first format is either:

dd mmm yyyy or  
mmm dd yyyy

mmm is the three character month abbreviation: jan, feb, mar, apr, may,

jun, jul, aug, sep, oct, nov, or dec. You can enter either upper case, lower case, or mixed case month abbreviations (i.e., jan, JAN, or Jan are all o.k.).

dd is the numeric digits for the day of the month and yyyy must be the full 4 digit year. If you want any day of a particular month to be used, leave off the dd parameter. Likewise, using just the 4 digit yyyy will accept any month and day for that year.

The absence of any of the elements of the date (mmm, dd, or yyyy) will indicate that that particular element should not be checked. As an example: if you want only messages for the month of September to be placed in a particular folder you would enter:

```
sep
```

by itself and the condition would be entered as equal to. This would capture messages with a Date: header of September of any year (Sep 1997, Sep 1998, etc.). If you were interested in messages with a Date: header of September of 1997 you would enter:

```
sep 1997
```

An alternate method of entering the date would be:

```
mm/dd/yy    or  
mm/dd/yyyy  or  
mm-dd-yy    or  
mm-dd-yyyy
```

mm is a one or 2 digit month (1 or 01 to 12), dd is a one or 2 digit day (1 or 01 to 31) and yy is either a 2 digit or 4 digit year. 0 is invalid for any of the mm, dd, or yy. If you want to indicate the absence of any of the elements use xx or XX. As an example, to capture messages with a Date: header equal to any day within September 1997 you could enter:

```
09/xx/97
```

Before the search for a Date: header is made, the date in the Date: header is converted to an internal format. The search argument is also converted to this same internal format so that the match can be performed correctly.

The Search argument for Msg is Reply, Msg w/Attachments, and Msg is Forwarded is ignored.

The END, AND, and OR gadgets are used to indicate that this is the last comparison argument (END), or that there is another comparison argument following this with either an AND or OR relationship.

Some examples of specific types of filtering parameters are given under

#### Examples of using Message Filtering

The list view in the lower half of the window lists the comparison arguments. Each comparison argument is listed on two lines. The first line shows the header to be checked and the comparison criteria in the following

format:

FOR header-name comparison-criteria (ignoring case)

(ignoring case) will not be present if Ignore Case is not checked.

The second line will show the search argument surrounded by quote (") marks. It will be followed by AND or OR if either of these were specified. If Ignore Case was checked, the Search argument will be in all lower case characters no matter how it was entered in the Search: string gadget.

To add a selection criteria to the list, enter the appropriate items in the gadgets at the top of the window and click on the [ Add ] gadget at the bottom of the window. That item will be transferred to the listview at the end of the current list of items.

To modify or delete an item, click on the item in the listview. Clicking on either the first or second line of any item in the list is acceptable. The information from the listview will be transferred to the gadgets at the top of the window. Then make the modifications you want (for modify) and click on either the [Modify] or [Delete] gadgets at the bottom of the window.

To insert an item into the list, enter the data in the gadgets at the top of the window as you did to add an item. This time click on the [Insert] gadget. The words Click on item you want to insert IN FRONT OF! will appear in yellow at the top of the listview. Now, as instructed, click on the item you want the selection criteria to be inserted in front of. This allows you to insert at the head of the list by clicking on the first item in the list. Clicking on either the first or second line of any item in the list is acceptable.

All of the selection criteria except for the last item must have an AND or OR relationship to the criteria following. You can have relationships as follows:

a OR b OR c

indicating that if any of the conditions (a, b, or c) are met that message will be selected for that particular folder, or

a AND b AND c

indicating that all of the conditions must be met for that message to be selected.

Be careful of mixing AND and OR conditions.

a OR b AND c

will work but

b AND c OR a

will not work correctly.

---

Conditions are checked serially.

In the first example above, if condition a is not met, then b will be checked. If b is not met no selection is made; however, if condition c is also met, the message will be selected. If condition a is met the message will be selected and the b or c conditions are not checked.

In the second example, if condition b is not met, no further check will be made so that even if a is met, the message will not be selected. In this example condition a will never be checked.

Advanced selection is designed to get around this problem. HOWEVER, THIS ADVANCED SELECTION HAS NOT BEEN IMPLIMENTED AS YET! AND WHEN IT IS IMPLIMENTED, IT WILL ONLY BE AVAILABLE TO REGISTERED USERS.

With advanced selection you will be able to group items in this manner:

(a AND b) OR (c AND d)

conditions a and b are a group and conditions c and d are a group. The checkmarked items Start Group and End Group are used to specify the first item in a group and the last item in a group. You will also be able to embed groups within groups such as

(a AND b AND (c OR d))

and use a not condition for a group such as

(a AND b AND NOT (c OR d))

or simply

NOT (a OR b)

Filtering Restrictions. Currently the following restriction is placed on filtering. This restriction will be lifted in a later release of AEMail.

Advanced selection (grouping selection criteria as described above), can not be done.

Other selection criteria (such as size of message) may be added later.

## 1.96 AEMAIL WINDOWS/Examples of using Message Filtering

### Examples of using Message Filtering

How would you use message filtering? Here is a practical example of how I use it. As you all know, when you implement a new version of AEMail and send your first message a special notification message is sent to me indicating the version you are using. This notification message is stored in a special folder for notification messages that I have received. All of the notification messages indicate what they are in the Subject: header. However, over the development of AEMail, the format of this subject header has changed. Before version 1.10 the Subject header looked

---

like this:

Subject: Registration of AEMAIL (Amiga EMAIL), Version x.xx

From version 1.10 through version 1.15, the Subject header looked like this:

Subject: AEMAIL Version x.xx Registration

After version 1.15 the Subject header looked like this:

Subject: AEMAIL Version x.xx Notification

Since I am still receiving notification messages back to version 1.03, I wanted all such notification messages to go into the same folder. The selection criteria for this folder was set to the following:

For Subject: Contains (ignoring case)  
"aemail version ???? registration" OR

For Subject: Contains (ignoring case)  
"aemail version ?\* notification" OR

For Subject: Contains (ignoring case)  
"registration of aemail (amiga email), version"

Notice how I handled the variable of the version number in each case. In the first criteria I used a fixed replacement wild card (????) to specify the version number. In the second criteria I used a variable replacement wild card (?\*) and in the third criteria I did not use any wild card for the version number replacement. That is because the version number occurs at the end of the line.

Another use of filtering can be used if you are subscribed to a listserve. The example I will show you is for the Miami list serve. Miami actually has two listserves: miami-talk-ml@nordicglobal.com and miami-announce-ml@nordicglobal.com. The To: address usually reflects which listserve the message is coming from but the Reply-To: address always reflects miami-talk-ml@nordicglobal.com.

If you want the folder to include all messages from both listserves you can set the following criteria for the that folder:

For Reply-To: Contains (ignoring case)  
"miami-talk-ml@nordicglobal.com"

If you set up two folders, one for the "talk" message list and the other for the "announcement" message list you could set the "talk" folder to reflect the following criteria:

For To: Contains (ignoring case)  
"miami-talk-ml@nordicglobal.com"

and the "announcement" folder as follows:

For To: Contains (ignoring case)  
"miami-announce-ml@nordicglobal.com"

---

If messages meet the selection criteria for two different folders, the first folder in the folder list which meets the criteria will be selected. So, if you were to have two folders set up as described above (one for "talk" messages and one for "announcement" messages) and you used the Reply-To: address instead of the To: address as the selection criteria for the "talk" folder and if the "talk" folder was first, all of the "announcement" messages would go in the "talk" folder. However, if the "announcement" folder was first, then the messages would be distributed to the correct folders. By using the To: header field, however, you would always insure that they go to the right folders.

You will find that the clipboard capability is very helpful in setting up your filtering conditions. If there is a particular header that you want selected, display the message that has that header, and then double click on the header in the message. Edit out the header designator (To:, From:, Subject:, etc) and save it to the clipboard. You can save various items changing the clipboard unit for each item. Then when you are in the Folder Configuration screen, select the Search string gadget and use Right Amiga U to call up the clipboard list. Then double click on the item you want to select on. It will then be automatically pasted into the Search string gadget.

As was stated in the earlier description of the Filter Selection Window, the window for the INBOX is used to EXCLUDE messages meeting the INBOX criteria from entering your system. Use this with CARE! If you exclude a message and you are deleting messages from you POP server, YOU WILL NEVER SEE THAT MESSAGE!

## 1.97 AEMAIL WINDOWS/Set Sort Keys Window

### Set Sort Keys Window

The Set Sort Keys window will be displayed over the entire screen below the top title line when either the

Set Sort Key...  
menu item from the

Folders menu  
is selected or the [Sort Keys] button is clicked in the

Folder Configuration Window

.

The Set Sort Keys window looks like the following:

```

=====
          1         2         3         4         5         6         7
Priorities: -----
Un-Read Messages: FIRST [ ]      Messages with Attachments: FIRST [ ]
Priority [ @|0|      LAST [ ]      Priority [ @|0|      LAST [ ]

Replied Messages: FIRST [ ]      Forwarded Messages: FIRST [ ]

```



```

Priority [0] LAST [ ] Priority [0] LAST [ ]

Latest Date: FIRST [ ] Largest Messages: FIRST [ ]
Priority [0] LAST [ ] Priority [0] LAST [ ]

Group by FROM at Priority [0] Group by Subject at Priority [0]

[ ] Order Received
--> at Priority [0] [ ] Apply to all Folders
[ ] Latest Received

[ LAST SAVED ] [ LAST USED ] [ USE ] [ SAVE ] [ CANCEL ]

```

```
=====
```

Messages in each of the folders can be displayed in various sort orders and each folder can have a different sort order. Up to seven levels of sort priority can be given. The various sorting criteria are shown on this window and a particular sort order can be given for any sort priority. The sorting criteria for any particular priority is selected by the priority cycle gadget under or opposite each criteria. A priority of 0 is used to indicate that this criteria is not used in the sort.

To help visualize which criteria applies to which priority a list at the top of the window shows the current position of any particular sort criteria in the priority list. With the exception of priority 0 (no priority), no two criteria can have the same priority. If this happens, **\*\*DUP\*\*** will appear for that priority in the priority list.

If you want the sorting criteria to be used for all folders check the Apply to all Folders box.

At the bottom of the window is the [LAST SAVED], [LAST USED], [USE], [SAVE], and [CANCEL] buttons. If you want the sorting to apply only to this AEMail session only select [USE]. If you want to make the sorting permanent, select [SAVE]. [CANCEL], of course, will abort the operation without setting any sort keys. The [LAST SAVED] button is used to restore the sort keys to those last saved and the [LAST USED] is used to restore the last used sort keys.

If this window was called from the  
Folder Configuration Window

selecting [USE], [SAVE], or [CANCEL] will return you to the Folder Configuration Window.

The [LAST SAVED] and [LAST USED] buttons will simply restore the appropriate sorting order and will not terminate the Folder Configuration Window. You will have to use the [USE], [SAVE], or [CANCEL] buttons to do that.

For examples of setting sort keys see  
Examples of Setting Sort Keys

## 1.98 AEMAIL WINDOWS/Sort Key Examples

### Examples of Setting Sort Keys

You may want your list of messages displayed in different orders in the

```

Message List Window
. This is the purpose of the
Set Sort Keys Window
.

```

Let's assume that you want your messages displayed with unread messages first. Within both the unread and previously read sections you want the messages sorted by the latest date first. To do this click on the Un-Read Messages: FIRST box and set the Priority underneath Un-Read Messages to 1. Then click on the Latest Date: FIRST box and set it's Priority to 2. Notice ← that as you change the Priority cycle gadget for Latest Date from 0 to 1 to 2, you will see \*DUP\* appear in priority 1 as the Date moves through the priority 1 position.

The final sort window for the above sorting priority will look like this:

```

=====
          1          2          3          4          5          6          7
Priorities: UNREAD  DATE  -----  -----  -----  -----  -----

Un-Read Messages: FIRST [X]      Messages with Attachments: FIRST [ ]
Priority [0|1|      LAST [ ]      Priority [0|0|      LAST [ ]

Replied Messages: FIRST [ ]      Forwarded Messages: FIRST [ ]
Priority [0|0|      LAST [ ]      Priority [0|0|      LAST [ ]

Latest Date:      FIRST [X]      Largest Messages: FIRST [ ]
Priority [0|2|      LAST [ ]      Priority [0|0|      LAST [ ]

Group by FROM at Priority [0|0|    Group by Subject at Priority [0|0|

[ ] Order Received
--> at Priority [0|0|    [ ] Apply to all Folders
[ ] Latest Received

[ LAST SAVED ]    [ LAST USED ]    [ USE ]    [ SAVE ]    [ CANCEL ]
=====

```

When you are satisfied with the order click on [SAVE] to save this order for this folder only. If you want to use this order for all your folders click on Apply to all Folders before clicking on [SAVE].

Another example might have the messages displayed with unread messages first, followed by messages grouped by SUBJECT, and within the SUBJECT grouping, by the latest date received. This, in effect, creates a message threading condition with like subjects grouped together.

To create this sort condition, click on the Un-Read Messages: FIRST box and set it's Priority to 1. Then set the Group by Subject at Priority cycle gadget to 2. Finally click on the Latest Date: FIRST box and set it's Priority to 3. The final sort window for this grouping would be:

```

=====
          1          2          3          4          5          6          7
Priorities: UNREAD SUBJECT DATE -----
Un-Read Messages: FIRST [X]      Messages with Attachments: FIRST [ ]
Priority [1] LAST [ ]      Priority [0] LAST [ ]
Replied Messages: FIRST [ ]      Forwarded Messages: FIRST [ ]
Priority [0] LAST [ ]      Priority [0] LAST [ ]
Latest Date: FIRST [X]      Largest Messages: FIRST [ ]
Priority [3] LAST [ ]      Priority [0] LAST [ ]
Group by FROM at Priority [0]      Group by Subject at Priority [2]
[ ] Order Received
--> at Priority [0]      [ ] Apply to all Folders
[ ] Latest Received
[ LAST SAVED ]      [ LAST USED ]      [ USE ]      [ SAVE ]      [ CANCEL ]
=====

```

If you want the messages sorted with the earlier messages first within the subject grouping, you would click on Latest Date: LAST rather than Latest Date: FIRST.

Since the date sort is controlled by the local date and time that the message was SENT, you might want to use the Order Received or Latest Received instead of Latest Date. Order Received will list the messages with the oldest received first, while Latest Received will list the messages with the newest received first.

You, of course, can set different sort orders for different folders. In this case select the folder you want to change the sort order for and DON'T click on the Apply to all Folders checkmark gadget.

## 1.99 AEMAIL WINDOWS/Address Book Window

### Address Book Window

The Address Book window will be displayed in the lower portion of the screen whenever you double click on the

ADDRESS BOOK

command icon or on

the [Call Address Book] button in the

COMPOSE MESSAGE window

.  
 If you have a non-interlaced screen (640 x 200), the display will cover the folder strip to allow more room for the Address Book display. With an interlaced screen (640 x 400) you will be able to see the folder strip  
 .

The Address Book window looks like the following:

```

=====
Address Book
=====

Nick Name: [          ] Address: [          ] Select [ @ | To: |

Real Name: [          ] Group [ ] Send Header Only [ ]

Nickname Real Name          UserID (Address)          [x] Expand
-----
xxxxxxx xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx | |
xxxxxxx xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx DISTRIBUTION LIST WITH n ENTRIES | |
                                             xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx | |
                                             xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx | |
-----
[ ADD ]      [MODIFY]      [DELETE]      [SELECT]      [ EDIT ]

=====

```

This window can be used to create, modify, or delete Address Book entries. It can also be used to select a Nickname to be used as a recipient of a message when composing messages.

Several of the

Command icons

remain active when you are displaying the

Address Book window, although their meaning may be slightly changed. These are the DISPLAY NEXT MESSAGE icon, the DISPLAY PREVIOUS MESSAGE icon, the DISPLAY NEXT FOLDER icon, the DISPLAY PREVIOUS FOLDER icon, the DISPLAY CURRENT FOLDER icon, the PRINT icon, the DELETE icon, and the COMPOSE MESSAGE icon.

The three fields of an address book entry are: a one to eight character Nickname, an individual's Real Name (up to 99 characters), and the address of the individual (UserID and Domain in the form userid@domain) which is limited to 70 characters.

Group lists can also be created which distribute a message to a number of different individuals. The group is identified with the heading DISTRIBUTION LIST WITH nnn ENTRIES in the top most UserID field. The nnn indicates the number of entries in the group. The UserID's for the members of that list are shown in alphabetic order below that heading. For items in the distribution list, real UserIDs or Nicknames can be used. An item in the distribution list can even be another distribution list identified by the Nickname for that group. By clicking on the Checkmarked item Group, you can identify the entry as a group item.

The checkmarked item identified as Send Header Only is only active when Group is checked. If a checkmark is in the Send Header Only box, only the group name will be sent in the To: field when a message is sent to the group; otherwise, every UserID in the group will be listed in the To: header. It is a good idea to check this item if you have large groups or if you don't want the other members of the group to know all the members of the group.

If a Nickname rather than a UserID is used in the group list Address field, then, if a modification is made to the UserID of the Nickname, you do not have to change the item in the Group list. The modification will be automatic when the group rather than the individual is selected.

When composing a message, a Nickname can be used to identify the recipient of a message. All Nicknames are expanded to Real Name and UserID when mail is sent.

For registered users of AEMail, the checkmarked box to the far right of the list heading labeled Expand is used to shrink or expand the group entries in the list. When this box is not checked, only the group heading is displayed without the entries in the group showing. When it is checked, the groups are expanded to show all the members of the group. When first displayed, this item will be checked. However, the system remembers the state of this checkmark so if you should shrink the groups, the next time you select the Address Book only the group headings will be displayed.

For un-registered users, this item will be checked and ghosted. You will not be able to shrink the groups.

Address Book entries are sorted by Nickname and group entries are interspersed with single entries. Also Real Names are presented as first name followed by last name rather than last name, first name.

This is a scrolling list. If there are too many entries to fit in the window, you can scroll the list by using the scroll bar, clicking on the up or down arrows below the scroll bar, or by using the up or down cursor keys.

Additionally the following keys can be used to move the list as follows:

- Home or Cursor Left moves the listview to the top.

- End or Cursor Right moves the listview to the bottom.

- PgUp or Shift Cursor Up pages the listview one page up. The top line of the previous page will be displayed as the bottom line of the new page.

- PgDn or Shift Cursor Down pages the list view one page down.

  - The bottom line of the previous page will be displayed as the top line of the new page.

- The cursor up/down keys on the keypad will have the same action as the normal cursor keys with the exception of the shift feature.

**WARNING:** if you have selected one of the string gadgets for entering data, the cursor keys will not work for scrolling the list. You will have to click outside of the string gadget to re-activate scrolling

---

with the cursor keys.

For adding entries to the Address Book, the entries at the top of the window are used to place data in the various fields of the Address Book entry. If a message was selected when the address book was called, the Real Name:, if present, and Address: fields are filled in with information from the Reply-To: header of the message. If the Reply-To: header is not present, the From: header will be used. You can force the From: header to be used by holding down the shift key when you click on the Address Book icon.

Please keep in mind that Reply-To: addresses normally do not have real names associated with them, but From: addresses many times do. If you want the real name you may have to hold down the shift key when you click on the Address Book icon.

If you access the Address Book from the  
Compose message window  
during a

mailto:  
call to AEMail, the userid from the mailto: will be placed in the address field. This allows you to assign a Nickname and Real Name to this address and save it in your Address Book.

If you click on one of the entries in the list view, that entry will be transferred to the Nickname:, Real Name:, and Address: fields at the top of the window. If you click on a group entry line which has the Group Nickname and DISTRIBUTION LIST in the address portion, only the Nickname: and the Group name (in the Real Name: field) will be transferred leaving any previous address in the Address: field. The Group box will also be checked. This facilitates adding items to a Group list.

When adding an entry to the address book, you must always enter a Nickname and Address. Real Name is optional, but recommended.

To add a group entry, the Group box must be checked. Groups need a Nickname that is unique (not the same as that used for an individual) and should have a group description entered in the Real Name: string gadget. Group entries are entered one at a time. The maximum number of entries that can be added to a group is 3000. When a message is sent to a group, the message will be sent to a maximum of 50 recipients at a time. This takes care of problems when there is a limit on the number of recipient addresses that a SMTP server can handle at a time.

After correctly filling in the top portion of the window, click on the [ADD] button to add the item to the list. Except for group Nicknames, there can't be a duplicate Nickname when adding to the list. An already existing group Nickname will cause the entry to be added to that groups distribution list.

To modify an entry, the Nickname for the entry must already exist in the list. You can not modify Nicknames. If you need to do this, delete the old entry and add a new one. For individual entries, you can modify either the Real Name: or Address: fields. For group entries you can only modify the Real Name: field. If you need to modify an address in the distribution list, delete the old one and add a new one.

---

One of the reasons that Nicknames are preferred in distribution lists is that, if you need to modify a user's address, you can do so by simply modifying the individual's entry. The address in the group is then automatically updated by reference.

Selecting one of the entries in the address list will move the data from that entry to the fields at the top of the window. Make the modifications you want then click on the [MODIFY] button to make the modifications.

To delete an entry, select it in the list and then click on the [DELETE] button. You can also use the  
DELETE icon  
to do this.

The [SELECT] button is used only for one special purpose. If the full Address Book was called from a mailto: call to AEMail, this button is used to select an address from the Address Book and place it in the appropriate recipients address line while composing the message. The Address Book display is slightly different if it was not a mailto: call (see below).

When you click on the [SELECT] button, the Address Book display is closed and the COMPOSE MESSAGE window is re-activated. To determine which header field is to receive the address, the Select cycle gadget at the top of the window is used. There are three items for this gadget: To:, cc:, and bcc:. Determine which field should receive the address and then click on the [SELECT] button. The Nickname for the selected item is transferred to the appropriate field in the compose window.

If the Address Book was not called from the Compose window, the Select cycle gadget will be ghosted and can not be used. If the Address Book was called from the

COMPOSE MESSAGE window  
, clicking on one of the address  
fields before calling the Address Book will automatically select the  
appropriate field in the Select cycle gadget.

You can avoid using the [SELECT] button for returning to the COMPOSE MESSAGE Window by double clicking on an item in the Address Book list view.

If the Address Book was not called from the COMPOSE MESSAGE window, instead of double clicking, the

COMPOSE MESSAGE  
command icon can be  
selected when in the Address Book window. When this is done, the COMPOSE MESSAGE window is activated for composing a new message with the selected address field always being the To: field. The selected address in the Address Book will be moved to the To: field.

The [EXIT] button is used to exit from the Address Book window without performing an address selection for a composed message. You will need to [EXIT] from the Address Book if you want to quit AEMail.

If the Address Book was called while displaying a message, clicking on the





You can also select which field you want to receive the address by clicking into the appropriate field in the

COMPOSE MESSAGE window

. You

will see the cycle gadget switch to that field and the cursor will disappear from the field since the Address Book window will again become activated.

When the Address Book is called from the COMPOSE MESSAGE window it will be in the un-expanded state. If you are a registered user, you can expand the group names by clicking on the Expand checkmark gadget to the right of the listview headings.

You can also have the full Address Book display called from the COMPOSE MESSAGE window by holding down the shift key when you click on the [Call Address Book] gadget.

NOTE: When AEMail is loaded it will automatically create an address book entry for the Nickname AEMAIL with a UserID for my email address: jzachar@calweb.com. You can use this entry whenever you wish to

report a bug

or send a message concerning AEMail to me.

## 1.100 AEMAIL WINDOWS/Message Display Window

### Message Display Window

The Message Display window will be displayed in the lower portion of the screen whenever you double click on a message in the

Message List

window.

If you are already displaying a message, clicking on the

NEXT

or

PREVIOUS

command icons will display either the next or previous message.

If you have a non-interlaced screen (640 x 200), the display will cover the folder strip to allow more room for the message display. With an interlaced screen (640 x 400) you will be able to see and use the

folder strip

.

To re-display the Message List, click on the

folder

icon on the Command

Icon Tool Bar or one of the folders in the folder icon bar (if visible).

The message is divided into two sections: message header information,

---

which is always present, and a scrolling list that displays the message. Header information will also be displayed in the scrolling message listview, but only those header lines that you want displayed.

The message header portion of the screen is set up as follows:

```
From: xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx Date: DOW, MMM DD YYYY HH:MM:SS
To: xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx [ATTACHMENT]
Subject: xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx
```

The From: and To: fields will show the Real Name (if present) from the appropriate header. If the Real Name is not present in the header, then the UserID will be used instead. If a Nickname is being used for a message being sent, then the Nickname will appear. (see  
     Address Book  
     for discussion  
 of Nicknames)

The Subject: field will have the RE: or (FWD) preappended to the field for messages that are REPLIES and/or are FORWARDED.

If the message has attachments, either MIME or UUENCODED, the [ATTACHMENT] button will appear at the right of the To: line. If no attachments are present this button will say [SAVE TEXT] instead. Clicking on the [SAVE TEXT] button will bring up the  
     Save Text Requester  
     along side the  
 [SAVE TEXT] button.

The complete message will be displayed in the message listview including any text type attachments. If the attachments are UUENCODED attachments or are non-text type attachments, they will not be shown, but can be retrieved by clicking on the [ATTACHMENT] button. This will bring up an attachment requestor which is described below under

#### Attachment Requester

.

Messages that are encoded with Quoted-Printable notation as well as text messages encoded with encoded binary (BASE64) will be correctly displayed as well. Since these types of messages will be saved with their encoding intact when saved using the

```
SAVE MESSAGE
icon or the Export... item
```

under the

Messages

menu, the [SAVE TEXT] gadget has been provided to save message text correctly decoded for messages without attachments. For messages with attachments, the first entry in the Attachment list is the body of messages itself.

The message display is a scrolling list. There are four methods that you can use to scroll the message:

- (1) Use the scroll bar to the right of the message.

- (2) Use the scroll arrows at the bottom of the scroll bar.
- (3) Use the up and down cursor keys. You can also move the listview with other keys as follows:

Home or Cursor Left moves the listview to the top.  
 End or Cursor Right moves the listview to the bottom.  
 PgUp or Shift Cursor Up pages the listview one page up. The top line of the previous page will be displayed as the bottom line of the new page.  
 PgDn or Shift Cursor Down pages the list view one page down. The bottom line of the previous page will be displayed as the top line of the new page.  
 The cursor up/down keys on the keypad will have the same action as the normal cursor keys with the exception of the shift feature.

- (4) click the mouse on the list display and while holding down the left mouse button, move above or below the display. When you lift up on the mouse button after the list starts to scroll, you can continue to scroll by moving the mouse up or down. Clicking into the display will stop the scrolling action.

While messages are loaded into the listview, you will not see them until they are completely read. A busy pointer will be displayed until the listview is completely built.

For un-registered users, the message display will be quite slow to load although you will be able to see the message as it is being loaded into the display. If you want a faster display load, register AEMail!

You can also edit and save lines from the message to the clipboard by double clicking on any line in the message. This will open a window at the top of the screen for editing and saving the line to the clipboard. See

Using the Clipboard with AEMail

## 1.101 AEMAIL WINDOWS/Message Display Window/ATTACHMENT REQUESTER

### Attachment Requester

When you click on the [ATTACHMENTS] button on the Message Display Window

an Attachment Requester will be displayed. It looks like this:

```

|=====|
|[o] Attachment List |
|=====|
|           MimeType/SubType           File Name           |

```

```

| ===== |
| | 1 SHOWN      text/plain          | | |
| |   Description: (None)             | | |
| | 2 VIEWABLE  image/gif           castle.gif | | |
| |   Description: Picture of a castle | | |
| | 3 SAVE ONLY application/octet-stream aemail.lha | | |
| |   Description: The AEMail archive  | | |
| ===== |
|
| [   VIEW   ]           [VIEW & SAVE]       [ SAVE FILE ] |
|
| [ SAVE CLIP ]         [ CLIP UNIT ]       [   EXIT   ] |
|-----|

```

This requester is initially placed at the top center of the window partially obscuring the command and folder icons and the top portion of the message. You can drag the requester around the window to expose other items of the display. You can also use the scroll bar on the message display listview to show different parts of the message; however, none of the commands on the command or folder bar or the menu bar can be activated until after you click on the [EXIT] button in the Attachment Requester.

The SHOWN designation is used for any attachment that is displayed in the message window. This is generally any attachment that has a MIME type of text or message. However, standard Mailcap entries have been included in the

Mailcap file

to also display and save these attachments from the Attachment window.

Any message with attachments will generally have one section (the initial message) which is displayable text and will be shown as an attachment with the SHOWN designation. You will also be able to VIEW all SHOWN parts of the message separably. You will always be able to save any item in the list in its un-encoded form.

UUENCODED attachments will have the designation UUENCODED displayed in the MIME types/subtypes field.

Any attachments that do not have a MIME type of text or message will have either a VIEWABLE or SAVE ONLY designation. The VIEWABLE designation is used for those MIME types/subtypes which have a program designated in the

mailcap

file for displaying this MIME type/subtype. If no program is designated for this MIME type/subtype the SAVE ONLY designator will appear on the attachment line and the [VIEW] and the [VIEW & SAVE] buttons will be disabled.

UUENCODED attachments are always SAVE ONLY attachments.

To select an attachment to view, view & save, or to save only, select the appropriate attachment line in the list view gadget. You can select the main description line (with number, mime type, and filename) or the second line with the Description: heading.

After selecting the attachment, the buttons below the listview will perform the following actions:

[VIEW]

This will display the attachment with the program you selected in the mailcap file for this MIME type/subtype.

If a program was not pre-defined for this MIME type/subtype this button will be disabled and you will not be able to display the attachment. You will also see SAVE ONLY rather than VIEWABLE on the description of this attachment.

[VIEW & SAVE]

A file requester will pop up which allows you to select a file to save your attachment to. The default directory designated to receive attachments is RAM;; however, you can change this with the file requester or set a different default with the

Default Path Parameters  
display on the  
Configuration screen

.

If a file name was provided in either the Content-Type: or Content-Disposition: headers, the file name will be shown on the attachment description and will be pre-set as the default filename in the file requester. You can, of course, change this name if you wish.

After the file is saved, the attachment will be displayed with the program you selected in the mailcap file.

If a program was not pre-defined for this MIME type/subtype this button will be disabled and you will not be able to display the attachment. You will also see SAVE ONLY rather than VIEWABLE on the description of this attachment.

[SAVE FILE]

A file requester will pop up which allows you to select a file to save your attachment to. The default directory designated to receive attachments is RAM;; however, you can change this with the file requester or set a different default with the

Default Path Parameters  
Page on the  
Configuration screen

.

If a file name was provided in either the Content-Type: or Content-Disposition: headers or with the UUENCODED begin line,

---

the file name will be shown on the attachment description and will be pre-set as the default filename in the file requester. You can, of course, change this name if you wish.

You will always be able to save any attachment even if it is SHOWN and a filename is not specified.

[SAVE CLIP]

If the attachment has an encoding type of 7-bit, 8-bit, or quoted-printable, you can save the attachment to the current clipboard unit. If the attachment is not a text type attachment (encoded binary), this button will be ghosted.

[CLIP UNIT]

This will bring up the requester that allows you to change the current clipboard unit (see

Using the Clipboard with AEMail  
).

[EXIT]

After performing all the operations you wish for any particular attachment, click on this button to remove the Attachment Requester. This requester also has a CLOSE gadget which you can also use to exit from the requester.

## 1.102 AEMAIL WINDOWS/Message Display Window/SAVE TEXT REQUESTER

### Save Text Requester

When you click on the [SAVE TEXT] button on the Message Display Window

, a

a tiered set of five buttons will appear to the left of the [SAVE TEXT] gadget that look like this:

```
[   VIEW   ]
[ SAVE FILE ]
[ SAVE CLIP ][SAVE TEXT]
[ CLIP UNIT ]
[  CANCEL  ]
```

Clicking on one of the buttons will perform the appropriate action as described below. With the exception of [CLIP UNIT], the buttons will disappear at the completion of the action.

[VIEW]

This will display the message text with the program you selected in the

mailcap  
 file for the "text" MIME type. If a program was not pre-defined for this MIME type, this button will be disabled (ghosted). This option is given so that you can select special message display programs to display the message and perhaps perform special operations of the message. As an example, you could specify an editor which would allow you to make modifications to the message and then save portions of it to a file or clipboard.

[SAVE FILE]

A file requester will pop up which allows you to select a file to save your message to. If the message used a coding scheme such as quoted-printable or encoded binary it will be properly converted before it is saved. The default directory designated to receive this text file is RAM;; however, you can change this with the file requester or set a different default with the

Default Path Parameters  
 Page on the

Configuration screen

.

[SAVE CLIP]

If the text has an encoding type of 7-bit, 8-bit, or quoted-printable, you can save it to the current clipboard unit. If the text is encoded binary, this button will be ghosted.

[CLIP UNIT]

This will bring up the requester that allows you to change the current clipboard unit (see

Using the Clipboard with AEMail  
 ).

[CANCEL]

This gadget is provided to exit from the request without performing any action.

### 1.103 AEMAIL WINDOWS/Compose Message Window

Compose Message Window

The Compose Message Window is brought up whenever you click on the

COMPOSE MESSAGE  
 command icon or select the  
 Compose...

,

Reply...

, or

Forward...  
 sub-menus under the  
 Messages menu  
 . If a message is selected

when you click on the COMPOSE MESSAGE command icon it will act as a  
 Reply to this message action.

The Compose Message window will cover the entire screen. You must proceed  
 sequential through the actions or cancel to abort the compose operation.

The Compose Message window looks like this:

```

=====
Compose a Message (Signature: [full path of signature file active])
=====

    To: [                               ] [CLR] [Call Address Book ]

    cc: [                               ] [CLR]

    bcc: [                               ] [CLR]

Reply To: [                             ] [CLR] [ Use Default ]

    Subject: [                           ] [CLR]

        [ ] New Message                [ ] 7-Bit
        [ ] Reply to Message            [ ] 8-bit
        [ ] Forward Message             [ ] quoted-printable
                                         [ ] encoded binary

[ ] Quote Original Message Text   Quote Prefix[>           ]

    Quote Header: [                       ]

[ ] Add Signature Block   [Select Signature]           [ Edit Signature]

[Compose/Edit Message]   [ Add Headers   ]           [Add Attachments]

[Save In Pending] [Queue Message] [Send Message Now] [Cancel Message]
=====

```

The title bar on the Compose Message window will contain the full path  
 name to the current, in use  
 signature file  
 .

When the Compose Message window first appears and if the message is a  
 replied message, the following requester will appear if the replied  
 message had To: recipients other than yourself:

```
|=====|
```



```

| Multiple Recipients |
|-----|
|           The message you are replying to |
|           has other To: recipients. |
|           Do you want to send the reply |
| |
| [o] to only the sender of the original message? |
| [ ] to all To: recipients of the original message? |
| [ ] cc: to all To: recipients of the original message? |
| [ ] bcc: to all To: recipients of the original message? |
| |
|           [ Continue ] |
|=====|

```

With this requester you can send the message you are composing to none of the other recipients, directly to all the other recipients (in the To: line), as a cc to all the recipients, or as a bcc to all the other recipients.

If there is a single recipient to the message and that recipient is the same as either your From: or Reply-To: address, you will not see the requester. Also, when the list of recipients is transferred to the appropriate address line in the Compose window, any address that is the same as your From: or Reply-To: address will be stripped. If you want to send the message also to the From: or Reply-To: address you will have to add the address yourself.

When you have selected the action you want, hit [Continue] and the list of To: recipients will be transferred to the appropriate string gadget in the Compose Message window.

**SPECIAL CONSIDERATION:** If the message you are replying to was received by a version of AEMail prior to 1.42, you will not be able to transfer recipients that extend beyond one line. You can solve this problem, however, by saving the message you want to reply to to a file (using the

```

export
function) and then reading it back into version 1.43 of AEMail.
To read it back in using the
From Local File..
menu item under the

Retrieve Msgs
menu.

```

One point of warning. If the recipient of the original message was the name of a list rather than the name of an individual, you will also see this requester. Unfortunately, there is no way to know that the recipient name is a list name rather than an individual name. In this event, you should always select "to only the sender of the original message" since the list name is probably not a valid recipient.

If there were cc:'s to the original message, you may also see the following similar requester for sending to the cc: recipients:

```

|=====|

```

```

| Multiple Recipients |
|-----|
|           The message you are replying to |
|           has one or more cc: recipients. |
|           Do you want to send the reply |
| |
| [o] to only the sender of the original message? |
| [ ] to all cc: recipients of the original message? |
| [ ] cc: to all cc: recipients of the original message? |
| [ ] bcc: to all cc: recipients of the original message? |
| |
|           [ Continue ] |
|=====|

```

Again, after you have selected the action you want, hit [Continue] and the list of cc: recipients will be transferred to the appropriate string gadget in the Compose Message window.

If the message is a replied message, the To: string gadget will also be filled in with the Reply-To: address from the message you are replying to or, if that is not present, the From: real name and user ID of the message you are replying to. This is in addition to any action caused by the previously mentioned requesters.

You can force the From: address to be used by holding down the shift key when clicking on the

```

compose
icon or selecting the menu sub-item Use

```

From... on the

```

Reply
menu item of the
Messages menu
.

```

Also, if the message is the result of a mailto: call, the To: string gadget will be filled in with the userid passed by the mailto: call.

If the message is a replied or forwarded message, the Subject: string gadget will be automatically filled in with the subject from the replied or forwarded message. RE: or (fwd) will also automatically appear in front of the subject.

You may enter names, either Nicknames or Real Names and/or UserID's, for any of the To:, cc:, or bcc: fields. If a Real Name and/or UserID is entered, it should be entered as

```

Real Name<userid@domain>           or
userid@domain(Real Name)          or
userid@domain

```

The domain can be left off if the recipient is at the same domain as the user. However, it is best that the full userid@domain be used so there is no confusion with Nicknames.

If a Nickname is used it will be automatically expanded when the message

is sent.

If multiple users are placed in any of the To:, cc:, or bcc: fields they must be separated by commas.

If the users you are sending the message to are in your Address Book, you can click on the [Call Address Book] button. This will call up an abbreviated form of your

Address Book

and you can select the user you want.

Clicking on the user will transfer the Nickname for that user to the appropriate field indicated by the cycle gadget at the bottom of the Address Book window (To:, cc: or bcc:). The Nickname for the user will be automatically added to the appropriate field in the Compose window. If you make a mistake and the wrong name is added or it is added to the wrong field, you can use the backspace key to remove the offending Nickname or the [CLR] gadget to completely clear the field.

The Address Book window will remain displayed to allow you to select multiple names. Multiple names in any field will be automatically separated by commas.

To exit from the Address Book display, either click on the Close gadget at the top of the Address Book window or the [CLOSE] button at the bottom of the window. Alternately, you can double click on the last name you add to a field.

You can also use the [Call Address Book] gadget to place the userid from a mailto: call into your Address Book. In this case the full address book will be shown rather than the abbreviated one. You can also access the full Address Book by pressing the shift key when you click on the [Call Address Book] gadget.

All of the gadgets in the Compose Window remain active when you are displaying the abbreviated form of the Address Book. They are not active when you display the full Address Book. The select cycle gadget in the Address Book can be used to select the field you want the address transferred to, or alternately, you can click into the field you want and the cycle gadget will automatically be set to that field. When you do this, the Address Book window will immediately become activated to allow you to select the address you want or to move the Address Book list view with the cursor keys.

The cc: field is used to send a "carbon copy" of the message to the people in the list on the cc: line. The cc: header will appear on the message sent to the To:, cc: and bcc: recipients. The bcc: field is used to send a "blind carbon copy" to the people in that list. The bcc: recipients will not be identified to any of the recipients of the message.

The Reply To: field is used to place a Reply-To: address header in the message. This field is intended for people who want replies directed to a different email address than their From: address. The configuration item Reply-To: will automatically be loaded into this field when the compose window is displayed. If the Reply To: address for this message should be different than the configured Reply-To address, then place it here. If you click on the [ Use Default ] button, your configured Reply-To address will be placed in this field. If the Reply To: field is left blank, no

---

Reply-To: header line will be added to the message.

The Subject: field is used to create a subject header for your message. If the message is a reply, RE: will be placed in front of the subject. If the message is forwarded, (fwd) will be placed after the subject.

The [CLR] gadget to the right of the To:, Reply To:, Subject:, cc:, and bcc: string gadgets allows you to easily clear the data in the appropriate string gadget.

Below the Subject field is two columns of Radio buttons for selecting the type message to create and to specify the encoding method for the message body. The first column of radio buttons specifies the message type to create. These can be:

- New Message
- Reply to Message
- Forward Message
- Edit Message

Which buttons appear depends on the way the Compose Message window was called.

New Message and Edit Messages appear if a message was selected from the PENDING or QUEUED folders and the COMPOSE MESSAGE command icon was selected or the Edit... menu item was selected from the Messages menu. The Edit Message button is initially highlighted.

New Message, Reply to Message, and Forward Message appears if a message was selected from an input folder (such as INBOX) and the COMPOSE MESSAGE command icon was selected or one of the Reply or Forward... menu items were selected from the Messages menu. If a Reply sub-menu item was selected, the Reply to Message button will be initially highlighted. If Forward... is selected, the Forward Message button will be initially highlighted.

Only New Message appears and is highlighted if no message was selected, if the Compose.. menu item was selected, or if a message in the SENT folder was selected.

New Message also appears if the Compose message window was activated by a

```
mailto: call
from a browser. If a message= argument was provided on
the shell call to AEMail, both the New Message and Edit Message will
appear and the Edit Message item will be highlighted..
```

If the Edit..., Reply or Forward... menu items are selected and a message was not selected, an error message appears. If the "Compose..." sub-menu is selected, a new message will always be created. Likewise, messages cannot be replied to or forwarded from the PENDING, QUEUED or SENT folders. If the Edit... menu item is selected, the message must come from either the PENDING or QUEUED folder.

You can always change the preferred type of message to one of the other ones allowed by clicking on the appropriate message type.

---

The radio button column on the right of the window is for the encoding method for the message body. Four items appear here:

```
7-Bit
8-Bit
quoted-printable
encoded binary
```

The default is 8-bit. Some Internet gateways, however, can not handle 8-bit data - only 7-bit. If this is the case with your situation, select 7-bit, or if your message contains characters above ASCII 128 (most foreign character sets have these types of characters), select quoted-printable or encoded binary.

The quoted-printable encoding is preferred in this instance. You will be able to read most of the raw message except for the extended character set characters. The encoded binary encoding will encode the message in BASE64 encoding which is totally un-readable in it's raw format. AEMail, however, is able to handle the translation of both quoted-printable and encoded binary in the message body for both sending and receiving messages.

If the message is a reply, the Quote Original Message Text box will be checked if you have selected this option in the

```
General Parameters
page of
```

the

```
Configuration screen
```

. You can un-check this box if you don't want the original text quoted in the message (or check it, if the default action was not to include text). For all other types of Compose windows, this checkbox will be disabled.

The Quote Prefix: string gadget will indicate what is to be placed in front of each quoted line. This, by default, is >; however, you can add whatever you like here (such as the person's initials followed by : or >). You can also permanently change this field with the

```
General Parameters
page of the
Configuration screen
```

.

A Quote header: will be placed on the line in front of the quoted material. Currently, the default header which will appear in the Quote Header: string gadget is:

```
On &(week), &(date2), at &(time), &(name) wrote:
```

The & followed by a field name in parenthesis indicates substitution of data from the original message headers. The values that can be substituted are:

```
&(name) The Real Name of the sender of the original
message. If the Real Name is not available,
the sender's UserID will be used instead
```

```
&(subject) The subject from the original message. Any RE:
```

or (fwd) will be stripped.

- &(week) The day of the week that the original message was sent.
- &(date) The date the original message was sent in the form dd mmm yyyy, where dd is the day of the month, mmm is month in the form Jan, Feb, Mar, etc, and yyyy is the full 4 digit year.
- &(date1) Same as &(date).
- &(date2) The date in the form mmm dd, yyyy.
- &(time) The time the original message was sent in the form hh:mm xM where hh is the hour on a 12 hour clock, mm is the minute, and xM is AM or PM.
- &(to) The email address the message was sent to. For mailing lists this could be the name of the mailing list if that is what appeared in the To: header.

The Quote Header is designed to be modified by the user and can be changed with the string gadget. This change is only in effect for this message, however. You can permanently change the Quote Header with the

General Parameters  
page of the  
Configuration screen

.

Whether or not the quoted message's headers are to be included in the quote is controlled by the  
     Incl Hdr in Resp  
     item under the  
     Messages main  
     menu. If this item is checked the Date, To, From:, Reply To:",  
 Subject:, cc:, and bcc: headers will be displayed from the original  
 message. If it is not checked, no header information will be included.

The amount of header information in the quoted message is also controlled by the

Display Full Hdr  
item in the Messages menu.

The row of gadgets below the Quote Header: is used to specify characteristics of your signature file if you want one. They work in conjunction with the full path name of your current active signature file shown in the title bar of the Compose Message window.

If a

signature file  
is present, the Add Signature Block box will be  
checked and the path name of that signature file will appear in the title  
bar. If the signature file is not present, this checkbox will be disabled.  
The default signature file is AEMail:.signature. However, if you are a  
registered user, you can change to any other signature file by clicking on

the [Select Signature] gadget. This will call up a file requester in which you can select the appropriate file. The file does not have to exist; you can create it with the [Edit Signature] gadget.

If you are an un-registered user, the [Select Signature] button will be ghosted and you can only use the standard AEMail:.signature file.

If you want to create or edit the current selected signature file, you can click on the [Edit Signature] button. This will call up your editor to allow you to create or edit the selected signature file. After you have edited or created your signature file in your editor, save the file and exit from the editor. This will return you to the COMPOSE MESSAGE window and the Add Signature Block check box will now be enabled.

If you do not want the signature block placed at the end of your message, uncheck the Add Signature Block box.

Note: if the message is being edited, the Add Signature Block box WILL NOT be checked. This is done to prevent two signature blocks being added to the message. However, rather than disable this item, it is left to allow the user to add a signature block in the event one was not added to the original message or you selected the new Message radio button.

The [Add Attachments] button brings up the  
Add Attachments Requester  
. This

requester allows you to add one or multiple files as attachments to your message. You can bring up this requester at any time. If it is brought up a second time, the old attachment information will appear in the attachment list. You can add to this information or delete entries as you desire.

The [Compose/Edit Message] gadget calls up the editor you specified in the General Parameters page of the Configuration Screen. If you are editing a previously composed message, you will see that message in your editor window. You can make changes as appropriate. Also, if you specified Quote Original Message Text you will see the quoted text. You can delete and insert lines as appropriate.

One of the things you will NOT see in the editor window are your message headers or the signature block unless it is an edited message. The signature block is always added after you compose the message. If this is a new message, you will see a blank editor screen when the editor is first called. Enter whatever text you wish to use in your editor's window and then select Save and Quit from your editor's menus. This will return you to the Compose Message window.

You will not be able to edit or add headers when you [Compose/Edit Message]. If you need to add additional headers to a message you can use the [Add Headers] gadget to add the headers. This feature is ONLY available to registered users. Un-registered users will find this gadget ghosted.

Clicking on the [Add Headers] gadget will bring up the  
Add Headers window  
which is very similar to the Information window for a icon which ←  
is  
called from the Workbench menus.

At the bottom of the Compose Window is a row of four action buttons as follows:

[Save In Pending] [Queue Message] [Send Message Now] [Cancel Message]

If you decide that you do not want to compose a message after all, click on the [Cancel Message] button to exit the COMPOSE MESSAGE window.

Otherwise, if all the correct information has been added in the COMPOSE MESSAGE window, click on the appropriate action button at the bottom of the window. [Save In Pending] will save your newly created message in the PENDING folder. [Queue Message] will place the message in the QUEUED folder and [Send Message Now] will send the message provided that you are connected to your Internet Provider. If you were unsuccessful with sending the message, it will be stored in the QUEUED folder to allow you to immediately send the message when you re-connect to your Internet Service Provider.

## 1.104 AEMAIL WINDOWS/Compose Message Window/ADD ATTACHMENTS

### Add Attachments Requester

When you click on the [ADD ATTACHMENTS] button on the Compose Message

Window, an Add Attachments Requester will be displayed which looks like this:

```

=====
[o] Add Attachments
=====

          Filename: [                               ] [REQ]
Attachment Description: [                           ]
          Content Type/SubType: [                     ]
                                     =====
                                     | text/plain           | |
                                     | text/enriched          | |
                                     | text/richtext           | |
                                     =====
          Encoding: |@|           Plain Text           |

Mime Type/Sub-Type  FileName                      Encoding
=====
|                               | |
|                               | |
|                               | |
|                               | |
=====

[ ADD ]           [DELETE]           [ APPLY ]           [CANCEL ]

```



=====

The Filename string gadget should contain the FULL path name and filename of the attachment. Clicking on the [REQ] gadget will bring up a file requester which will allow you to select the appropriate file. The filename portion of this string will be used as the "file=" parameter of the Content-Type MIME header and as the "filename=" parameter of the Content-Disposition MIME header.

The initial directory that is chosen for the file requester is the directory that was set up in the Add Attachment from Directory string gadget in

Configuration: Default Path Parameters

. If you are adding

multiple attachments to the message, clicking on [REQ] will bring up the last directory that you used.

If you enter a non-existent file, an error requester will be displayed when you try to [ADD] the file to the attachment list.

The Attachment Description is an optional string gadget for entering a description of the attachment. If present, this string gadget will create a Content-Description MIME header.

Content Type/SubType is a string gadget which contains the MIME Content Type/Subtype entry which will appear on the Content-Type MIME header. THIS IS A REQUIRED ENTRY UNLESS YOU ARE ADDING AN UUENCODED attachment. It is not used for UUENCODED attachments.

A scrolling list below this gadget is used to select an appropriate type/sub-type. Predefined type/subtypes, as defined in RFC 1341 and RFC 1521, are included in this list as follows:

```
text/plain
text/enriched
text/richtext
message/rfc822
message/partial
message/external-body
multipart/mixed
multipart/alternative
multipart/digest
multipart/parallel
application/octet-stream
application/postscript
image/gif
image/jpeg
audio/basic
video/mpeg
```

Also added to this list will be any additional type/subtypes added through the

mailcap file

and any type/subtypes encountered when displaying attachments during THIS RUN OF AEMAIL. AEMail has no way to remember differing type/subtypes that it encounters unless they are included in the mailcap file.

You can also add your own type/subtype by directly entering it in the Content Type/SubType string gadget. Unless the type/subtype is well known and published, you should pick one of the existing types (text/, message/, application/, image/, audio/, or video/) and use a subtype beginning with "x-". As an example, you might want to define an IFF image (not part of the mime published standard) as:

```
image/x-iff
```

It is suggested that you use a mailcap entry for image/x-iff to cause it to permanently appear in the list of Content Type/Subtypes. Attachments must be in the format you select. AEMail will do no conversion. As an example, if you select application/postscript, the file you attach should already be in postscript format.

Also, {i}DO NOT use the following types/subtypes:

```
message/partial
message/external-body
multipart/mixed
multipart/alternative
multipart/digest
multipart/parallel
```

All of the multipart types are not supported except at the highest level (specifying the initial attachment list), and this is done automatically by the program.

The encoding cycle gadget has four states as follows:

```
Plain Text
Quoted-Printable
Encoded Binary
UUENCODED
```

Generally, Plain Text should be used for:

```
text/
message/
```

The exception to this is when the attachment contains characters outside the range of ASCII 32 to ASCII 128 and you ISP can not handle 8-bit codes. If the document you are attaching contains these characters (usually present in documents using foreign character sets), you should use Quoted-Printable or Encoded Binary encoding.

---

Generally speaking Encoded Binary should be used for the following types:

```
application/  
image/  
audio/  
video/
```

UUENCODED should be selected if you want the attachment to be in UUENCODED format. You can not mix UUENCODED attachments with MIME attachments!

When a type/subtype is selected, the appropriate encoding format is automatically selected. Of course, you can change this with the cycle gadget if there is a need.

Once all of the attributes for any particular attachment are selected, click on the [ADD] gadget to add the attachment to the attachment list. If the Filename field or Content Type/Subtype field (other than for UUENCODED attachments) is blank an error requester will appear indicating that you must have a valid entry in these fields. As many attachments as you want can be added to this list, but you can not mix MIME type attachments with UUENCODED attachments.

If you wish to delete any particular gadget, select the attachment from the list and click on [DELETE]. There is no way to modify attachment attributes once they have been added to the list. If you want to do this, first click on [DELETE], make the appropriate changes, and then click on [ADD].

Once you are satisfied with your attachment list click on [APPLY]. The Add Attachments Requester will disappear and the attachments will be automatically added to your message after it is composed.

If you decide that you don't want to add attachments after all, click on [CANCEL] and the attachments will not be added when you compose your message.

Clicking on the Close Gadget at the top of the window has the same effect as if you clicked on [CANCEL].

If you are editing a message which has attachments and you select the [ADD ATTACHMENTS] button in the Compose Window and then decide you do not want to change the attachments you have previously added, you should click on [APPLY]. Clicking on [CANCEL] at this point will bring up a special warning requester which says:

```
Continuing will delete all previous attachments  
Use APPLY if you wish to keep them.
```

```
[CONTINUE]
```

```
[APPLY ATTACHMENTS]
```

To keep the attachments you should click on [APPLY ATTACHMENTS].

---

## 1.105 AEMAIL WINDOWS/Compose Message Window/ADD HEADERS

### Add Headers Window

Clicking on the [Add Headers] gadget in the Compose Message window will bring up the Add Headers window which is very similar to the Information window for a icon which is called from the Workbench menus. The Add Headers window looks like this:

```

=====|
|[o] Add Additional Headers |
=====|
|                               |
|                               |
|           =====|
| Headers |                               | ||
|         |                               | ||
|         |                               | ||
|[ NEW ] |                               | ||
|           =====|
|[DELETE] [                               ]|
|                               |
|   [ SAVE ]           [CLEAR ALL]           [CANCEL] |
|                               |
|=====|

```

Your additional headers will appear in the scrolling list. To add a header to the list, click on [NEW] and enter the complete header line in the string gadget below the scrolling list. Be sure and include the header identifier as well as the header text. To add this new header to this list hit the [RETURN] key. To transfer a header to the string gadget for editing or deleting it, click on the header line in the scrolling list. Clicking on [DELETE] will then delete the header from the list. If you want to edit the header, make the changes you want and then hit [RETURN]. When you are satisfied with the headers you want to add, click on [SAVE] and the new headers will be saved and added to your message. [CLEAR ALL] will clear all the headers from the list and [CANCEL] will cancel the operations.

## 1.106 AEMAIL FILES

### AEMAIL Files

The following are the various files used by AEMail. Normally, they all reside in the AEMAIL: directory with the exception of the aemail.cnfg file, the TCPLOG file and the mailcap file. The aemail.cnfg file normally resides in the S: directory, and both the TCPLOG file and the mailcap file may or may not reside in the AEMAIL: directory depending on the user's preference.

```

aemail.cnfg
file: Main AEMail Configuration file

```

```

folder.config

```

```
file: configures folders

[folder_name].config
file: configures message lists

Message
files: each individual message

.signature
file: your signature

.addrbook
file: address book entries

.headers
file: list of headers for minimum headers

mailcap
file: used for displaying MIME attachments

TCP Trace Log File (TCPLOG)
: transaction trace file
```

The aemail.cnfg file is the main configuration file for AEMail.

You can override the AEMAIL: assign by using the  
MAIL\_DIR=  
Tool Type and  
you can change the name and location of the aemail.cnfg file with the

```
CONFIG=  
Tool Type.
```

**SPECIAL NOTE:** If the AEMAIL: assign is missing or is incorrect and you do not have a MAIL\_DIR= Tool Type, you will not be able to run AEMail.

With the exception of the mailcap file, you can begin AEMail without any of the other files being present. They will be automatically created as you process messages or do other AEMail actions.

The mailcap file, if used, **MUST** be setup prior to executing AEMail. This can be done using any text editor or through the  
Installation  
process.

## 1.107 AEMAIL FILES/mailcap

mailcap file

The mailcap file is used to establish programs that should be executed to display MIME attachments. Use of this file allows AEMail to use any AmigaDOS operating system 2.1 or above.

The mailcap file is a standard Internet file which is specified in RFC

---

(Request For Comment) 1524. Since it is standard, you can use a mailcap file that was created for another program that specified a display program for the same media type. That is the reason that AEMail allows you to specify the directory that contains the mailcap file with the

Tool Type

MAILCAP\_DIR=

or the

Configuration Screen

. If you did not include

this Tool Type or change the specification in the

Default Path

page of

the Configuration Screen, the mailcap directory will default to the AEMAIL: directory.

AEMail only uses the two required fields of the RFC 1524 standard. Other fields are ignored at this time.

Each mailcap file consists of entries that describe the proper handling of one media type at the local site. A mailcap file consists of a sequence of such individual entries separated by LINE FEEDS. Blank lines and lines starting with '#' are considered comments and are ignored. Long entries may be continued on multiple lines if the line to be continued ends with a backslash character ('\'). In this event, multiple lines are to be treated as a single mailcap entry. Note that for such "continued" lines, the backslash must be the last character of the line to be continued.

Each mailcap entry consists of a number of fields each separated by a semicolon(';'). The first two fields are required, and must occur in the specified order. The remaining fields are optional and may appear in any order. NOTE: At this time AEMail does not use these optional fields and if they are present, ignores them. Because of this, these optional fields WILL NOT be discussed in this documentation.

The general format of the mailcap entry is:

```
content type; view command [; .....] LINE FEED
```

The first field is the content type, which indicates the type of data this mailcap entry describes how to handle. It is to be matched against the type/subtype specification in the Content-Type MIME header (see the

```
    Add Attachment Requester
    which is part of the
    Compose Message window
  ).
```

If the subtype is "\*", it is intended to match all subtypes of the named content type.

Examples of the content type field are:

```
images/gif
```

which is intended to match only the images/gif type/subtype whereas

```
images/*
```

matches all image types (images/gif, images/jpeg, etc).

The second field, view command, is a specification of how the attachment meeting the content type specification is viewed. For any particular operating system, this would indicate how the display program is called. For AEMail this would include the entire path name for calling the program and any parameters that are needed on the command line. A %s is used to indicate the substitution of the attachment name. The entire entry should be surrounded by quotes. As an example:

```
"sys:Utilities/multiview %s screen"
```

would call MultiView, placing the displayed attachment on its own screen (the screen parameter).

If you needed to have the display on the Workbench screen you can add the keyword `wb;` in front of the program path. As an example, if you wanted MultiView to open on a window on the Workbench screen, you could use:

```
"wb;sys:Utilities/multiview %s"
```

Note the use of the quotes (") surrounding the parameter. This is necessary so that the mailcap interpreter will be prevented from treating special characters (such as ;) as part of the mailcap syntax.

Also note the absence of the screen keyword. The above call would push the Workbench screen to the front when MultiView was called and the Workbench screen would be used for the MultiView window. The only problem with this is you would be limited to the number of colors and the resolution specified for Workbench. Some other programs, however, might only be able to open as a window on the Workbench screen and would be hidden by the AEMail screen when those programs were called unless the `wb;` parameter was specified.

An example of a complete mailcap entry to use MultiView to display all images would be:

```
image/*; "sys:Utilities/multiview %s screen"
```

Any image/ type, regardless of the subtype, would be displayed providing there was an appropriate data type present for that image subtype.

A

sample mailcap file

---

is included with the archive which uses MultiView for text, message, sound, image, and video files. Since MultiView is a 3.x program using datatypes, this mailcap file will ONLY work with 3.x systems. To make it work for 2.x systems, you would need to change the display programs to your favorite programs that work with your system. You might also have to be specific as to the subtype for a specific display type/subtype. If you

install AEMail on a 2.1 system using the provided installation script, you will be able to create the mailcap file provided you selected Expert mode for the installation "user mode".

## 1.108 AEMAIL FILES/mailcap sample file

Sample mailcap file

This is the sample mailcap file used for AmigaDos 3.x that uses MultiView as the display agent. Please note the use of the screen parameter which tells MultiView to open on it's own screen rather than the WorkBench screen. This allows the use of all colors in the image's palette.

```
text/*; "sys:Utilities/multiview %s"
message/*; "sys:Utilities/Multiview %s"
image/*; "sys:Utilities/multiview %s screen"
audio/*; "sys:Utilities/multiview %s screen"
video/*; "sys:Utilities/multiview %s screen"
```

## 1.109 AEMAIL FILES/aemail.cnfg

General Configuration File (aemail.cnfg)

The General Configuration file (s:aemail.cnfg) contains various configuration information including the version and revision number of the AEMail version that was last loaded. A special flag in this file indicates whether this file should take precedence over the Tool Type entries.

This file is normally placed in the S: directory rather than the AEMAIL: directory. The reason for this was that if you changed the location of the AEMAIL: directory, AEMail would not be able to locate the new configuration file the next time you loaded AEMail. Also, the S: directory is more commonly used to store configuration files for AMIGA programs.

You do not have to store this file in the S: directory nor do you have to name it "aemail.cnfg". This is only the default name and location for this file. With the use of the

```
CONFIG=
Tool Type or the
config=
parameter on the
```



shell call for AEMail, you can rename the file and place it anywhere you want.

With AEMail version 1.13 you can also have multiple configuration files. This allows you to set up multiple configurations for different users of AEMail. You can select which configuration you want through the

Project/Configuration/Open  
menu item.

If the configuration is never changed with the  
Configuration Screen  
, the

Tool Type entries  
will take precedence. If either the [SAVE] or [SAVE TO]  
gadgets in the Configuration Screen is selected, or the

Project/Configuration/Save  
or  
Project/Configuration/Save to  
menu items

are selected, the General Configuration file will always take precedence.

The s:aemail.cnfg (or CONFIG= Tool Type or config= shell parameter) is referred as your base configuration file. You can always return to the base configuration through the

Project/Configuration/Restore Default  
menu item.

If you display the AEMail General Configuration file with a text editor, you will find that not all portions of the file are readable as text. The only way you can create and update the general configuration file is through AEMail itself.

As part of this file is your password stored in encrypted format.

## 1.110 AEMAIL FILES/.headers

.headers

The .headers file provides a list of message headers. Those that you want displayed in the message as "minimum headers" are preceded by an asterick (\*); all other headers are preceded by a space.

The .headers file may not be present. If it is not, the following are displayed as the "minimum headers":

Date:  
From:  
Reply-To:  
To:  
cc:  
bcc:

Subject:

See the discussion on configuring minimum headers in the  
     General Parameters  
     section of the  
     Configuration Screen  
     .

## 1.111 AEMAIL FILES/folder.config

folder.config

This file gives the general information about each of the folders including:

Flags (long word, 4 bytes): general flags concerning this folder  
 Name (9 bytes including ending NULL): short folder name  
 Pen (1 byte): pen number for folder tab  
 Sort Keys (8 bytes): the permanent sort keys for the folder  
 Folder Description (string ending in LINE FEED): the folder  
     description. If this is a folder for one of the pre-set  
     folders, this string will be empty (LINE FEED only) unless  
     the user has decided to change the folder description.  
 Each Filter string ending in a LINE FEED. Each string begins with 4  
     bytes that provide filter parameters as follows:  
     1 byte indicating the header to be searched  
     2 bytes of flags  
     1 byte indicating the compare criteria  
 Three successive LINE FEEDS ends each folder config entry.

For those fields that are strings: if the field is empty there will be a  
 LINE FEED with no data preceding it. If filters have been specified, each  
 filter will have at least 4 bytes followed by the search argument (if  
 present) and a LINE FEED.

folder.config files for versions prior to 1.40 can be read by AEMail  
 version 1.40 or later. However, once a filter has been added, earlier  
 versions can not properly read the version 1.40 or later folder.config.  
 If no filters are added, earlier versions of AEMail can still read the  
 folder.config file.

It is suggested that you copy your current folder.config file to  
 folder.config.old before implementing AEMail 1.40. The Install script  
 will do this for you with a prompt.

NOTE: if for some reason your folder.config file becomes corrupted or is  
 accidentally deleted, you can restore all of the folders and the messages  
 within them, providing a

    [Folder\_Name].config  
     file is present for the

folder, by doing the following:

    delete any current folder.config file (or rename it so it is  
     no longer recognized).  
     Run AEMail. Add any additional folders that you previously

had added. (INBOX, PENDING, QUEUED and SENT will automatically be created). You must use the exact name you had previously used.

The new folders will show 0 messages.

Quit AEMail.

Re-Run AEMail. The new folders should now show the appropriate number of messages provided a valid Folder\_Name.config file was present for that folder. The name of the new folder must exactly match the Folder\_Name in the Folder\_Name.config file.

## 1.112 AEMAIL FILES/@{i}Folder\_Name@{ui}.config

Folder\_Name.config

For each of the folders that contain messages there will be a configuration file which gives information on the messages in that folder. The name of the file will be the short folder name with ".config" appended to it.

For this version of AEMail, the Folder\_Name.config file contains the following information for each message in the folder:

Message Flags (word, 2 bytes): Flags describing the message.  
File Code (long word, 4 bytes): this field is a binary field which is used to derive the file name for the message file itself.  
Message Size (long word, 4 bytes): size of message.  
Body Displacement (word, 2 bytes): the position where the body of the message starts.  
From (string ending in LINE FEED): the information in the From: field in the message header.  
Subject (string ending in LINE FEED): the information in the Subject: field in the message header. The RE: and FWD: headings at the beginning of the Subject header are stripped, but indicated by flags in the Message Flags field so that the exact subject field can be reconstructed.  
Date (string ending in LINE FEED): the information in the Date: field in the message header.  
To (string ending in LINE FEED): the information in the To: field in the message header.  
Reply-To (string ending in LINE FEED): the information in the Reply-To: field in the message header.  
cc (string ending in LINE FEED): the information in the cc: field in the message header.  
bcc (string ending in LINE FEED): the information in the bcc: field in the message header.

For those fields that are strings: if the field is empty, there will be a LINE FEED without any data preceding it.

NOTE: For AEMail versions prior to 1.42, only the first header line of any particular header type (ie, To:, cc:, etc.) was saved in the header strings of the Folder\_Name.config file. For version 1.42 and later, the

complete header string is saved with all lines of the particular header type. Up to 4096 characters can be saved (if there are that many lines for a particular header type).

This is particularly important for messages that have multiple To: or cc: recipients. This means that the complete list of recipients can be examined in

```

Filter
  commands and also provides the capability to send
replies to
  all the recipients
  of a message.

```

This does create a problem, however, if the Folder\_Name.config created by Version 1.42 or later is read by a version of AEMail prior to 1.42. The Version 1.42 or later Folder\_Name.config file that contains any message that has long multiple recipient lists (more than one line) can not be read correctly by versions prior to 1.42. If you need to revert to an earlier version of AEMail, you can do the following:

```

With Version 1.42 or later,
  export (save)
  all messages with multiple
recipients that were read by 1.42 or later to a file. You do not have to
worry about messages read by earlier versions.

```

```

Delete
  all of the messages you just saved.

```

```

Then, from the earlier version of AEMail,
  retrieve from file
  the messages
you just saved. The header lines will be truncated by the earlier
version.

```

The reverse is also possible. Messages with multiple recipients read by earlier versions will have their header data truncated. You can export (save) the message to a file and then re-read it into AEMail with all header data intact.

### 1.113 AEMAIL FILES/.addrbook

```
.addrbook
```

This file provides address book information. Each record looks like this:

```

Version (word, 2 bytes): The address book version. Prior to
  Version 1 of the address book, this and the following field
  did not exist. The flag $8000 identifies this as a
  legitimate version field to distinguish the address book
  file from version 0. NOTE: The Address Book version is
  NOT the same as the AEMail Version. The Address Book
  version only changes when the format of the Address Book

```

changes.

Flags (word, 2 bytes): Flags describing group actions. In Version 0, the flags field was given in the high order byte of the count field which limited the group count to 255.

Count (word, 2 bytes): If this field is zero, the entry is a single user entry. If this field is greater than zero it represents a group entry and indicates the number of UserIDs in the group.

Nickname (string ending in LINE FEED): the Nickname for this entry (both group or user).

Real Name (string ending in LINE FEED{ui}): the Real Name for individual users or the group description for group entries.

UserID (one or more strings ending in LINE FEEDS): The number of UserID fields is determined by the count at the beginning of the record. For individual users, this MUST be the UserID and Domain for that user. For group users this can be a Nickname that points to the real user.

For a description of how entries in the address book can be created and displayed see the

Address Book  
window.

## 1.114 AEMAIL FILES/.signature

.signature

This is a flat ASCII file that contains the signature block that is to be appended to any composed messages. Each line of the signature block must end in a LINE FEED.

A facility is provided when composing messages to create and or edit this signature block (see the

Compose Message  
window description).

Starting with AEMail Version 1.20, multiple signature files can be used. These signature files can be named whatever the user wishes and can be placed wherever the user wishes (Registered Users ONLY).

## 1.115 AEMAIL FILES/Messages

Messages

Each message is stored as an individual file with a cryptic file name generated from the File Code in the

[Folder\_Name].config  
file. This name

begins with "AE" and ends with "M" with a number of numeric digits in

between. The message is stored as a flat ASCII file as it is received from the POP Server with any CARRAGE RETURNS in a CARRAGE RETURN/LINE FEED sequences stripped. This follows the AMIGA format for ASCII files.

The complete message is stored along with any attachments as they were originally received. Any particular message can be copied to a named file anywhere in your system through the

SAVE MESSAGE TO FILE  
command. If

you have an off line program that can process a MIME message or a message with UUENCODED attachments, you can use that program against this file to extract the attachments or you can save that attachment directly with the

Attachment Requester  
in the  
Message Display Window

.

If messages are left in the PENDING or QUEUED folders, two additional files may be created when AEMail terminates. If attachments were added to the message when it was created, a file with the same name as the message file but with AT appended to it will be created. This file contains information about the attachments. A second file may be created if additional headers were created. This file has HD appended to the original message name.

Both of these files are deleted when AEMail is loaded and the PENDING and QUEUED message lists are created internally. The files are re-created if the messages remain in the PENDING or QUEUED folders when AEMail terminates.

PLEASE NOTE: if the Folder\_Name.config file is deleted you will lose all capability of retrieving your messages unless you have previously copied them to named files.

## 1.116 AEMAIL FILES/TCPLOG

TCP Trace Log File (TCPLOG)

This file is present if you have specified

TCPLOG=name-of-log-file

in the

Tool Types  
parameters or named a TCP Logging File in the

Default Path Parameters  
page of the  
Configuration screen

. Since

name-of-log-file must be the full path name of the log file, this file may or may not reside in the AEMAIL: directory.

The TCP Trace Log File traces every TCP transaction. Each time AEMail is started the following record is written to the file:

```
Logging Beginning at dd mmm yy hh:mm:ss
```

where dd is the day of the week, mmm is the month (Jan, Feb, Mar, etc), yy is the 2 digit year (97) and hh, mm, and ss are the hour (24 hour clock), minutes, and seconds.

Each logging record will consist of a 38 byte header and up to 82 bytes of either descriptive information or actual data received or sent over the TCP interface. The header consists of a 21 byte date/time stamp (dd mmm yy hh:mm:ss) and a 16 byte routine name of the routine in AEMail that called the trace.

If data is displayed, instances of a CARRAGE RETURN will be displayed as <CR> and of LINE FEEDS as <LF>. If the data exceeds 82 bytes, <---> will be placed at the end of the line.

When AEMail terminates, or the TCPLOG file name is changed by the Configuration screen, the following record is written to the file:

```
Logging Ending at dd mmm yy hh:mm:ss
```

Each AEMail session is stacked behind the previous one, so that any single TCPLOG file can become quite large. Periodic purging of the file can occur by deleting the TCPLOG file in between sessions of AEMail. Also, a new file is created when you change the name of the TCPLOG file with the Configuration screen.

## 1.117 BUG REPORTS & SUGGESTIONS

### Bug Reports and Suggestions

Bugs should be reported to:

```
jzachar@calweb.com
```

by email. You can also use the nickname AEMAIL which has been automatically stored in your

```
address book
```

.

In reporting bugs, be as complete as possible in describing the circumstances leading up to the bug. It would be helpful if you indicate all actions (mouse clicks, etc) that you took before the problem occurred. If you are having problems connecting to your Internet provider, or sending or receiving mail, you should activate the

```
TCP Log file
```

and send a copy of the log as an attachment to your message. You might want to block out any password that is contained in the file before you send it to me, however. You can do that

---

with any text editor.

I would also appreciate any suggestions that you have for improving AEMail. I will not guarantee that I will accept all suggestions or that I will necessarily implement them in the next release; however, I do take each suggestion seriously. In the past I have implemented a number of suggestions made by my testers. I will attempt to respond to each suggestion that is made.

In making suggestions keep in mind some of the restraints that I have placed on AEMail: (1) The program should be able to be run on any version of AmigaDos 2.1 or greater, and (2) with the exception of TCP/IP stack software (the standard Amiga does not come with such software), AEMail should not require any extension to your system that does not come with a standard AmigaDOS release. This effectively rules out MUI. Using an editor of your choice meets this criteria since you can use the standard AmigaDOS editors, ED or MEMACS, which come with the standard AMIGA systems.

When reporting bugs or making suggestions, please be as complete as possible in describing the circumstances that brought about the problem or how the suggestion could be implemented.

## 1.118 REVISION HISTORY

### REVISION HISTORY

Version 1.43 Released January 15, 1998. This release is essentially identical to Version 1.42 with the addition of the documentation files and the installation script. Some bugs that appeared after 1.42 was released are also corrected.

Bug fixes and new features in version 1.42 (version 1.43) are as follows:

Corrected a bug with the Address Book Window where selecting a group nickname would sometimes wipe out the address left in the address field. It now works correctly in all situations. The address is left in the address field to facilitate adding addresses to group entries.

Corrected a bug in the sort order when selecting messages in the order received if the folder contained in excess of 999 messages. The order is now correct to 9,999 messages. Note: because some messages do not have the correct date in them (their computers did not have a correct date set), you will see messages that appear out of order by date if you set the order received criteria. This is not a bug since even though the date was incorrect, the order is maintained



as to when the message was received.

If you gave a description to a folder that was too large to fit on the

Message List Window list view heading line, the system crashed. The description is now truncated if it will not fit in the list view heading.

Corrected a bug in which a minimum header specification would not display a header that did not have the same case as the specification (i.e., CC:, Cc: headers would not display for a cc: minimum header specification). The check is now case insensitive.

Added the Last Selected menu item under Messages . If you did a multiple selection on a group of messages and then performed an operation on the group of messages (such as deleting, copying, saving the group to a file, etc.), the messages will be de-selected as the operation is performed on each message. The Last Selected menu item will allow you to re-select the same previously selected messages so that you can perform another operation on the same group of messages.

Added [Last Saved] and [Last Used] buttons to the

Sort Window . This allows the user to restore the sort criteria that was last saved or last used.

Filtering of messages is now no longer restricted to the first line of a particular header. This is particularly true of messages that have been sent to or cc'd to multiple recipients. Now the entire To: or cc: header is checked if specified as the filtering criteria.

To accommodate the ability to filter on the complete list of recipients and to provide the capability to send replies to all To: and cc: recipients (see below), the

Folder-Name.config file format has been changed.

The filtering criteria specification for headers which contain substrings is changed from "Equals" to "Contains" and from "Not Equal" to "Does Not Contain". This provides

---

no difference in operation and is only a syntactical change.

For registered users only, two new field types have been added for filtering: Other Message Hdrs and Message Body. Filtering for Other Message Hdrs will check any other header that might be in the message and Message Body will check data that is contained within the message.

Increased the size of the string gadgets in the

COMPOSE MESSAGE window  
for To:, cc:, and bcc: to allow  
long multiple address strings. Up to 4096 bytes are now  
allowed for these strings. Individual addresses (name and  
email address) are still restricted to what can fit on one  
message line (maximum of about 70 characters).

Allowed the ability to add multiple recipients of messages  
that are responded to to either the To:, cc:, or bcc:  
fields. If there are multiple recipients or one or more  
cc: addresses in a message that is being replied to, a  
special requester will appear on the

COMPOSE MESSAGE  
window to allow the addition of these addresses.

Corrected a bug that sometimes caused headers in messages  
being composed to be garbled. This was a rare occurrence.

When sending messages using the  
Send Message Immediately  
command from the  
Command Icon Tool Bar  
the default folder  
used to send the message is now the QUEUED folder and not  
the PENDING folder. You will have to select the PENDING  
folder if you want to send the messages from there.

When  
sending messages  
to more than one recipient, the  
progress window will now report Sending to n of n  
recipients of message n of n. You can also abort the send  
as each recipient is contacted.

When you call the  
Address Book  
from the  
Compose window

,  
you can click into the To:, cc:, or bcc: field to select  
which field you want the address from the Address Book  
to be added to. You will notice that the select cycle gadget  
will automatically reflect the field you are adding the  
address to. This works with both the special Address Book  
and the full Address Book if it is called from the compose  
window.

---

If you call the Address Book directly, the select cycle gadget is ghosted since it has no effect. If you call the compose window FROM the Address Book the selected address will appear in the To: field only (this is the way it always has worked even if you were to have selected a different field in the cycle gadget).

Additional icons are active when the Address Book is called directly. These are the current folder message list icon and the previous and next folder message list icons.

Version 1.42 Limited release on January 1, 1998. This release contained the changes and bug fixes listed above under Version 1.43 without the documentation files or installation script.

Version 1.41 Limited release on November 1, 1997. Released on diskette as a registered version at the MAE show. Several minor bugs were corrected with this release as follows:

Corrected a bug that occurred when you double-clicked on a name in the Address Book when composing a message. The [Call Address Book] gadget remained ghosted (disabled) after the Address Book was closed. It is now enabled.

When reading attachments, if the [Save Clip] button is ghosted (disabled), the [Clip Unit] button will also be disabled.

If there are multiple attachments to a message, when you save an attachment AEMail will now remember the drawer you saved it to. However, if you read another message with attachments, the directory will return to the default save directory.

If you are unable to send a message when you click on [Send Message Now] in the compose window the message will be stored in the QUEUED folder rather than the PENDING folder. This will allow you to immediately send the message when you re-connect to your Internet Service Provider.

Version 1.40 Released October 10, 1997. Major enhancements and

---

corrections in this release are:

Added the ability to filter incoming messages to specified folders. (see

Filter Selection Window

) This ability acts

on information in the header of the message to determine where to direct a message. Wild card capability, ignoring case capability, and simple AND or OR relationships can be specified in the filtering criteria. You can also exclude messages from being stored in any folder including the INBOX.

Corrected a bug which caused the system to freeze if you double clicked on the [Add Address Book] gadget in the

Compose Message window

(or clicked on the gadget after the

Address Book

was displayed). When you click on the [Add Address Book] gadget in the Compose Message window it will now become disabled until you close the Address Book window.

Corrected a problem that sometimes occurred if you received an error from your service provider when you were sending a message. You would get constant error messages saying that the system could not open the output mail. The error message from the service provider was also shifted to the right and off the screen. It is now correctly displayed.

Corrected a problem that could cause a GURU when sending a message if the combined length of the Real Name (from the

Address Book

) and the UserID from the Address Book was greater than 71 characters. Now, if this occurs, only the UserID is placed in the To: field of the message. Also, when placing the UserID in the Address Book you are limited to 70 characters.

The Novice user level has been removed from the

AEMail\_Installation

script. Intermediate is now the minimum user level that you can install AEMail. The Installation script also provides for backing up your folder.config file.

Version 1.31 Limited release on September 24, 1997.

Increased the size of the UserID that could be entered.

All configuration items in the

Identity

configuration page

have a maximum entry size of 99 characters with the exception of the Password which is limited to 30 characters.

Version 1.30 Released September 1, 1997. Major enhancements and corrections in this release are:

Clipboard support has been added to AEMail in the following manner:

- (1) All string entry gadgets allow copying to and pasting from the clipboard.
- (2) Multiple clipboard units can be specified (up to 256)
- (3) The message body can be copied in it's entirety to the clipboard.
- (4) Any line in a message can be edited and copied to the clipboard. While it is being edited you can paste data from another clipboard unit into the line being edited.
- (5) A unique feature has been added where you can display the contents of all clipboard units currently active. You can select a item from this list to paste into a string entry gadget.

The

[Save Text]

button used when displaying text will now call up a special requester which will allow you to select from a number of options including a VIEW option which will allow you to use your mailcap viewing program to display and manipulate the message.

The

[Attachment]

requester has been modified to include options for saving to the clipboard.

Messages marked for deletion were not being deleted if no other activity had been performed on the folder that contained the messages. This has been corrected.

Occasional problems were occurring when double clicking on a message caused a "Error: Select Folder Logic Error!!!" message to appear and AEMail exited. This has been corrected.

A period instead of a comma was being incorrectly placed after the day of the week in the Date: header. This has been corrected.

---

If you attempted to send a message to a group with the Expand not checked in the main Address Book display (registered users only), the message was not being sent to any of the group addresses and you would get an error message saying that the message could not be sent. This has been corrected.

The Quote Original Message box remained checked if you changed from a reply to either a forwarded or new message. This has been corrected so that Quote Original Message will be un-checked if you change from a reply to either a forwarded or new message.

The Add Signature Block box remained unchecked if you changed from editing a message to creating a new message. This has been corrected so that Add Signature Block will become checked when you switch to creating a new message.

(some of the above bug corrections were in the 1.22 release)

Version 1.22 Limited release on July 21, 1996.

A problem occurred with one particular ISP (bcsupernet.com) in which small, partial buffers were being sent from the ISP. AEMail could not recognize the response because it was not complete in the buffer that AEMail received. AEMail was corrected so that, if it received an incomplete buffer, it continued to ask for data until it received the ending line feed.

Version 1.21 Released July 6, 1997. Major corrections to this release are:

A major bug has been corrected in which lines greater than 78 characters could cause AEMail to hang or guru when exiting from the Compose window.

Depending on your screen dimensions, some of the gadgets on the Compose window could have overlaid others, especially at the bottom of the screen. This was partially caused by the use of large Screen fonts in the screen and window titles (set by the Fonts Preferences). AEMail now more intelligently calculates the placement of gadgets on the Compose screen. It also forces the use of the Topaz 8 font for screen and window titles.

The word wrap feature in the message display window was not taking full advantage of the width of the listview.

The EXPAND checkmark gadget in the address book

---

displays  
did not work properly with certain screen widths.

If you were display a message when you decided to Compose a reply, the message did not remain selected so that you could delete or transfer it without re-selecting it. The message now remains selected until you exit from the message display.

New cursor commands have been added to the control of the listviews. They include:

- Home or Cursor Left moves the listview to the top.
- End or Cursor Right moves the listview to the botton.
- PgUp or Shift Cursor Up pages the listview one page up. The top line of the previous page will be displayed as the bottom line of the new page.
- PgDn or Shift Cursor Down pages the list view one page down. The bottom line of the previous page will be displayed as the top line of the new page.

The cursor up/down keys on the keypad will have the same action as the normal cursor keys with the exception of the shift feature.

The slider bar on the message listview did not move the message as you moved the slider, but only when you release the left button. The listview now moves as you move the slider.

Some of the command tool bars have been modified - primarily as to color.

Two new  
command tool bar  
icons have been added  
corresponding to the menu items Copy Messages and Transfer Messages. These are placed after the delete icon and before the startnet icon. The copy icon looks like two sheets of paper and the transfer icon looks like a sheet of paper with arrows going out horizontally.

Mode requester in the  
General Parameters Configuration  
page now displays the current screen mode in the ⇐  
requester.

The problem with hacks or commodities that moved a window to the front when you clicked into it such as the Click-To-Front commodity (the folder window disappeared) has been corrected. Any other hack or commodity that automatically brings the current window to front either when you click on it or when you pass the cursor over it, should work now. Please let me know if you are still having problems.

in this release are:

For registered users you can use password protection to access AEMail. This is particularly useful for multiple user configurations.

The command tool bar as been re-designed and re-arranged. The icons are now in color and several new ones have been added including:

Display Previous Folder's Message List

Display Current Folder's Message List

Display Next Folder's Message List

Start TCP/IP Network Connection

Terminate TCP/IP Network Connection

The folder icon bar has been re-designed and made smaller. Since the vertical and horizontal size of each folder icon depends on the font used, the font and size for the folder bar can be user defined.

The Compose Message window has been completely revised. It now allows message text to be encoded with printed-quotable and BASE64 encoding. Also, when calling your editor, the compose window is re-activated when you save and quit from the editor. Only the body of the message appears in the editor window. This change makes the use of any editor that relenquishes control (such as CygnusEd (CED)) usable without any special considerations.

You can save messages from the Compose Message window in either the PENDING or QUEUED folders or you can immediately send them.

The Address Book when called from the Compose Message window will normally have only the Group header without the members of the group shown. For registered users, you will be able to expand the group names, however. Also, the Address Book, when called from the Compose window, will not have the data entry fields for adding addresses to the Address Book (although there is an option to call the complete Address Book).



For registered users, when you directly call the Address Book, you will be able to "shrink" the Groups to show only the Group header.

For registered users, different signature files are possible.

For registered users, additional user headers can be defined.

Attachments can use quoted-printable encoding.

When composing messages that are stored in the PENDING or QUEUED folders the system will remember previous attachments and additional headers that were added.

When editing messages, the message that is edited will be completely removed from the PENDING or QUEUED folder rather than marked deleted.

For all major list views, you can use the cursor keys to move the lists up or down.

For users of AmigaDOS 3.0 or above, drag select has been implemented for the Message list. You can select multiple messages by holding the left mouse button down and dragging it over several messages.

The messages counts that are shown in the folder icons will have deleted messages subtracted out.

Several new menu items have been added including the ability to "hide" deleted messages and to show only unread messages. You can also force a reply to a message to the "From:" address even if there is a "Reply-To:" address.

If you print a message, it will be marked as "un-read" the same as if you displayed it.

If you are reading a message when you receive additional messages, delete a message, or print a message, the display will remain on the message and not switch to the message list.

A &(to) parameter has been added to the Quote Header for quoted replies.

Corrected a problem where (fwd) was not recognized at the end of the subject line. AEMail will now recognize the (fwd) at either the beginning or end of the line. Compose now also places the (fwd) correctly at the end of the subject line.

Other minor corrections have been made.

---

Version 1.15 Released April 5, 1997. Major corrections to this release are:

The message display routines have been speeded up considerably. As a result of this, the restriction which prevented text attachments from being "shown" in the message window if they exceeded 5000 characters has been lifted. Further increases in message display speed will be implemented in future releases.

Foreign character sets requiring 8-bit display are now correctly shown and sent provided your provider can handle 8-bit encoding. Other encoding methods, such as "quoted-printable" on output, are not handled as yet. They will be handled in a future version.

When messages are marked for deletion, the on-disk configuration file is NOT updated. This greatly speeds up the deletion marking process. The downside of this is that, if the system crashes or your system is turned off before AEMail terminates, these messages will not be deleted or remain marked for deletion when AEMail is re-loaded.

Daylight Saving Time was only being calculated correctly for the United States. The United Kingdom and Europe use "Summer Time" which starts one week before DST in the United States (last Sunday in March rather than the first Sunday in April). This has been corrected.

By using a special AEMail tz environmental variable you can now specify time zone increments in half hours and with names longer than 3 characters (up to 9 characters for both Standard Time and Daylight Savings/Summer Time).

In versions prior to 1.15, whenever you sent your first email (and, as a result, sent the registration message), the ABOUT window would indicate you were "\*\* REGISTERED \*\*". This is no longer true. The "\*\* REGISTERED \*\*" designation will only occur when your shareware fee is acknowledged.

The Installation script has been modified so that it no longer copies the sys:rexxc directory to C:.. Instead, an assign statement has been added which adds the assignment of SYS:REXXC to C:..

Version 1.14 Released March 20, 1997. Minor correction release.

---

Fixed Installation script (Install\_AEMail). It would not properly install AEMail if AEMail had not been installed previously.

Insured that the Mail directory and the Mailcap directories ended with either ':' or '//'. If the definitions did not, an '/' was appended to the path definitions.

Corrected a problem where the Mailcap directory was being used instead of the Mail directory hor the .header file (this was not apparent in the Mail directory and the Mailcap directory were the same).

Corrected a problem where the .header file was being read before the configuration file. This again probably would not have been an apparent problem.

Corrected a problem with the "Remove DELETED Msgs" menu item in which selecting [CANCEL] would go ahead and delete the messages anyway. [CANCEL] will now exit without deleting any messages.

Corrected a problem when AEMail was called from the shell. The "config=" parameter was not working properly. It now works correctly.

Version 1.13 Released March 10, 1997. Bugs that were corrected are:

If a message file is missing, AEMail no longer terminates if you try to access that file.

A busy pointer has been added to a number of processes.

When AEMail terminates and you don't want to check for mail, AEMail no longer attempts to access your POP server. This can result in a requester, however, that states you are online, even when you are not.

Duplicate hot key menu calls have been eliminated.

Other minor corrections have been made.

For enhancements see  
Version 1.12 and 1.13 Enhancements

.

Version 1.12 Released February 15, 1997. This version was a special version without updated documentation or install script. It was not uploaded to AmiNet. It featured the following corrections:

There was a limitation (or bug) in the address book routine which limited the number of addresses you could store in a group to 255. This limitation has been lifted. You can now store up to 32,000 addresses in a group.

---

The buttons to call up file requesters have been changed from [DIR] to [REQ].

Other minor corrections have been made including the recognition of additional UUencoding formats.

For enhancements see  
Version 1.12 and 1.13 Enhancements

.

Version 1.11 Released October 14, 1996. This version corrects some minor bugs as follows:

Corrected the installation script which incorrectly identified the "Amitcp:bin" directory.

Corrected bug that did not allow files in the file requester for the "stopnet" script in the Configuration screen.

Implemented the 9 character NickName for the address book that was suppose to be implemented in Version 1.10.

Made minor revisions in the printout formats for message lists and the address book.

Corrected the display of dates in the mm/dd/yy format when the year was beyond 2000.

Version 1.10 Released September 29, 1996. The following bugs have been corrected (includes bugs corrected with Versions 1.04 a, b, and c.):

Corrected bug caused by multiple line SMTP responses. This would result in a "hang" when trying to send messages.

Prevents a GURU (8000005 - Divide-By-Zero error) from occuring when AEMail was unable to determine the size of a message that was being retrieved from the POP Server.

Corrected a bug in which not enough memory was being allocated for error message requester displays. This caused a GURU after the error message was displayed.

When a group address book entry had an actual UserID rather than a Nickname for one of it's addresses, the entire group was not sent.

A guru or freeze occurred when reading certain messages. These messages had an incomplete Content-Type: header.

Some requester windows had overlapping fields when a large Screen Text font was used.

If you tried to change your .signature file after you composed a message, you could not save your .signature

---

file (the .signature file was left open).

If you composed a message without an ending Carriage Return and you added attachments, the attachments were not correctly recognized. AEMail now forces a Carriage Return before attachments are added to the file.

Headers were not being printed when you printed a message.

Did not properly decode quoted-printable Content-Transfer-Encoding.

Times from 12 noon to 1 PM and from 12 midnight to 1 AM were incorrectly displayed. Changed from 0:xx PM to 12:xx PM and from 0:xx AM to 12:xx AM.

Changed install script so that it does not require AmiTCP: assign or TermiteTCP environmental variable at the Novice level. If the AmiTCP: assign is not present, AEMail will be installed in a AEMAIL directory on your largest disk partition. Also corrected some problems with install script.

Did not save default Save Attachment Path in AEMail.cnfg file.

For enhancements see  
Version 1.10 Enhancements  
.

Version 1.04c Limited release on September 11, 1996.

Corrected bug caused by multiple line SMTP responses.

Version 1.04b Limited release on September 4, 1996.

Corrected divide-by-zero error with progress indicator.

Version 1.04a Limited release on September 2, 1996.

Added the time zone capability and corrected a number of bugs.

Version 1.03 Released August 28, 1996

Corrects bug in which clicking on a folder after the folder strip was slid to the side selected the wrong folder. This occurred when more folders were present than could fit on the display. The correction of this bug was considered important enough to immediately release this version.

Corrected a bug when messages that were not read were transferred to another folder. The number of unread messages on the folder strip was incorrect. Also, if you delete a message that was unread, it will reduce the unread count for that folder (the total message count

still includes messages marked for deletion). If you undelete a message that was never read, the unread count will increase.

Version 1.02 Released August 25, 1996

Major bug found and corrected! When sending email there was a problem with parsing the email addresses of the recipients of the message which could cause the system to freeze or guru.

Made minor changes to accomodate TCP/IP stacks other than

AmitTCP  
, but which are compatable with AmitTCP. Tested with

TermiteTCP  
and  
Miami

.  
Added arguments when invoking AEMail from the shell. This was to allow AEMail to be used as a mailto agent with several Amiga web browsers. Tested with

Voyager  
and  
AWeb

.  
Consult  
USING AEMail AS A MailTo AGENT  
for how to  
implement this feature.

Set default editor to C:ed.

Made changes to install script to create an easier installation.

Corrected bug when Text Attachments had lines longer than 100 characters.

Changed Start Net and Stop Net menu items to provide for starting and stopping the network connection when your TCP/IP does not provide an automatic way to start or stop the Internet connection (signing onto your provider). See the

TCP/IP Parameters  
Section of the  
Configuration screen  
on how this function works.

(some of the above changes were in the 1.01 release)

Version 1.01 Released August 5, 1996

Limited release incorporating some changes for TermiteTCP.

---

- 
- Version 1.0 Released July 24, 1996. First BETA release.
- This is the first public version of AEMail released at the Sacramento Amiga Computer Club meeting. The release includes the complete AEMail package including an installation script and documentation in AmigaGuide (MultiView) format.
- Version 0.06 Released July 8, 1996
- Implemented expanded configuration windows.
- Added feature in which AEMail periodically checks for mail on your POP Server.
- Added the "Iconify AEMAIL" feature and the menu item that supports it.
- Version 0.05 Released June 18, 1996
- Added UUENCODED attachment support.
- Added "Change Password" capability to main "Configure" window.
- Added requirement that minimum configuration data be entered prior to starting AEMail.
- Added QUEUED message check at program startup and when StartNet script is executed.
- Added POP message and QUEUED message check at program termination.
- Version 0.04 Released June 2, 1996
- Added the "About" menu item.
- Added the delete folder menu item.
- Implemented the printing of messages with your preferences printer.
- Added "Progress" Windows to both the Send Message and Receive message processes.
- AEMail now automatically recognizes whether it is connected to your Internet provider on program startup.
- A Tool Type was added (AUTOCONNECT=YES) which automatically executes the StartNet script at program startup.
- Added check to automatically to see if any messages are currently available on your POP server at program startup
-

or when the StartNet script is executed.

- Version 0.03 Released on May 21, 1996
- Added the "Startnet" and "Stopnet" menu items under a new "AmiTCP" menu and added the Tool Types to specify the calls for the STARTNET and STOPNET scripts.
- Added the Configuration screen activated by the "Configuration" menu item under the PROJECT menu.
- Version 0.02 Released on April 20, 1996.
- Added MIME support for attachments.
- Version 0.01 Released on March 20, 1996. First ALPHA version.
- This initial version could handle sending and retrieving text messages only; no attachment capability was present. Certain features were not yet available and configuration was by Tool Types only.

## 1.119 VERSION 1.10 ENHANCEMENTS

### Version 1.10 Enhancements

Version 1.10 of AEMail incorporates a number of enhancements and revisions suggested by users. These include:

- o Added time zone support. This was both a "bug", in the sense that it was overlooked in the earlier version of AEMail, and an enhancement. Consult  
    Setting the Time Zone  
    for how to setup your  
local time zone.
- o A window is now displayed when  
    exiting AEMail  
    which informs you  
that AEMail is updating it's configuration files. If you had turned your computer off before this update was complete, you would have corrupted configuration files.
- o Eliminated the  
    Delete/Undelete  
    Verification Requester. This  
requester seemed unnecessary since you could always "undelete" a message you deleted by mistake.
- o The



- Copy
    - and
    - Transferoperations no longer require you to click on "Continue" to complete the operation. Instead, an informational window will be displayed with a "Cancel" button. Closing the window is automatic when you click on a folder. Clicking on "Cancel" will abort the operation.
  - o After a Copy or Transfer operation, the folder message list FROM which the messages were copied or transferred will be displayed.
  - o
    - Printinghas been enhanced to allow the user to print a list of messages in a folder and to print the contents of the Address Book.
  - o The
    - Address Book windowhas been modified to include a number of new features including:
    - The Nickname has been increased in size to 9 characters.
    - The Previous and Next command icons are activated to exit from the Address Book and display either the previous or next message in a message list. This facilitates adding addresses to the Address Book.
    - Double clicking on an address in the list view when the Address Book is called from the Compose window will immediately return to the Compose window transferring the Nickname of the appropriate Compose string gadget.
    - In the Address Book, when you click on a group's DISTRIBUTION LIST line, any existing address in the Address: string will not be destroyed. This facilitates adding addresses to the group.
  - o Allowed messages in
    - QUEUED folder to be edited
    - .
  - o Remembers the last directory used when adding multiple attachments
    - .
    - Also allows you to establish a default path for adding attachments.
  - o Sets an environmental variable called AEMail\_dir during the
    - install process
    - which contains the directory AEMail was installed in to facilitate future AEMail updates.
-

For more information on these revisions and/or enhancements click on the appropriate links above.

## 1.120 VERSION 1.12 ENHANCEMENTS

### Version 1.12 and 1.13 Enhancements

Versions 1.12 and 1.13 of AEMail incorporate a number of enhancements and revisions. These are listed below (The version number that applies is shown in parenthesis after the revision description).

- o Several menu items have been changed or added:
    - AEMail now allows for multiple configuration files.
      - . The Project/Configuration menu item now has five sub-items: Open, Edit, Save, Save As and Restore Default
      - The old Save Settings and Restore Settings menu items have been removed from the Project menu
      - . (1.13)
    - Under the Folders menu, an item called Remove DELETED Msgs has been added. This will IMMEDIATELY delete ALL ← messages marked for deletion in the current active folder. (1.12)
    - A new menu item has been added under the Messages menu group called Edit...
      - . (1.12)
    - The TCP Logging File process has been changed to provide additional menu control over the logging file. A new menu sub-group called TCP Logging File has been added under the TCP/IP menu group. This sub-group has three menu sub-items called Active, Purge, and Display/Edit.... (1.12)
-

- o The configuration screens have been totally revamped. Some new items have been added and others re-named or moved to other configuration 'pages'. The heading for the Required screen has been changed to Identity to more clearly indicate its purpose and the buttons to call the various configuration 'pages' have been moved to the top of the screen. When you select a configuration page, the button for that page will "light" up and stay "lit" while you are on that page. (1.12)

Other changes involving the configuration (including Tool Types) include:

A Save As button has been added to the Configuration screen. (1.13)

From (email) Address: (your email address), Reply To: and Organization items have been added to the Identity page.

New Tool Types have also been added to correspond to these items. (1.12)

The Edit Call: has been moved to the GENERAL parameter page. (1.12)

A new checkmarked item is added under the TCP Logging File: item in the PATHS page of the configuration screen called TCP Logging active on AEMail startup (1.12).

To accomodate multiple configurations, the Mail Directory has been removed from the Configuration screen. It is still available as a Tool Type, however. (1.13)

A CONFIG= Tool Type has been added to allow AEMail to start up with a specified configuration file. (1.13)

The Install script has been modified to provide for the added configuration items. (1.13)

- o When you reply to a message, the compose message routine will

first try to send the reply to any Reply-To: address that was in the message you are replying to. If the Reply-To header was not present, it will then send the reply to the From: header address. (1.12)

- o The same applies to transferring addresses to the address book. If you want to transfer the address from a message you are reading (by clicking on the address book icon), it will first try to transfer the address in the Reply-To: header. If that is not present, it will use the From: header address. YOU CAN FORCE it to use the From: header address by pressing the SHIFT key when you click on the Address Book. (1.12)
  - o The address book window has been modified to include a check mark item for group addresses to send only the group header in any message sent to a group rather than the email addresses of each member of the group. (1.12)
  - o When sending a message to a group, the messages will be sent in groups of 50. This is to allow for limitations in some SMTP servers that will not allow a message to be sent to more than a definitive number of recipients. Most SMTP servers should be able to handle 50 recipients at a time. (1.12)
  - o A busy pointer is now being displayed while a message is being read into the viewer. You can not scroll the message display while this busy indicator is being displayed. (1.12)
  - o Attachments that are text attachments are generally shown in the message window itself with SHOWN indicated for the attachment in the Attachment requester. The behaviour of AEMail has been changed for messages with attachments exceeding 5000 bytes. Now, with such messages, the text attachment will not be shown in the main message window, but you would be able to save or view it with the attachment requester. (1.12/1.13)
  - o text/\* and message/\* have been added to the mailcap file using MultiView (3.x users only). This allows you to view long text attachments that are not SHOWN (see above). (1.13)
  - o Miami Start Net and Stop Net scripts have been provided. (1.13)
  - o A special
-

CygnusEd script  
has been provided to properly use  
CygnusEd (CED) as your editor. (1.13)

## 1.121 IN CONCLUSION

### IN CONCLUSION

As payment for receiving and using this unregistered BETA version of AEMAIL,  
I would like any bugs, comments, or suggestions reported to me. You can  
send me email at

jzachar@calweb.com

or use the AEMAIL Nickname created in your  
Address Book.

You can also register AEMail for a shareware fee of \$30. (See the ←  
discussion

on

REGISTRATION

.

See the

Bug Reports and Suggestions  
section for the reporting procedure.

If you give this program to anyone else to use and evaluate, please include  
the complete archive as distributed. This includes the AEMail program, the  
installation script, and all documentation and readme files.

The complete archive is being posted on AmiNet and may be posted to any BBS.  
If it is posted to any particular BBS, I would appreciate it if the SYSOP  
of that BBS would send me an email message indicating the BBS it was posted  
to.

Future versions of AEMail are planned that will implement the following  
features:

- AREXX Support
- Filtering incoming messages to specified folders
- Asynchronous retrieval of messages from a POP server
- Asynchronous sending of messages to the SMTP server
- Even faster message display routines with several added features
  - including saving portions of the message to the clipboard
  - and transferring embedded email addresses to the address book.
- Built in message editor
- Other features suggested by users

I have a web site at:

<http://www.calweb.com/~jzachar>

---

The latest version of AEMail will be posted to this web site. Major releases will also be posted on AmiNet.

Whenever a new version of AEMail is available, I will email all users for which I have received notification messages (see

Registration  
) with notice

of the new version.

Thanks,

John Zacharias

jzachar@calweb.com

www: <http://www.calweb.com/~jzachar>

## 1.122 REFERENCES

### REFERENCES

A number of software packages are mentioned in this documentation. Details on how to obtain these packages are given below:

#### TCP/IP STACKS

**AmiTCP** A TCP/IP stack for use with the Amiga. AmiTCP is copyright (c) 1994, 1995 by Network Solutions Development, Inc.

AmiTCP was developed by Network Solutions Development, Inc., P.O. Box 32, FIN-02151 Espoo, Finland.

A demo 4.0 version is available on AmiNet sites in countries other than USA or Australia. It can also be found on many BBS's.

The commercial version is distributed by Village Tronic Marketing GmbH, Wellweg 95, D-31157 Sarstedt, Germany, and is available from many Amiga dealers and mail order houses.

World Wide Web home page for Network Solutions Development, Inc is:

<http://www.xgu.fi/biz/NSDI/>

email addresses: [info@nsdi.fi](mailto:info@nsdi.fi)  
[AmiTCP-Support@nsdi.fi](mailto:AmiTCP-Support@nsdi.fi)  
[AmiTCP-Group@nsdi.fi](mailto:AmiTCP-Group@nsdi.fi)

**Miami** A TCP/IP stack compatible with AmiTCP. This stack is also very simple to install and configure. Miami is copyright (c) 1996, 1997 by Holger Kruse. It is currently

shareware and is available at

<http://www.nordicglobal.com/miami.html>

on the WWW or it may be available on local BBS's. Some versions are available on AmiNet, but if you want the latest version consult the web page listed above.

email addresses: [kruse@nordicglobal.com](mailto:kruse@nordicglobal.com)  
[kruse@america.com](mailto:kruse@america.com)

If you are using Miami, the Down when Offline item in the TCP/IP Settings page for Miami should be checked and your settings saved. This will prevent Miami from waiting 80 seconds before returning a failure when you try to access the Internet when you are "Offline".

**TermiteTCP** A TCP/IP stack compatible with AmiTCP. This stack is very simple to install and configure. TermiteTCP is copyright (c) 1996 by Oregon Research, 16200 S.W. Pacific Hwy, Suite 162, Tigard, OR 97224.

This is a commercial product available at many Amiga dealers, mail order houses, or directly from Oregon Research.

World Wide Web home page for Oregon Research is:

<http://www.orres.com/~orres/>

email address: [support@orres.com](mailto:support@orres.com)

#### WWW BROWSERS

**IBrowse** Copyright (c) 1995, 1996 by Omnipresence Intl.

IBrowse is a commercial product distributed by Oregon Research in the United States and HiSoft in the United Kingdom and can be obtained from Amiga dealers or mail order houses. A demo version and upgrades can be obtained from the Omnipresence WWW site at:

<http://www.omnipresence.com/ibrowse>

and on AmiNet.

**Voyager** Copyright (c) 1995-96 by Oiver Wagner. Voyager 1.0 is available for download from AmiNet or the

<http://www.vapor.com/support>

WWW site. A commercial Version 2.0 is planned but is not available as yet.

email address: [owagner@lsd.wupper.de](mailto:owagner@lsd.wupper.de)

---

AWeb Copyright (c) 1996 by Yvon Rozijn. Published by Amitrix Development, 5312-47 Street, Beaumont Alberta, Canada T4X 1H9.

Both a public domain demo (AWEB) and a commercial (AWEB II) version are available. The public domain demo version can be found on AmiNet (AWeb v1.2b), many BBS's, or on the AmiTrix WWW site:

<http://www.networkx.com/amitrix/aweb.html>

The commercial version (AWEB II) can be obtained from Amiga dealers or mail order houses.

email addresses: [sales@amitrix.com](mailto:sales@amitrix.com)  
[support@amitrix.com](mailto:support@amitrix.com)

---