AppleScript

This section gives an overview of SoundApp's support for the AppleEvent Object Model and AppleScript. Not everything is documented here. For more information, see your documentation on AppleScript and the Scripting Dictionary of SoundApp using your favorite script editor.

Script Menu

SoundApp supports a script menu which allows scripts to be executed directly from a menu in SoundApp. In order to utilize this feature, create a folder called "Script Menu Items" in the same directory as the SoundApp application. Then place compiled scripts into the folder and launch SoundApp. A new "Script" menu will be added to the menu bar, listing the scripts in the folder. Simply select one to run it. Scripts can direct SoundApp or other applications to do just about anything.

Application

In addition to the Core Suite of open, run, and quit (print is not supported), SoundApp supports the following verbs:

\(\preceq \) convert alias, alias list, string, string list [to alias, alias list, string, string list] [encoding PCM, uLaw, IMA] [channels default, mono, stereo] [bits default, eight, sixteen] [rate rate] [law full, reduced, smart] [with(out) DOSify] [with(out) suffix] [as System7, suitcase, AIFF, Wave, AU, NeXT, SD, QuickTime] [start at time] [stop at time]: Converts the specified file(s) to the destination file(s). If multiple source files are specified and a single destination, the destination is assumed to be a folder. If no to parameter is specified, the default conversion output method is used (as specified in the Convert pane of the Preferences dialog). The encoding, channels and bits parameters allow the encoding, channel and bit resolution setting to be overridden. The rate parameter allows the output sampling rate setting to be changed. If these are omitted, the value specified in the Convert pane of the Preferences dialog will be used. The law parameter controls whether μ -law and a-law files are converted as 16-bit (full), 8-bit (reduced) or 8-bit with smart processing (smart). The DOSify parameter causes new output file names to be created with the archaic MS-DOS 8.3 file name format. The suffix parameter causes the new output file to be created with a three letter dot-suffix, e.g. ".wav". These last two are ignored if a single file is converted and the to parameter is specified. The as parameter allows the output sound format to be specified. Again, if it's not specified, the default in the Convert pane of the Preferences dialog will be used instead. The start at and stop at parameters allow conversion of a specified range of the original sound file as specified in seconds. A single one may be specified, if desired.

◊ play alias, alias list, string, string list [bits default, eight, sixteen] [law full, reduced, smart] [buffer size] [MODDriver trecker, preferTrecker, preferZSS, ZSS] [MODStereo mono, stereo, enhanced] [with(out) MODFilter] [with(out) MODSixteen] [with(out) MODTempMem] [MODVolume volume] [modRate rate] [MIDIDriver QuickTime, OMS] [with(out) sendGMReset] [with(out) ignoreSysEx] [with(out) useMIDIVolume] [start at time] [stop at time]: Plays the file or files passed as the direct parameter. The bits and law parameters function as above. The buffer parameter specifies the size in kilobytes of the buffer used for double-buffering. A value of zero means don't double-buffer; otherwise, the value must be at least 64. The MODDriver, MODtereo, MODixteen, MODItempMem, MODRate and modVolume parameters control the "MOD Driver," "Stereo Mode," "Real-Time Filter," "16-Bit," "Use System Memory," "Playback Rate" and "Volume" settings in the MOD pane of the Preferences dialog respectively. The MIDIDriver, sendGMReset, ignoreSysEx and useMIDIVolume parameters control the "MIDI Driver," "Send General MIDI Reset," "Ignore

SysEx Messages," and "Use Playback Volume" settings in the MIDI pane of the Preferences dialog respectively. The volume value must be at least zero and no more than 255. The rate value must be at least 8000 and no more than 48000. The start at and stop at parameters allow playback of a specified range of the original sound file as specified in seconds.

- ♦ send oms data string: Sends raw MIDI data to an OMS synthesizer. The data is consists of a string of hexadecimal octets. MIDI timing is not supported. Also, remember to include the length fields for system exclusive messages. For example, to send a "GM Reset" command, use the command: send oms data "f0 05 7e 7f 09 01 f7". Note the "05" which is the length of the system exclusive message.
- \Diamond display information alias, alias list, string, string list: Opens an information window for each of the specified files.
- \Diamond fetch information alias, alias list, string, string list: Returns a record or list of records containing information about the specified sound file or files.
- ♦ get status: Returns one of idle, busy, paused indicating what SoundApp is currently doing.
- ♦ set status to paused, next, previous, stopped: Changes the current activity status of SoundApp. "Paused" pauses or resumes playback, "next" and "previous" jump to the next or previous file and "stopped" stops processing immediately.
- ♦ get preferences: Returns a record containing a list of all the global preferences.
- \Diamond set preferences to preference: value ...: Changes one or all of the global preferences based on a specified record. Single preferences can be operated on directly if desired, e.g. set autoOuit to true.
- ♦ get conversion setting specifier: Retrieves the indexed or named conversion setting. The object conversion settings can be used to retrieve a list of all of them.
- \Diamond get setting of conversion setting: Retrieves an attribute from the specified conversion setting.
- \Diamond set setting of conversion setting to specifier: Sets an attribute of the specified conversion setting to the specified value.
- ♦ set convert settings save flag to true, false: Sets an internal flag which controls whether to save the conversion settings whenever they are changed via an AppleEvent. This can speed processing, but the settings will be lost when SoundApp exits. This flag has no effect on changing the conversion settings via the user interface. It only affects scripting.
- \Diamond get convert settings save flag: Returns the value of the internal flag which can be set with the above command.
- ♦ get playback volume: Returns the current playback volume SoundApp uses relative to the system volume. The number is in the range 1 to 384. A value of 256 is 100%.

- ♦ set playback volume to value: Sets the current playback volume SoundApp uses relative to the system volume. The value is the same as above.
- ♦ get current file: Returns a record containing the name, type and file specification for the file currently being processed.
- ♦ show about, help window: Opens the About window and displays either the About or Help pane, respectively. You can use "set/get pane" to manipulate the current pane in the window.
- ♦ yield: Yields time to SoundApp to process files. This can be used in an AppleScript loop which waits for status to go to idle to determine when SoundApp is done.

Play Lists

Play lists are references as a document in SoundApp. The following verbs can be used on them:

- \Diamond insert into document files file at position: Inserts the specified file at the specified position (an integer) in the Play List window document.
- \Diamond play from entries selected, list of entries: Plays either the currently selected entries or the list of entries specified.
- ♦ convert from entries selected, list of entries: Converts either the currently selected entries or the list of entries specified.
- \Diamond get information from entries selected, list of entries: Gets information for either the currently selected entries or the list of entries specified.
- ♦ delete entry: Removes the specified entry from the list.
- ♦ move entry to location: Moves the specified entry to another location in the list.
- \Diamond duplicate entry to location: Creates a copy of the specified entry at another location in the list.
- ♦ set shuffle, repeatProcessing to true, false: Changes the value of the Shuffle and Repeat checkboxes.
- ♦ get shuffle, repeatProcessing: Retrieves the value of the Shuffle and Repeat checkboxes.
- ♦ get sort mode: Retrieves the sorting mode. Valid values are none, by name and by type.
- ♦ set sort mode to none, by name, by type: Retrieves or changes the sorting mode.
- ♦ get selection: Retrieves the current selection.
- ♦ set selection to entry, list of entries: Changes the selection to the specified entry or entries.

Objects

The following objects are supported:

- ♦ application: The SoundApp application.
- \Diamond document: A Play List document. Documents can only be referenced by name.
- \Diamond entry: An entry in a Play List.
- \Diamond conversion setting: A list containing all the output setting parameters.
- \Diamond preferences record: A record consisting of all the SoundApp global preferences. Settings in the Convert menu are not included here.