

AmiSlate

Jeremy Friesner

COLLABORATORS

	<i>TITLE :</i> AmiSlate		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY	Jeremy Friesner	January 18, 2023	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	AmiSlate	1
1.1	AmiSlate ARexx Commands	1
1.2	conventions	2
1.3	Mode Index Numbers	3
1.4	commentary	4
1.5	problems	5
1.6	displaybeep	6
1.7	breakarexxscripts	6
1.8	circle	7
1.9	clear	7
1.10	connect	8
1.11	disconnect	8
1.12	easyrequest	8
1.13	filerequest	9
1.14	flood	10
1.15	getpixel	10
1.16	getremotestateattrs	11
1.17	getstateattrs	11
1.18	getversion	12
1.19	getwindowattrs	13
1.20	line	13
1.21	loadiff	14
1.22	lock	14
1.23	lockpalette	15
1.24	pen	15
1.25	penreset	16
1.26	playscript	16
1.27	point	17
1.28	putrasterpixels	17
1.29	quit	18

1.30	recordscript	18
1.31	remoterexxcommand	19
1.32	remotestringrequest	20
1.33	saveiff	20
1.34	sendmessage	21
1.35	setbcolor	21
1.36	setbpen	22
1.37	setfcolor	22
1.38	setfpen	23
1.39	setraster	23
1.40	setremotewindowtitle	24
1.41	settoolbehavior	24
1.42	setuserbcolor	25
1.43	setuserbpen	25
1.44	setuserfcolor	26
1.45	setuserfpen	26
1.46	setusertool	27
1.47	setwindowtitle	27
1.48	stringrequest	27
1.49	typekeys	28
1.50	square	28
1.51	waitevent	29

Chapter 1

AmiSlate

1.1 AmiSlate ARexx Commands

AmiSlateRexx V1.2 by Jeremy Friesner

This document describes the ARexx commands that are supported by AmiSlate and how to use them. Although I have tried to be as clear and accurate as possible, it's likely that some descriptions will contain errors or ambiguities. With that in mind, it's a good idea to look at the example ARexx scripts included with the AmiSlate distribution as well as this document.

Commands prefixed with a "*" are currently not implemented or have no useful effect. They will be completed in a later release.

Conventions - Things assumed in this document

Commentary - General info on AmiSlate ARexx operation

Common Problems - Common problems and their solutions

BreakARexxScripts - Make AmiSlate try to break all ARexx scripts

Circle - Draw a circle or ellipse

Clear - Clear the Drawing area

Connect - Connect to remote AmiSlate client

Disconnect - Disconnect from remote AmiSlate client

DisplayBeep - DisplayBeep the local or remote screen

EasyRequest - Present user with an EasyRequester

FileRequest - Present user with a FileRequester

Flood - Flood fill an area

GetPixel - Return palette number of pixel

GetRemoteStateAttrs - Get data on remote client's status

GetStateAttrs - Get data on local client's status

GetVersion - Get AmiSlate version information

GetWindowAttrs - Get data on AmiSlate's window size, etc.

Line - Draw a line

LoadIFF - Load an IFF ILBM file onto the canvas

Lock - Keep user from drawing

LockPalette - Lock Palettes

Pen - Draw next line in a chain of lines

PenReset - Start a new line

PlayScript - Playback an AmiSlate script

Point - Plot a point

PutRasterPixels - Send a stream of pixels to raster window

Quit - Cause AmiSlate to quit

RecordScript - Cause AmiSlate to begin recording to a file

RemoteRexxCommand - Start Rexx script on remote client

RemoteStringRequest - Present remote user with StringRequester

SaveIFF - Save the current screen to an IFF ILBM file

SendMessage - Send message to remote client's ARexx program

- * **SetBColor** - Set Background pen by RGB value
- * **SetBPen** - Set Background pen by palette #

SetFColor - Set Foreground pen by RGB value

SetFPen - Set Foreground pen by palette #

SetRaster - Set Raster window parameters

SetRemoteWindowTitle - Set remote client's window title

- * **SetToolBehavior** - Set a Tool's behavior
- * **SetUserBColor** - Set the user's background pen by RGB value
- * **SetUserBPen** - Set the user's background pen by palette #

SetUserFColor - Set the user's foreground pen by RGB value

SetUserFPen - Set the user's foreground pen by palette #

SetUserTool - Set the user's selected tool

SetWindowTitle - Set the Window Title

StringRequest - Present user with StringRequester

TypeKeys - Enter keystrokes into Chat Line

Square - Draw a square or rectangle

WaitEvent - Wait for an event

1.2 conventions

In this document, the following rules and conventions hold true for all commands:

1) All commands that accept arguments use the ARexxBox convention of

"var" and "stem" variables. That is, you can have your results returned as a single string into one variable via the "var" keyword, or you can have your results returned into a stem array via the "stem" keyword.

For example:

```
remotestringrequest stem answ. ARexx_Test Def_String Gad_Text
```

will set the stem array variable `answ.message` to (whatever the user typed into the requester).

By contrast, the command:

```
remotestringrequest var answ ARexx_Test Def_String Gad_Text
```

will set the variable `answ` to the string the user typed in.

2) Argument meaning is implicit in the ordering of the arguments, and thus keywords should not be explicitly stated in the command (the exception being "var" and "stem", above). Arguments will be designated with `<anglebrackets>`. Switches are stated explicitly, of course, and will be designated with `[brackets]`.

3) When an ARexx script is run by an AmiSlate client, it is provided with two command line arguments: the first being the name of the AmiSlate client's ARexx port, and the second being either "LOCAL" or "REMOTE" depending on whether the execution was initiated by the local or the remote user.

4) Commands that are not yet implemented will have * in front of them.

1.3 Mode Index Numbers

When communicating information about which tool (a.k.a mode) the local or remote client is in, AmiSlate makes use of the following constants.

It is a good idea to copy the following declarations into the beginning of your ARexx program in order to later easy refer to different modes.

```
/* Mode Constants for use with AmiSlate's ARexx interface */
```

```
AMode.DOT = 0
```

```
AMode.PEN = 1
```

```
AMode.LINE = 2
```

```
AMode.CIRCLE = 3
```

```
AMode.SQUARE = 4
```

```
AMode.POLY = 5
```

```
AMode.FLOOD = 6
```

```
AMode.DTEXT = 7
```

```
AMode.FILLCIRCLE = 13
```

```
AMode.FILLSQUARE = 14
```

When replying to the WaitEvent function, AmiSlate uses a set of message codes to indicate which type of event occurred. Note that despite the binarily-disjoint nature of the following constants, only one type of event currently is replied per WaitEvent call.

```
/* Message reply codes for use with AmiSlate's ARexx interface */  
AMessage.TIMEOUT = 1 /* No events occurred in specified time period */  
AMessage.MESSAGE = 2 /* Message recieved from remote Amiga */  
AMessage.MOUSEDOWN = 4 /* Left mouse button press in drawing area */  
AMessage.MOUSEUP = 8 /* Left mouse button release in drawing area */  
AMessage.RESIZE = 16 /* Window was resized--time to redraw screen? */  
AMessage.QUIT = 32 /* AmiSlate is shutting down */  
AMessage.CONNECT = 64 /* Connection established */  
AMessage.DISCONNECT = 128 /* Connection broken */  
AMessage.TOOLSELECT = 256 /* Tool Selected */  
AMessage.COLORSELECT = 512 /* Palette Color selected */  
AMessage.KEYPRESS = 1024 /* Key pressed */
```

Furthermore, when MESSAGE events are replied, the following subtypes (returned in the code1 result variable) reflect the origin of the received method:

```
AMessageOrg.STRINGUSER = 1 /* String was sent by remote ARexx script */  
AMessageOrg.STRINGEASYREQ = 2 /* String was sent by remote EasyRequester */  
AMessageOrg.STRINGSTRINGREQ = 3 /* String was sent by remote StringRequester */
```

1.4 commentary

AmiSlate's ARexx port is designed to be able to run in parallel with the local and remote user's input. Thus, the ARexx port has its own internal state (current foreground color, etc.) and most ARexx commands will not interfere with or change the state of the user's settings. (Notable exceptions to this are the SetUser(*) commands) If you do not want the user to be drawing while the ARexx script is running, execute a 'lock on' command.

AmiSlate is based on the idea of keeping the local and remote user's drawing area as identical as possible. Thus there are no commands available that draw without sending the drawing info to the remote user. EasyRequests, StringRequests, and WindowTitles can be sent either locally or remotely only, however.

1.5 problems

Common Problems and their solutions:

1) I can't get results from any of the commands I send to AmiSlate!

- Make sure you set "options results" at the beginning of your script.

2) ARexx scripts don't work properly if I execute them from the second (or later) concurrent instance of AmiSlate that is running on my system.

- Probably this is because your script isn't parsing the Port Name correctly from the command line arguments AmiSlate starts it with.

Make sure the following lines are at the beginning of your script:

```
parse arg CommandPort ActiveString
address (CommandPort)
```

3) I need to see the output of my REXX script in order to debug it!

- Use the REXXOUTPUT=<outputfile> startup option.

4) My request for information from the remote user terminated immediately, before the remote user even responded to the requester!

- Commands that ask the remote user for information, including RemoteRexxCommand, RemoteStringRequest, and RemoteEasyRequest, all return immediately. In order to find out the user's response, you need to follow the Remote command with a "WaitEvent MESSAGE".

When the remote user responds to the requester, his/her response will be returned as a message string.

5) Anytime I try to put string literals with spaces in them into my arguments to AmiSlate, I get a warning/error message, and my command doesn't work.

- This is apparently due to ARexx being lame about argument passing-- when AmiSlate receives the messages, the quote marks have been stripped and AmiSlate thinks each word is a separate argument.

If anyone knows a way to get around this, please tell me! For now, here is the workaround:

You have to specify a set of quotation marks separately and concatenate them in explicitly. So, instead of:

```
SetWindowTitle "Hi There, Welcome to AmiSlate!"
```

you should use:

```
SetWindowTitle ''' || "Hi There, Welcome to AmiSlate!" || '''
```

1.6 displaybeep

DISPLAYBEEP

Arguments

[LOCAL] [REMOTE]

Effect/Description

Causes a DisplayBeep() on the local or remote screen, or both.

Return Values

rc is always 1.

Example

Beep LOCAL REMOTE

1.7 breakarexxscripts

BREAKAREXXSCRIPTS

Arguments

None.

Effect/Description

Causes AmiSlate to try to remove all ARexx scripts, by sending a QUIT command to any waiting script and closing its port.

Warning: Unless you are very careful, the script YOU are running will be one of the scripts that are "broken"!

What AmiSlate does to break the ARexx scripts is this:

If any script is waiting on a WaitEvent command, it will be replied with a QUIT message (yes, even if it didn't specify QUIT as something to wait on!). Then AmiSlate will close its ARexx port for about three quarters of a second. Any script that tries to send AmiSlate a command during that time will execute with "host environment not found" or somesuch.

If you want to keep your script running after executing this command, have your script do nothing for about two seconds after executing the BreakARexxScripts.

Return Values

rc is always 1.

1.8 circle

CIRCLE

Arguments

<x> <y> <rx> <ry> [FILL] [XOR]

Effect/Description

Draws a circle with center (x,y) and radii (rx, ry) in the current foreground color. If the FILL switch is specified, the circle will be filled. If XOR is specified, it will draw the circle in XOR mode instead of using the current foreground color.

Return Values

On success, rc = 1. Otherwise, rc = 0.

Example

Circle 50 60 20 25 FILL

1.9 clear

CLEAR

Arguments

none

Effect/Description

Clear the drawing window and Chat Lines.

Return Values

rc is set to 1.

Example

Clear

1.10 connect

CONNECT

Arguments

<hostname>

Effect/Description

Attempts to connect to the given host computer. Fails if there is already a connection running, or if the connect attempt failed.

Return Values

rc is 1 on success, 0 on failure.

Example

Connect jfriesne.extern.ucsd.edu

1.11 disconnect

DISCONNECT

Arguments

none

Effect/Description

Disconnects from a remote client. Fails if no connection is active or AmiTCP is not running.

Return Values

rc is 1 on success, 0 on failure.

Example

Disconnect

1.12 easyrequest

EASYREQUEST

Arguments

<title> <message> <gadgets>

Effect/Description

Presents the local user with an EasyRequester from which he/she may make a choice.

<gadgets> should be a string of the form "name1|name2|...|nameN" where each |-separated substring is the name of one gadget the user can select.

Return Values

rc is set to the option selected by the user, in EasyRequester style--i.e. The rightmost button in the list returns 0 when selected, and the rest are numbered 1..(N-1), where N is the total number of gadgets.

Example

EasyRequest "A_Nice_Title" "Do_you_like_llamas?" "Yes|No|Maybe"

if (rc == 0) then say "You picked Maybe"

if (rc == 1) then say "You picked Yes"

if (rc == 2) then say "You picked No"

1.13 filerequest

FILEREQUEST

Arguments

<title> <dir> <file> [SAVE]

Effect/Description

Brings up an ASL FileRequester from which the user may choose a file.

The default directory and file of the requester may be specified, and if the SAVE switch is specified, the ASL Requester will operate slightly differently, disallowing file selection by double-clicking on the file.

Return Values

<file> - the dir/file path chosen by the user.

Example

FileRequest stem filer. Select_a_File "ram:" DefaultFile.txt

say "You picked: " filer.file

1.14 flood

FLOOD

Arguments

<x> <y> [UNSAFE]

Effect/Description

Affects a flood fill in the current foreground color at the given location.

Specifying UNSAFE will cause the flood fill to be made in Not-So-Safe mode.

(see AmiSlate.guide for more info on this)

Return Values

rc is 1 if flood succeeded, 0 on failure.

Example

Flood 25 50

1.15 getpixel

GETPIXEL

Arguments

<x> <y>

Effect/Description

returns the palette number and red, green, and blue values of the pixel
at the given co-ordinates.

Return Values

rc is the pen number of the pixel at the given co-ordinate

Example

GetPixel 50 30

say "The pixel at 50 30 is of color " rc

1.16 getremotestateattrs

GETREMOTESTATEATTRS

Arguments

none

Effect/Description

Returns data about the state of the remote peer on a connection.

If there is no active connection, then all values will be set

to -1.

Return Values

mode - The **mode index number** of the remote amiga's current mode.

fpen - The remote amiga's current foreground pen's palette position

bpen - The remote amiga's current background pen's palette position

fred - The remote amiga's current foreground pen's red value (0..7)

fgreen - The remote amiga's current foreground pen's green value (0..7)

fblue - The remote amiga's current foreground pen's blue value (0..7)

bred - The remote amiga's current background pen's red value (0..7)

bgreen - The remote amiga's current background pen's green value (0..7)

bblue - The remote amiga's current background pen's blue value (0..7)

Example

GetRemoteStatAttrs stem rsa.

say "Remote mode = " rsa.mode

say "Remote fpen = " rsa.fpen

...

1.17 getstateattrs

GETSTATEATTRS

Arguments

none

Effect/Description

Gets data about the local client's current state.

Return Values

mode - The **mode index number** of the local amiga's current mode.

fpen - The local amiga's current foreground pen's palette position

bpen - The local amiga's current background pen's palette position

fred - The local amiga's current foreground pen's red value (0..7)

fgreen - The local amiga's current foreground pen's green value (0..7)

fblue - The local amiga's current foreground pen's blue value (0..7)

bred - The local amiga's current background pen's red value (0..7)

bgreen - The local amiga's current background pen's green value (0..7)

bblue - The local amiga's current background pen's blue value (0..7)

pendown - 1 if user is currently drawing, else 0

locked - 1 if user is currently locked out of drawing on the screen, else 0.

Example

```
GetStateAttrs stem sta.
say "Local mode = " sta.mode
say "Local fpen = " sta.fpen
...
```

1.18 getversion

GETVERSION

Arguments

none

Effect/Description

Returns a string containing AmiSlate's current version number.

Return Values

version - a version string.

Example

```
GetVersion var ThisVersion
say "Current AmiSlate version is: " ThisVersion
```


1.19 getwindowattrs

GETWINDOWATTRS

Arguments

none

Effect/Description

Returns data about the current state of the AmiSlate window.

Note that maxwidth and maxheight are not always the same as the screen width and screen height. They may be less if the remote client is using a smaller screen than the local client.

Return Values

top - distance of window from top of screen, in pixels

left - distance of window from left of screen, in pixels

width - width of window, in pixels

height - height of window, in pixels

depth - Screen depth/Number of bitplanes used by screen window is on

maxwidth - Maximum possible width of window, in pixels

maxheight - Maximum possible height of window, in pixels

Example

GetWindowAttrs stem wat.

say "Window top = " wat.top

say "Window left = " wat.left

...

1.20 line

LINE

Arguments

<x1> <y1> <x2> <y2> [XOR]

Effect/Description

Draws a line from (x1, y1) to (x2, y2) in the current foreground color.

If the XOR switch is specified, draws the line in XOR mode instead.

Return Values

rc is 1 if the line draw was wholly successful, else 0.

A line draw is wholly successful if both endpoints were in the window.

Example

Line 5 5 25 35

1.21 loadiff

LOADIFF

Arguments

<file> [EXPAND] [LOADPALETTE] [PROTECTGUI]

Effect/Description

Causes AmiSlate to attempt to load the specified file in as an IFF ILBM picture file. If successful, the file will be displayed on screen, and transmitted to the remote client.

If the EXPAND switch is specified, AmiSlate will attempt to resize its window larger to fit the ILBM, if need be.

If LOADPALETTE is specified, AmiSlate will load in the new color map of the IFF.

If PROTECTGUI is specified, AmiSlate will make sure not to alter pens 0 through 3, thus keeping the screen looking mostly sane.

Return Values

rc is 1 on success, 0 on failure.

Example

LoadIFF "work:graphics/lo-res/alien.IFF" EXPAND LOADPALETTE PROTECTGUI

1.22 lock

LOCK

Arguments

[ON] [OFF]

Effect/Description

A Lock ON command will disallow the user from drawing on the drawing area. A Lock OFF command will re-allow the user to draw.

Return Values

rc is always 1.

Example

Lock ON

1.23 lockpalette

LOCKPALETTE

Arguments

[ON] [OFF]

Effect/Description

Lock ON causes AmiSlate to Lock Palettes with the remote client. This means that it will copy the remote client's palette to the local client's palette, and thereafter any palette changes made on one client will be echoed to the other.

Lock OFF releases the two palettes so that they may be modified separately.

A Lock will only succeed if there is a TCP connection active.

Return Values

rc is 1 on success, 0 on failure.

Example

LockPalette ON

1.24 pen

PEN

Arguments

<x> <y> [XOR]

Effect/Description

If this is the first Pen command issued since a PenReset command, Pen

will set the beginning co-ordinates of a line. Otherwise, Pen will draw a line from the beginning co-ordinates given previously and then draw a line to the co-ordinates (x,y). After the draw, (x,y) becomes the beginning co-ordinates for the next line draw.

If XOR is specified, it will draw the line segment in XOR mode instead of the current foreground color.

Return Values

rc is 1 if the specified co-ordinates were within the drawing area, else 0.

Example

Pen 15 25

1.25 penreset

PENRESET

Arguments

none

Effect/Description

Causes the Pen tool to reset to its initial state. After executing a PenReset, the next Pen command will be the start of a new line, rather than the continuation of an existing line.

Return Values

rc is always 1.

Example

PenReset

1.26 playscript

PLAYSCRIPT

Arguments

<file>

Effect/Description

Plays the specified AmiSlate script file back to the user.

Return Values

rc is 1 on success, 0 on failure.

Example

PlayScript "dh0:AmiSlate/Scripts/FunnyFace.script"

1.27 point

POINT

Arguments

<x> <y> [XOR]

Effect/Description

Plots a single pixel at the the co-ordinate (x,y) in the current foreground color. If XOR is specified, it will draw the pixel in XOR mode instead.

Return Values

rc is 1 if the point was within the drawing area, else 0.

Example

Point 20 30

1.28 putrasterpixels

PUTRASTERPIXELS

Arguments

<length> <red> <green> <blue>

<length> PEN <pennumber>

Effect/Description

Paints <length> pixels into the Raster drawing area specified by a previous call to SetRaster. The pixels will be drawn in the closest color matching the given R, G, B, values, or if the

PEN keyword is specified, they will be drawn with the given pen.

Return Values

If no Raster drawing area has been set, rc is 0. Otherwise 1.

Example

PutRasterPixels 15 12 3 0

PutRasterPixels 15 PEN 3

1.29 quit

QUIT

Arguments

[FORCE]

Effect/Description

Causes AmiSlate to quit. Specifying the FORCE switch causes the user not to be asked for confirmation first. (Currently this has no effect, as the user is not asked for confirmation anyway)

Note that sending any commands to AmiSlate after this command will cause your ARexx script to error out.

Return Values

rc is always 1.

Example

Quit

1.30 recordscript

RECORDSCRIPT

Arguments

<file> [FORCE] [START] [STOP]

Effect/Description

Causes AmiSlate to begin or end recording to the given file. The

START and STOP keywords control whether recording is to begin or end, and RecordScript will fail if it is asked to START when a script is already being recorded or asked to STOP when no script is being recorded. The FORCE keyword currently has no effect.

Return Values

rc is 1 on success, 0 on failure.

Example

RecordScript "ram:TempScript.script" START

1.31 remoterexxcommand

REMOTEREXXCOMMAND

Arguments

<file>

Effect/Description

This command will attempt to execute an ARexx script on the remote client's Amiga, first getting permission from the user thereof with an EasyRequest. When the user responds to the requester asking him whether or not he wants to run the given script, the remote AmiSlate client will send back a one character message giving a result code. Use "WaitMessage MESSAGE" directly after executing a RemoteRexxCommand to catch the response.

Possible response values are:

- 0) Remote user refused to run the script, or another failure occurred.
- 1) Remote user allowed the script to be run.
- 2) Remote user chose another script to run instead.

Return Values

1 on success, 0 on failure.

Example

RemoteRexxCommand "SlateRexx:Chess.Rexx"

WaitEvent MESSAGE stem waitev.

if (waitev.message > 0) then say "Remote script running"

1.32 remotestringrequest

REMOTESTRINGREQUEST

Arguments

<title> <defaultstring> <message>

Effect/Description

This command presents a StringRequester to the remote user. This command does NOT wait for an answer, however. Use WaitEvent immediately after this command to be sure to catch the MESSAGE event that will come back when the remote user responds.

RemoteStringRequest will fail if a connection is not active.

Return Values

rc is 1 on success, 0 on failure.

Example

RemoteStringRequest RemoteStringTitle Jeremy WhatIsYourName

WaitEvent MESSAGE stem wat.

say "Reply was: " wat.message

1.33 saveiff

SAVEIFF

Arguments

<file>

Effect/Description

Saves the current canvas as an IFF ILBM file to <filename>.

Return Values

rc is 1 on success, 0 on failure.

Example

SaveIFF "work:graphics/newfile.IFF"

1.34 sendmessage

SENDMESSAGE

Arguments

<message>

Effect/Description

Sends the given string to the remote client, where if an ARexx script is waiting for it with a WaitEvent MESSAGE, it will be received by the remote script.

SendMessage will fail if a connection is not active.

Return Values

rc is 1 on success, 0 on failure.

Example

SendMessage HiRemoteClient

1.35 setbcolor

SETBCOLOR

Arguments

<red> <green> <blue> [NOTBACKGROUND]

Effect/Description

Will set the background color to the closest matching palette position to the given (R,G,B) triplet. The NOTBACKGROUND flag, if specified, will ensure that the new color is not the previous background color.

This command currently has no useful effect.

Return Values

rc is always 1.

rc2 is the pen number of the color chosen.

Example

SetBColor 15 1 1 /* A bright red */

1.36 setbpen

SETBPEN

Arguments

<pen>

Effect/Description

Sets the current background color to the given palette position.

This command currently has no useful effect.

Return Values

rc is 1 unless <pen> is an invalid palette position.

Example

SetBPen 1

1.37 setfcolor

SETFCOLOR

Arguments

<red> <green> <blue> [NOTBACKGROUND]

Effect/Description

Will set the foreground color to the closest matching palette position to the given (R,G,B) triplet. The NOTBACKGROUND flag, if specified, will ensure that the new color is not the background color.

Return Values

rc is always 1.

rc2 is the palette position of the number chosen.

Example

SetFColor 0 9 0 /* Medium green */

1.38 setfpn

SETFPEN

Arguments

<pen>

Effect/Description

Sets the current foreground color to the given palette position.

Return Values

rc is 1 as long as <pen> is a valid palette position.

Example

SetFPen 4

1.39 setraster

SETRASTER

Arguments

<top> <left> <width> <height> <pixeloffset>

Effect/Description

Defines a drawing area for raster pixels. After executing this call, the raster drawing area can be filled from top to bottom, left to right, with pixels of various colors, by using the PutRasterPixels command. pixeloffset is the number of pixels into the raster window that you wish to start drawing pixels at. This number can range from zero to ((width * height)-1), with zero being the top left, and the latter expression being the lower right of the window.

Return Values

If the raster is entirely on the drawing canvas, rc is 1.

Otherwise it will be zero (although the raster will still work--it will be clipped at the edges of the drawing area)

Example

SetRaster 10 10 50 55 0

1.40 setremotewindowtitle

SETREMOTEWINDOWTITLE

Arguments

<message>

Effect/Description

Sets the remote client's WindowTitle to "R:<message>". The R: lets the remote user know that the message came from a remote location. This command will fail if there is no active connection.

Return Values

rc is 1 on success, 0 on failure.

Example

SetRemoteWindowTitle HelloFromTheOtherGuy

1.41 settoolbehavior

SETTOOLBEHAVIOR

Arguments

<not specified>

Effect/Description

This command is not yet implemented. It will eventually be used to control the behavior and possibly the appearance of the various buttons in the ToolBar.

Return Values

<not specified>

Example

<haven't got a clue>

1.42 setuserbcolor

SETUSERBCOLOR

Arguments

<red> <green> <blue> [NOTBACKGROUND]

Effect/Description

Will set the user's background color to the closest matching palette position to the given (R,G,B) triplet. This command will cause a visible change to the Palette, and will set the color that is drawn with the mouse.

The NOTBACKGROUND flag, if specified, will ensure that the new color is not the previous background color.

This command is not yet implemented.

Return Values

rc is always 1.

Example

SetUserBColor 0 1 2 /* Almost black */

1.43 setuserbpen

SETUSERBPEN

Arguments

<pen>

Effect/Description

Will set the user's background to the palette position <pen>. This command will cause a visible change to the Palette, and will set the color that is drawn with the mouse. The NOTBACKGROUND flag, if specified, will ensure that the new color is not the previous background color.

This command is not currently implemented.

Return Values

rc is 1 as long as <pen> is a valid palette position.

Example

SetUserBPen 5

1.44 setusercolor

SETUSERFCOLOR

Arguments

<red> <green> <blue> [NOTBACKGROUND]

Effect/Description

Will set the user's foreground color to the closest matching palette position to the given (R,G,B) triplet. This command will cause a visible change to the Palette, and will set the color that is drawn with the mouse.

The NOTBACKGROUND flag, if specified, will ensure that the new color is not the background color.

Return Values

rc is always 1.

rc2 is the pen number of the color chosen.

Example

SetUserFColor 9 9 9 /* Gray */

1.45 setuserfpen

SETUSERFPEN

Arguments

<pen>

Effect/Description

Will set the user's foreground to the palette position <pen>. This command will cause a visible change to the Palette, and will set the color that is drawn with the mouse. The NOTBACKGROUND flag, if specified, will ensure that the new color is not the background color. <pen> ranges from zero to (number of colors in palette) - 1.

Return Values

rc is 1 as long as <pen> is a valid palette position.

Example

SetUserFPen 0 /* Background color? */

1.46 setusertool

SETUSERTOOL

Arguments

<mode>

Effect/Description

This command will cause the user's current Tool Setting to change to <mode>. This command causes a visible change in the ToolBar.

Return Values

rc is 1 as long as <mode> is a valid **mode index number**

Example

```
SetUserTool 0 /* Selects "dot" mode */
```

1.47 setwindowtitle

SETWINDOWTITLE

Arguments

<message>

Effect/Description

Changes the local window title to <message>

Return Values

rc is always 1.

Example

```
SetWindowTitle HiThereUser
```

1.48 stringrequest

STRINGREQUEST

Arguments

<title> <defaultstring> <message>

Effect/Description

Presents the user with a StringRequester.

Return Values

message - What the user entered, or "(User aborted)" if the user clicked the close box instead of pressing return.

Example

StringRequest ThisIsTheTitle SquidLips WhatsYourFavoriteFood

1.49 typekeys

TYPEKEYS

Arguments

<message>

Effect/Description

Enters <message> into the Chat Line as if the user had typed it in.

Return Values

rc is always 1.

Example

TypeKeys TheUserOnlyWishesHeCouldTypeThisFast

1.50 square

SQUARE

Arguments

<x1> <y1> <x2> <y2> [FILL] [XOR]

Effect/Description

Draws a rectangle with opposing corners (x1,y1) and (x2,y2) in the current foreground color. If the FILL switch is specified, fills the rectangle in. If the XOR switch is specified, draws the square in XOR mode instead of using the current foreground color.

Fails if either set of co-ordinates is outside the drawing window.

Return Values

rc is 1 on success, 0 on failure.

Example

Square 50 50 120 100 FILL

1.51 waitevent

WAITEVENT

Arguments

<timeout> [MESSAGE] [MOUSEDOWN] [MOUSEUP] [RESIZE] [QUIT] [CONNECT]
[DISCONNECT] [TOOLSELECT] [COLORSELECT] [KEYPRESS]

Effect/Description

This is an important function if you wish to make highly interactive ARexx scripts. This function will wait until one of the specified events happens, or <timeout> tenths of seconds have elapsed, and then Return control to the ARexx script with the **Message type Code** and other pertinent data set.

Any combination of the events/switches may be specified at once, the event/switch types are described as follows:

[MESSAGE] - A Message String was received from the remote client's ARexx port.

[MOUSEDOWN] - The user depressed the left mouse button in the drawing area.

[MOUSEUP] - The user let go of the left mouse button in the drawing area.

[RESIZE] - The window was resized.

[QUIT] - The user quit AmiSlate.

[CONNECT] - A connection to a remote AmiSlate client was made.

[DISCONNECT] - The connection to the remote AmiSlate client was broken.

[TOOLSELECT] - The user selected a new tool.

[COLORSELECT] - The user selected a new color

[KEYPRESS] - The user pressed a key.

Return Values

type - the unique **Message type Code** for the event.

x - In TIMEOUT, MOUSEUP and MOUSEDOWN events, the X co-ordinate of

the mouse when the event occurred.

- In RESIZE events, the new width of the window.

y - In TIMEOUT, MOUSEUP and MOUSEDOWN events, the Y co-ordinate of the mouse when the event occurred.

- In RESIZE events, the new height of the window.

message - In MESSAGE events, the message string received.

- In CONNECT events, the name of the host connected to.

code1 - In KEYPRESS events, the ASCII code of the pressed key.

- In TOOLSELECT events, the **Mode Index Code** of the selected tool.

- In COLORSELECT events, the palette entry number of the selected color.

- In MESSAGE events, the **source ID** of the Message.

- In RESIZE events, 0 if the RESIZE was caused locally, else 1.

code2 - unused.

code3 - unused.

code4 - unused.

Example

```
/* Waits 5 seconds, or until one of the three given events happens, before returning */
```

```
WaitEvent 50 stem waitev. MESSAGE RESIZE QUIT
```

```
if (waitev.type == AMessage.Timeout) then say "WaitEvent timed out"
```

```
if (waitev.type == AMessage.Message) then say "Message received: " waitev.message
```

```
if (waitev.type == Amessage.Resize) then say "Resize to: " waitev.x waitev.y
```

```
if (waitev.type == AMessage.Quit) then say "Bye Bye!"
```
