

Motion Pixels Movie CD

Motion Pixels and Sirius Publishing have joined forces to bring you the latest in software video technology for your personal computer. You can now view full-length feature films from a pair of CD-ROM discs, complete with your own personal remote control.

Features

- Video playback in a window or full-screen
- Instant access to any portion of video content
- Fully-functional remote control - *Advance one frame, back one frame, play, stop, rewind, fast-forward, go to specific time, slow-motion, adjustable rewind & fast-forward speeds, audio mute, replay, always on top, boost priority, play fullscreen, minimize/maximize, exit, video time counter, user-definable playback styles, adjustable screen resolutions, video chipset detection, and optimize for no cache.*
- Auto run
- Auto install

Minimum System Requirements

486\66 Mhz CPU
8MB RAM
2X CD-ROM drive
128KB Level 2 cache
Local-bus video adapter (640x480, 256 colors) w\ 1MB RAM
Sound Blaster or 100% compatible sound card w\ speakers
10MB available hard disk space
DOS 5.0
Windows 3.1 or Windows for Workgroups 3.11
Windows-compatible mouse

Recommended System Requirements

Pentium 75Mhz CPU or greater
16 MB RAM or greater
256KB Level 2 cache or greater
4X CD-ROM drive or greater
PCI-bus video adapter (640x480, 32,768 colors) w\ 1 MB RAM
Sound Blaster or 100% compatible sound card w\ speakers
10 MB available hard disk space
DOS 6.0 or greater
Windows 95, or Windows NT
Windows-compatible mouse

Windows 95 Installation

The Motion Pixels Movie CD features an automatic installation routine that runs under Windows 95.

- Insert the CD into the CD-ROM drive. Windows 95 will scan the disc and begin the installation process.
- If the setup does not start automatically, go to the Start Menu in the Windows 95 taskbar and select "Run".
- In the "Run" dialog box, type the CD-ROM drive letter,(i.e. F:\) SETUP.EXE or choose the "Browse" button. Select the appropriate drive letter under "Look In", then click on the SETUP icon. Click on "OK" to begin the installation.
- The Install Shield wizard will appear. When this wizard is complete, click on "Next" to continue or "Cancel" to abort the installation.

- Click "Next" to continue the installation in the Welcome screen, click "Back" to go to the previous screen, or "Cancel" to abort the process.
- In the Change Destination Directory dialog box, click on "Next". This will create a directory called "C:\MPIXELS" on the local hard disk.

Note: As the installation progresses, the system will be checked for any necessary files needed to run the Movie CD program. For example, if Microsoft Video for Windows already exists on your system, it will not be reinstalled. The Movie CD program will make all the necessary modifications to your system files.

- Once the Motion Pixels Program Group is created, click on "Finish" to complete the installation. The Movie CD program will launch automatically. Please consult the "Using the Remote Control" section for more information.
- To remove the Movie CD program from the system, go to the Windows 95 Start Menu, select "Settings", then "Control Panel".
- Click on the "Add\Remove Programs" icon and choose "The Motion Pixels Movie Player"
- Click on the "Add\Remove" button and confirm that you want to delete the files.
- The Uninstall Shield program will launch and remove all applicable files from the system. Close the "Add\Remove Programs" dialog box when finished.

Windows 3.1 Installation

To install the Movie CD program under Windows 3.1 or Windows for Workgroups 3.11, do the following:

- Insert the CD disc into the CD-ROM drive. In the Windows Program Manager, select "File", then "Run".
- In the Command Line box, type the CD-ROM drive letter,(i.e. F:\) SETUP.EXE or choose the "Browse" button. Select the appropriate drive letter under "Drives", then click on SETUP.EXE. Click on "OK" when ready to proceed.
- Click "OK" in the Run dialog box to begin the installation.
- The Install Shield wizard will appear. When this wizard is complete, click on "Next" to continue or "Cancel" to abort the installation.
- Click "Next" to continue the installation in the Welcome screen, click "Back" to go to the previous screen, or "Cancel" to abort the process.
- In the Change Destination Directory dialog box, click on "Next". This will create a directory called "C:\MPIXELS" on the local hard disk.

Note: As the installation progresses, the system will be checked for any necessary files needed to run the Movie CD program. For example, if Microsoft Video for Windows already exists on your system, it will not be reinstalled. The Movie CD program will make all the necessary modifications to your system files.

- Once the Motion Pixels Program Group is created, click on "Finish" to complete the installation. The Movie CD program will launch automatically. Please consult the "Using the Remote Control" section for more information.

Note: A message may appear "No DCI driver installed". This error message is not an error message at all, but a status message stating that your video performance will increase if you have a DCI driver for your specific video adapter. Please consult your video adapter manufacturer for more information.

- To remove the Movie CD program from the system, click on the Uninstall icon in the Motion Pixels Program Group.