

EPSON MX SERIES PRINTER CONTROL AND ESCAPE CODE WORKSHEET

JAMES G. CONTOS
THE COMPUTER TUTOR
303 PARK DRIVE
JOLIET, IL 60436

THIS WORKSHEET CONTAINS SOME OF THE POPULAR EPSON MX SERIES PRINT CODES. TO USE A PARTICULAR CODE IN YOUR WORKSHEET, USE THE FOLLOWING STEPS:

- 1) POSITION YOURSELF AT THE CELL IN YOUR WORKSHEET THAT YOU WANT TO "ENHANCE"
- 2) TYPE IN THE FOLLOWING 1-2-3 COMMAND SEQUENCE: /FCCN
- 3) AT THIS POINT, 1-2-3 WANTS TO KNOW THE NAME OF THE RANGE TO GET, SO ANSWER WITH THE CODE LETTER OF THE DESIRED PRINT FUNCTION. (SEE THE TABLE BELOW)

CODE LETTER	CODE STRING	FUNCTION
A	X	BACKSPACE (USE FOR OVERSTRIKE)
B	XXX	CONDENSED ON/OFF
C	4XXX5	ITALICS ON/OFF
D	EXXXF	EMPHASIZED ON/OFF
E	GXXXH	DOUBLE STRIKE ON/OFF
F	XXX	DOUBLE WIDE ON/OFF

- 4) FINALLY, 1-2-3 WANTS TO KNOW THE NAME OF THE FILE TO GET THE NAMED RANGE FROM. UPON GIVING IT THE FILE NAME, SUCH AS PRTCODES IN THIS EXAMPLE, SOMETHING LIKE THE FOLLOWING WILL APPEAR IN THE CELL:

4XXX5 (THIS IS THE CODE FOR ITALICS ON)

- 5) THE XXX IS TO BE REPLACED WITH YOUR TEXT VIA THE EDIT FEATURE OF 1-2-3. AFTER THAT, THE CELL MAY LOOK LIKE THIS:

-THIS TEXT WILL BE IN ITALICS!-

6) THAT'S IT! WHEN YOUR WORKSHEET IS PRINTED, THIS CELL
WILL BE PRINTED USING THE EPSON ITALICS FONT MODE.

Г

Э)

[/OFF)