

## Introduction

SSCFG32 allows Windows 3.1 users to configure and run many Windows NT screen savers. SSCFG32 comes with the following Windows NT screen savers:

<u>Filename</u>	<u>Comments</u>
CLOCK.SCR	Current Time
DANCE.SCR	Dancing Lines
HYPERS.SCR	HyperCycloids
LIFE.SCR	Conway's Game of Life
SNAKES.SCR	Animated Snakes
SPHERES.SCR	3-Dimensional Spheres
ZOOM.SCR	Enlarge/Reduce Desktop

In addition to configuring NT screen savers, SSCFG32 can also configure ordinary Windows 3.1 screen savers.

## Required Software

SSCFG32 requires Windows 3.1 running in Enhanced Mode and Win32s. Win32s requires a 386 or better CPU and at least 4 MB of memory.

## Installing the Program

In order to run SSCFG32, you must have previously installed the Win32s software. The Win32s software allows Windows 3.1 users to run many Windows NT programs, including screen savers. If you need the Win32s software, send a POSTPAID, self-addressed disk mailer containing a high-density 3 1/2" or 5 1/4" floppy disk to:

Pocket-Sized Software  
8547 E. Arapahoe Road  
Suite J-147  
Greenwood Village, CO 80112 USA

Please include a note requesting the Win32s software.

To install SSCFG32:

1. Install the Win32s software.
2. Unzip the files if necessary.
3. Copy SSCFG32.CPL and SSCFG32.HLP to your \WINDOWS\SYSTEM directory.
4. Copy all the .SCR files to your \WINDOWS directory.
5. Re-start Windows.

## Running SSCFG32

After re-starting Windows, go to the Windows Control Panel. Double-click the SSCFG32 icon with the mouse. For further instructions, press the Help button.

## **Distribution and Payment**

SSCFG32 and the included screen savers may be freely copied without cost, provided they are not changed in any way. If you find them useful, please send \$5.00 to:

Pocket-Sized Software  
8547 E. Arapahoe Road  
Suite J-147  
Greenwood Village, CO 80112 USA

## **Other Shareware Programs from Pocket-Sized Software**

Consult the on-line help for information about other shareware programs from Pocket-Sized Software.