Creative SoftWorks Inc.redible

WINEXIT - Fast End Session Program

Contents:

What is WINEXIT? How to use Features of WINEXIT CSWI

What is WINEXIT?

WINEXIT is a Fast End Session program for Windows 3.1 or later.

It is used to exit Windows as quick as possible.

How to use WINEXIT

Double click on the WINEXIT-icon will cause the end session of the Windows.

Right mouse button gives the menu (see more details in 'Features of WINEXIT').

WINEXIT INSTALLATION: Move the WINEXIT-icon to startup-group or add run= and the program's whole path in place [Windows], <u>e.g.</u>, in Windows win.ini-file.

PARAMETERS: WINEXIT adds its own [Winexit] -section in win.ini-file. There are parameters: <u>Query</u> and <u>Top</u> (see more details about the denotation of parameters in 'Features of WINEXIT, Control window').

There is also the third parameter <u>NoExecute</u> in win.ini [Winexit]-section. NoExecute is used only when the WINEXIT is started from Program Manager icon. It must be added manually by editing win.ini.

WINEXIT-program requires WIN 3.1 or later.

[windows] .

- run = c:\windows\cswi\winexit.exe
 - .

When Query = 0, then session ends without query. When Query = 1, then session ends with query. When Top = 0, then the 'always on top'-setting is off. When Top = 1, then the 'always on top'-setting is on. When NoExecute = 0 Winexit is in default settings. When NoExecute = 1 it exits immediately, when Winexit is started.

Features of WINEXIT

WINEXIT uses functions in <u>CTL3DV2.DLL</u> file to create 3D controls.

Right mouse button will open the menu box, which includes four functions:

CLOSE - will exit the program, same function as the key combination Alt-F4.

HELP - will open the help system, same as the key F1.

CONTROL - will open the <u>control window</u>, same as the key F8.

ABOUT WINEXIT - will open the about window, which will tell you some information about the program.

CTL3DV2.DLL is a Dynamic Link Library from Microsoft Corporation.

It is needed to create 3D controls in Windows. This file MUST be located in the \SYSTEM directory of Windows. NOT in the same directory with WINEXIT!



Creative SoftWorks Inc.redible

Freeware -team

| Duty | Alias | Internet e-mail address |
|----------------------------|----------------|-------------------------|
| idea and code | by Tomppa-setä | tomitm@evitech.fi |
| code | by Turno | atu@phoenix.oulu.fi |
| graphics and documentation | by Jone | s93081@mail.vitech.fi |

Mail can be sent to the following address: Tomi Mikkonen Viherlaaksonranta 14 B 24 02710 ESPOO FINLAND

If possible, please contact via e-mail!

This is Freeware, be free !



Control Window

Control Window has two groups WINDOW and POSITION.

WINDOW-group:

END SESSION WITH QUERY - If there is a check mark in this box, WINEXIT will ask, if you want to end Windows. Otherwise it will pass the query. Of course, if you have tasks open and they are not saved, WINEXIT gives you opportunity to save them. In any case all open tasks are possible to save before ending Windows.

ALWAYS ON TOP - causes WINEXIT to be displayed always on the top of other windows.

POSITION-group:

WINEXIT position can be changed by moving window using its' drag'n'drop feature. Another possibility is to enter screen x- and y-coordinates into their places. It is impossible to move WINEXIT out of the screen, if you try it, you will get an error message and the current position is returned. When you will open the control window there are the current coordinates of the WINEXIT in position section.

SAVE SETTINGS AS DEFAULT - When you check this box and press OK, all settings in control window will be saved in to the Win.ini file after pressing the button.