

Arexx_Printers

Copyright © 1992-1996 Nova Design, Inc.

COLLABORATORS

	<i>TITLE :</i> Arexx_Printers		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		January 13, 2023	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	Arexx_Printers	1
1.1	ImageFX Printer Module Commands	1
1.2	PostScript Printer Module Commands	1
1.3	Prefs Printer Module Commands	1
1.4	Prefs2 Printer Module Commands	2
1.5	SuperPrefs Printer Module Commands	2
1.6	Printer Format	2
1.7	Printer Image	3
1.8	Printer Mode	3
1.9	Printer Offset	4
1.10	Printer Page	4
1.11	Printer Print	4
1.12	Printer Aspect	5
1.13	Printer Density	5
1.14	Printer Print	6
1.15	Printer Aspect	6
1.16	Printer Density	6
1.17	Printer FormFeed	7
1.18	Printer Print	7
1.19	Printer Shade	7
1.20	Printer Size	8
1.21	Printer Aspect	8
1.22	Printer Density	9
1.23	Printer FormFeed	9
1.24	Printer Options	9
1.25	Printer Print	10
1.26	Printer Shade	10
1.27	Printer Size	11

Chapter 1

Arexx_Printers

1.1 ImageFX Printer Module Commands

Select A Printer Module:

PostScript

Prefs

Prefs2

*

SuperPrefs
(2.6)

1.2 PostScript Printer Module Commands

Available Commands Are:

Printer Format

Printer Image

Printer Mode

Printer Offset

Printer Page

Printer Print

1.3 Prefs Printer Module Commands

Available Commands Are:

Printer Aspect
Printer Density
Printer Print

1.4 Prefs2 Printer Module Commands

Available Commands Are:

Printer Aspect
Printer Density
Printer FormFeed
Printer Print
Printer Shade
Printer Size

1.5 SuperPrefs Printer Module Commands

Available Commands Are:

Printer Aspect
Printer Density
Printer FormFeed
Printer Print
Printer Shade
Printer Size

1.6 Printer Format

PRINTER FORMAT**FORMAT**

Printer Format PS/S,EPS/S

FUNCTION

Select the file format saved.

INPUTS**PS**

Select standard PostScript output.

EPS

Select Encapsulated PostScript output.

RESULT

None.

1.7 Printer Image

PRINTER IMAGE**FORMAT**

Printer Image Width/A,Height/A

FUNCTION

Set the output image size, in inches.

INPUTS

Width, Height

Output image size, in inches. Fractional values are accepted.
Must be less than the page size.

RESULT

None.

1.8 Printer Mode

PRINTER MODE**FORMAT**

Printer Mode Binary/S,ASCII/S

FUNCTION

Select whether to write standard ASCII or binary data.

INPUTS

Binary

Image data is output in binary (produces smaller files).

ASCII

Image data is output as ASCII text.

RESULT
None.

1.9 Printer Offset

PRINTER OFFSET

FORMAT
Printer Offset Left/A,Top/A

FUNCTION
Set the image offset from the top left corner of the page.

INPUTS
Left, Top
Upper left corner of the image, given in inches distanced from the
tupper left corner of the page. Fractional values are accepted.

RESULT
None.

1.10 Printer Page

PRINTER PAGE

FORMAT
Printer Page Width/A,Height/A

FUNCTION
Set the page size, in inches.

INPUTS
Width, Height
Width and height of the page, in inches. Fractional values are
accepted.

RESULT
None.

1.11 Printer Print

PRINTER PRINT

FORMAT
Printer Print File/A

FUNCTION
Print the main image buffer to a PostScript file, using the current

PostScript settings. Note that the file may be SER: or PAR: to print directly to a printer.

INPUTS**File**

Name of the file to send PostScript data to. If not given, a file requester will be presented.

RESULT

None.

1.12 Printer Aspect

PRINTER ASPECT**FORMAT**

Printer Aspect Ignore/S,Keep/S

FUNCTION

Choose whether or not to heed the main buffers aspect and DPI settings.

INPUTS**Ignore**

Ignore images DPI/aspect settings; use the values defined in the Preferences Limits.

Keep

Keep images DPI/aspect settings; the image will print out in the size specified by these values.

RESULT

None.

1.13 Printer Density

PRINTER DENSITY**FORMAT**

Printer Density Value/N

FUNCTION

Select the print density, as defined in Preferences.

INPUTS**Value**

Density value, ranging from 1-7. See the documentation for your printer driver for the meanings of the 7 densities.

RESULT

None.

1.14 Printer Print

PRINTER PRINT

FORMAT

Printer Print

FUNCTION

Print the main image buffer to the current printer driver as defined by Preferences. Uses the current settings of the print module.

INPUTS

None.

RESULT

None.

1.15 Printer Aspect

PRINTER ASPECT

FORMAT

Printer Aspect Ignore/S,Keep/S

FUNCTION

Choose whether or not to heed the main buffers aspect and DPI settings.

INPUTS

Ignore

Ignore images DPI/aspect settings; use the values defined in the Preferences Limits.

Keep

Keep images DPI/aspect settings; the image will print out in the size specified by these values.

RESULT

None.

1.16 Printer Density

PRINTER DENSITY

FORMAT

Printer Density Value/N

FUNCTION

Select the print density, as defined in Preferences.

INPUTS

Value

Density value, ranging from 1-7. See the documentation for your printer driver for the meanings of the 7 densities.

RESULT

None.

1.17 Printer FormFeed

PRINTER FORMFEED

FORMAT

Printer FormFeed

FUNCTION

Send a form feed command to the printer.

INPUTS

None.

RESULT

None.

1.18 Printer Print

PRINTER PRINT

FORMAT

Printer Print

FUNCTION

Print the main image buffer to the current printer driver as defined by Preferences. Uses the current settings of the print module.

INPUTS

None.

RESULT

None.

1.19 Printer Shade

PRINTER SHADE

FORMAT

Printer Shade BW/S,Grey/S,Color/S

FUNCTION

Select the print shade.

INPUTS

BW
Select black & white (monochrome) printing.

Grey
Select greyscale printing.

Color
Select color printing.

RESULT
None.

1.20 Printer Size

PRINTER SIZE

FORMAT
Printer Size Width,Height

FUNCTION
Specify output print size, in inches.

INPUTS
Width, Height
Output print size, in inches.

RESULT
None.

1.21 Printer Aspect

PRINTER ASPECT

FORMAT
Printer Aspect Ignore/S,Keep/S

FUNCTION
Choose whether or not to heed the main buffer's aspect and DPI settings.

INPUTS
Ignore
Ignore image's DPI/aspect settings; use the values defined in the Preferences Limits.

Keep
Keep image's DPI/aspect settings; the image will print out in the size specified by these values.

RESULT
None.

1.22 Printer Density

PRINTER DENSITY

FORMAT

Printer Density Value/N

FUNCTION

Select the print density, as defined in Preferences.

INPUTS

Value

Density value, ranging from 1-7. See the documentation for your printer driver for the meanings of the 7 densities.

RESULT

None.

1.23 Printer FormFeed

PRINTER FORMFEED

FORMAT

Printer FormFeed

FUNCTION

Send a form feed command to the printer.

INPUTS

None.

RESULT

None.

1.24 Printer Options

PRINTER OPTIONS

FORMAT

Printer Options

Dither/N, Magenta/N, Yellow/N, Gamma, UseIFX/S, UsePrefs/S,
Horiz/S, Vert/S, FormFeed/S, NoFormFeed/S

FUNCTION

Set extended SuperPrefs options.

INPUTS

Dither

Select dither method:

0 = 8x8 Dispersed

1 = 16x16 Dispersed

2 = 6x6 Cluster
3 = 8x8 Cluster
4 = 16x16 Cluster

Magenta, Yellow
Magenta and yellow ink compensations for color printouts.

UseIFX, UsePrefs
Render method.

Horiz, Vert
Print orientation.

FormFeed, NoFormFeed
Enable or disable form feed after printing.

RESULT
None.

1.25 Printer Print

PRINTER PRINT

FORMAT
Printer Print

FUNCTION
Print the main image buffer to the current printer driver as defined by Preferences. Uses the current settings of the print module.

INPUTS
None.

RESULT
None.

1.26 Printer Shade

PRINTER SHADE

FORMAT
Printer Shade BW/S,Grey/S,Color/S

FUNCTION
Select the print shade.

INPUTS
BW
Select black & white (monochrome) printing.

Grey
Select greyscale printing.

Color
Select color printing.

RESULT
None.

1.27 Printer Size

PRINTER SIZE

FORMAT
Printer Size Width,Height

FUNCTION
Specify output print size, in inches.

INPUTS
Width, Height
Output print size, in inches.

RESULT
None.
