

April 27th 1996
mIRC version 4.1
Tjerk Vonck. mirc@dds.nl

<http://www.mirc.co.uk/index.html>
<http://www.sbcomp.com/mirc/index.html>
<http://www-2.nijenrode.nl/software/mirc/index.html>
<http://www.geocities.com/Colosseum/1822/index.html>

-Note-
mIRC supports almost all IRCii commands that make sense in mIRC and/or windows... Commands like Set_blabla are not supported cause Windows uses pull down menus and option dialogs to change settings. Other commands like Scroll_lock make no sense in the Windows. Guys, we have scroll bars.... All standard server specific commands are available too... If you need more info on any command listed here, type /help <command> in mIRC.

All (?) mIRC's commands :

/ Recalls the previous command entered in the current window.
/! Recalls the last command typed in any window.
/action <action text> Sends the specified action to the active channel or query window.
/add [-apuce] <filename.ini> Loads aliases, popups, users, commands, and events.
/ame <action text> Sends the specified action to all channels which you are currently on.
/amsg <text> Sends the specified message to all channels which you are currently on.
/auser [-a] <level> <nick|address> Adds a user with the specified access level to the remote users list.
/auto [-r] [on|off|nickname|address] Adds (-r removes) auto-opping of a nick or address or sets it on or off totally.
/away <away message> Sets you away leave a message explaining that you are not currently paying attention to IRC.
/away Sets you being back.
/ban [#channel] <nickname> [type] Bans the specified nick from the current or given channel.
/beep [<number> <delay>] Locally beeps 'number' times with 'delay' inbetween the beeps.
/channel Pops up the channel central window (only works in a channel)
/clear Clears the entire scrollbar buffer of the current window.
/clearall Clears all text in all open windows.
/closemsg <nickname> Closes the query window you have open to the specified nick.
/commands [on|off] Sets the Tools/Remote/Commands section on or off or checks its status.
/creq [ask | auto | ignore] Sets your DCC 'On Chat request' settings in DCC/Options.
/ctcp <nickname> <ping|finger|version|time|userinfo|clientinfo> Does the given ctcp request on nickname.
/dcc send <nickname> <file1> [file2] [file3] ... [fileN] Sends the specified file(s) to nick.
/dcc chat <nickname> Opens a dcc window and sends a dcc chat request to nickname.
/dde [-r] <service> <topic> <item> [data] Allows DDE control between mIRC and other applications.
/ddeserver [[on [service name] | off] To turn on the DDE server mode, eventually with a given service name.
/describe <#channel> <action text> Sends the specified action to the specified channel window.
/disable <#groupname> De-activates a group of commands or events in the remote section.
/disconnect Forces a hard and immediate disconnect from your IRC server. Use it with care.
/dlevel <level> Changes the default user level in the remote section.
/dns <nickname | IP address | IP name> Uses your providers DNS to resolve an IP address.
/echo [N] [-s|nickname|#channel] <text> Displays the given text only to YOU on the given place in color N.
/enable <#groupname> Activates a group of commands or events.
/events [on|off] Shows the Tools/Remote/Events section status or sets it to listening or not.
/exit Forces mIRC to closedown and exit.
/finger <nickname | address> Does a finger on a users address... also if his nick is given.
/flood [<numberoflines> <seconds> <pausetime>] Sets a crude flood control method.
/flush [levels] Clears all nicknames from the Remote/users list that are currently not on your channels.
/font Activates the font selection dialog.
/fsend [on|off] Shows fsends status and allows you to turn dcc fast send on or off.
/fserve <nickname> <maxgets> <homedirectory> [welcome text file] Opens a fileserver.
/groups [-eld] Shows all (enabled or disabled) groups defined in the remote sections.
/guser [-a] <level> <nick> [type] Adds the user to the user list with the specified level and address type.
/help <keyword> Brings up the Basic IRC Commands section in the mIRC help file.
/ignore [-r][on|off|nickname|address] [type] Ignores a nick or address or sets it on or off totally. -r to remove.
/invite <nickname> <#channel> Invites another user to a channel.

/join <#channel> Makes you join the specified channel.
 /kick <#channel> <nickname> Kicks nickname off a given channel.
 /links Shows the entire list of IRC servers in the network you are currently connected to.
 /list [#string] [-min #] [-max #] Lists all currently available channels, evt. filtering for parameters.
 /load <-apuce> <filename.ini> Loads Aliases, Popups or Remote items into mIRC.
 /log [on|off] Shows the logging status or sets it on or off for the current window.
 /me <action text> Sends the specified action to the active channel or query window.
 /mode <#channel|nickname> [[+|-]modechars [parameters]] Sets channel or user modes.
 /msg <#channel|nickname> <message> Send a private message to this user without opening a query window.
 /names <#channel> Shows the nicks of all people on the given channel.
 /nick <new nickname> Changes your nickname to whatever you like.
 /notice <nick> <message> Send the specified notice message to the nick.
 /notify [-sh][-ar][on|off|nickname] Toggles notifying you of a nick on IRC or sets it on or off totally.
 /onnotice [#channel] <message> Send the specified notice message to all channel ops.
 /omsg [#channel] <message> Send the specified message to all ops on a channel.
 /part <#channel> Makes you leave the specified channel.
 /partall Makes you leave all channels you are on.
 /ping <server address> Pings the given server. NOT a nickname.
 /play [-cpqmr] [channel/nick] <filename> [delay/linenumber] Allows you to play text files. Read the help !
 /pop <delay> [#channel] <nickname> Performs a randomly delayed +o on a not already opped nick.
 /protect [-ar][on|off|nickname|address] Toggles protection of a nick or address or sets it on or off totally.
 /query <nickname> <message> Open a query window to this user and send them the private message.
 /quit [reason] Disconnect you from IRC with the optional goodbye message.
 /raw [-q] <raw command> Sends any raw command you supply directly to the server. Use it with care !
 /remote [on|off] Sets the entire Tools/Remote section on or off or checks its status.
 /remove <c:\path\filename> Will delete the requested file.
 /rlevel <access level> Removes all users from the remote users list with the specified access level.
 /run <c:\path\program.exe> [parameters] Runs the specified program, evt. with parameters.
 /ruser [-r] <nick[!]|address> [type] Removes the user from the remote users list.
 /save [-apuce] <filename.ini> Saves remote sections into a specified INI file.
 /say <text> Says whatever you want to the active window.
 /server [server # | server address [port] [password]] (Re)connects to the server or a newly specified one.
 /sound [nickname|#channel] <filename.wav> <action text> Sends an action and a fitting sound request.
 /speak <text> Uses the external text to speech program Monologue to speak up the text.
 /sreq [ask | auto | ignore] Sets your DCC 'On Send request' settings in DCC/Options.
 /time Tells you the time on the server you use.
 /timer[N] <repetitions> <interval in seconds> <command> [<more commands>] Activates a timer.
 /timestamp [on | off] Sets timestamping on or off for all your conversations.
 /topic <#channel> <newtopic> Changes the topic for the specified channel.
 /ulist [<|>]<level> Lists all users in the remote list with the specified access levels.
 /url [-d | on | off | close] Opens or closes the URL window that allows you to surf the www parallel to IRC.
 /uwho [nick] Pops up the user central with information about the specified user.
 /version Tells you the version of the IRC server you use.
 /wavplay <c:\path\sound.wav> Locally plays the specified wave file.
 /who <#channel> Shows the nicks of all people on the given channel.
 /who <*address.string*> Shows all people on IRC with a matching address.
 /whois <nickname> Shows information about someone in the status window.
 /whowas <nickname> Shows information about someone who -just- left IRC.
 /write [-cid] <filename> [text] To write the specified text to a .txt file.

Idea of the day : Print this file as well as the mIRC FAQ and store them in the bathroom ! You'll read them !
 (..... no people, not -as- but next to the toilet paper..)

 The syntax used in this file is the one DOS uses too.... look in your DOS help files to get a goood explanation
 {x}, {x|y or <x|y> means you HAVE to use one or more of the choises
 x|y means use x OR y
 x,y means use x and/or y
 [x] means you can but dont have to use this parameter

- [-a] Will force the item to be added to the list (not toggled)
- [-r] Will force the item to be removed from the list (not toggled)
- [-q] Will force the operation to happen quietly (no report in any window)

EXAMPLE :

```
/echo <N> [nickname|#channel|status] {text}
```

Displays the given text only to YOU on the given place in color N {1..6}.

in this case you ALWAYS have to give a number N in the range 1,2,3,..6.
and you HAVE to give the 'text'
and you -can- give a nickname (to display the text in a private window)
OR a channel name OR the word 'status' to display in your status window..

EXAMPLE :

```
/auto [on|off|nickname|address] (the auto-op function)
```

here your possibilities are

```
/auto to ; see its status
```

```
/auto on ; to set it on
```

```
/auto off ; to set it of
```

```
/auto nickname ; to toggle autoopping of a person by nick
```

```
/auto address ; to toggle autoopping of a person by address
```