

Default

COLLABORATORS							
	TITLE : Default						
ACTION	NAME	DATE	SIGNATURE				
WRITTEN BY		June 25, 2022					

REVISION HISTORY							
NUMBER	DATE	DESCRIPTION	NAME				

Default

Contents

1	Defa	Default			
	1.1	Main	1		
	1.2	Distribution	1		
	1.3	Installation	2		
	1.4	Introduction	2		
	1.5	System Requirements	2		
	1.6	Configuration	2		
	1.7	Contact	3		
	1 8	Disclaimer	1		

Default 1/4

Chapter 1

Default

1.1 Main

LedA version 0.9

Tiny frontend for AmiTCP and related tools.

© 1997 Marek Jablonski.

Introduction

System Requirements

Installation

Configuration

Contacting the Author

Disclaimer

Distribution

1.2 Distribution

Distribution

The program and files in this distribution are freely distributable, but are also Copyright (c) Marek Jablonski (with one exception: The led.image file is Copyright (c) 1994 Commodore-Amiga, Inc.). They may be freely distributed as long as no more than a nominal fee is charged to cover time and copying costs.

Default 2/4

1.3 Installation

Installation

```
'LedA' can be located anywhere on your system. 'LedA' requires 'led.image' (included) to work. It must be present in your sys:classes/images directory (or in libs:images if you prefer).
```

1.4 Introduction

1.5 System Requirements

```
System requirements
-----

* An Amiga with Kickstart 2.0 or higher.

Tested on
-----

* A4000/040, 2 Mb Chip, 20 Mb Fast Ram

* A600, 2 meg Chip.
```

1.6 Configuration

```
Configuration
```

Default 3/4

```
You can set up 'LedA' by editing tooltypes of its (her?) icon.
These are supported tooltypes:
 START - (re)starts the AmiTCP/IP protocol stack. Resets and starts the
         counter.
         Eg. START=AmiTCP:Bin/startnet
         Note:
         Script files (like 'startnet') MUST have 's' flag set. It can be
         done from shell:
         1> protect AmiTCP:Bin/startnet S ADD
 STOP - stops AmiTCP/IP protocol stack if possible. Stops the counter.
         Saves start/stop/elapsed time to log file.
         Eg. STOP=AmiTCP:bin/stopnet
 EMAIL - Mail program of your choice.
         Eq. EMAIL=Mail:Thor/Thor
  IRC - As above-mentioned but for IRC
         Eg. IRC=dh1:comms/amirc/amirc
 WWW
     - I think it is quite obvious ;-)
 FTP - Isn't it?
 TELNET - TELNET=Work:comms/AmTelnet would be nice.
 XCOOR - X position of the left top corner of the LedA's window
         Eq. XCOOR=400
 YCOOR - same for the Y coordinate.
 LOG - Name of the log file. Default is T:LedA.log. BTW, 'LedA' does not
         check CARRIER. It (She) simply records your clicks on
         START/STOP buttons.
         Eg. LOG=AmiTCP:log/my.log
 Important:
 Clicking the close gadget will cause an action defined in STOP tooltype
 before quitting.
1.7 Contact
Contact
 If you have any suggestions, bug reports etc.
```

EMail: mjab69@friko.onet.pl

Default 4/4



Author takes no responsibility [...] etc. In other words: Have fun ;-)