

DRAFU ii

COLLABORATORS				
	TITLE :			
ACTION	NAME	DATE	SIGNATURE	
WRITTEN BY		June 25, 2022		

REVISION HISTORY				
NUMBER	DATE	DESCRIPTION	NAME	

DRAFU

Contents

1	DRA	AFU	1
	1.1	DRAFU_Documentation	1
	1.2	purpose	2
	1.3	ps	2
	1.4	installation	2
	1.5	usage	3
	1.6	history	11
	1.7	correspondence	13
	1.8	distribution	15
	1.9	copyrights	16

DRAFU 1/16

Chapter 1

DRAFU

1.1 DRAFU_Documentation

```
DRAFU plus V2.10 (18.8.97)
```

- SHAREWARE -

 \odot 1990-97 by Andreas Ralph Kleinert. All rights reserved. FWB \odot 1991-97 by Dipl.Ing. Ulrich Degens. All rights reserved.

A PerSuaSiVe SoftWorX PRODUCT.

EMail: Andreas Kleinert (Fido 2:2457/350.18) (see "Where to send ..." for more addresses)

Needs Kickstart V2.04. Kickstart release 3.x compatible. GUI created with Designer 1.54.

Copyrights

Distribution

Author/Correspondence

PerSuaSiVe SoftWorX

The program's purpose

How to install it

How to use it

Program history

_ //
Only \X/ Amiga makes it possible!

The CHAOS-Theory (rough english translation):

DRAFU 2/16

The Chaos theory for example deals with trying to catch the god damned butterfly, which caused the many storms the last times.

(see "Witches Abroad" by Terry Pratchett)

Ahm...well:

...and thanks for all the fish.

1.2 purpose

DRAFU means (D) raw (A) (Fu) nction, which seems to be a good description of the program's abilities:

DRAFU is able to display all mathematical functions - certainly also many at the same time - on your screen.

Also there's the possibility to calculate Integrals and Zeropoints of functions.

Optionally:

The display may be saved in any of the graphics file formats, which superview.library does support.

The Evaluation version (without keyfile) does not allow saving of function description files (ending ".dfu"), which may only be created by hand until you recive your keyfile.

1.3 ps

Well, once there was resistance and we were persistent.

But then one thought he must clone that company name :-> so we changed it to "PerSuaSiVe SoftWorX".

1.4 installation

Even if you use the supplied Installer-Script, you should read the following notes. If you do not own the standard Installer-Program you should read them even more carefully and follow the instructions given.

If you own a KeyFile, place it to "S:", or place it elsewhere and change the environment variable "KEYPATH" to the corresponding directory.

Needed Workbench Resources

HardDisk-Users won't perhaps have to install any additional Workbench Resources to their HardDisk.

Disk-Users will have to copy the following libraries into their "LIBS:"-Directory, if these not already do residate in ROM (may depend on the version of the operating system):

DRAFU 3/16

```
- gadtools.library V37+
- asl.library V37+
- workbench.library V37+
- icon.library V37+
```

Users of OS V2.04 or greater should also install the following libraries:

- amigaguide.library V34+

Users of OS V2.1 or greater should also install the following libraries:

- locale.library V38+

1.5 usage

```
1.1 "First Steps" or "How to display a function !?"
```

At first you have to select a suitable Screen-Mode and Color-Depth inside the DRAFU-ModeRequester.

The best solution would perhaps be an Interlace-Mode, but you may also work in the Hires-Mode quite good.

After that you have to choose the Menu "Functions" and then "f(x)=???", where you have to select inside the FunctionRequester, which function you would edit or that you want to enter a new one. Also the value of a Step-Size and the borders of the interval, which

Also the value of a Step-Size and the borders of the interval, which should be displayed are to enter here.

The following things then can be done with the entered function :

- "Draw alone

(Draw and display the function, after clearing the Screen before.)

- "Add to drawing"

(Draw and display the function, WITHOUT clearing the Screen before.)

- "single/multiple x-range"

(Enter a partly-defined function. This is described under 1.2.)

- "Do not draw"

(Leaves the requester, but memorizes the funtion.)

After that the calculation begins and the function will be displayed.

DRAFU 4/16

1.1.1 Allowed Functions And Operators

Functions	Operators	
sin	+	
cos	_	
tan	*	
exp	/	
neg	^	
asin		
acos		
atan		
abs		
sinh		
cosh		
tanh		
ld		
log		
log10		
sqrt		
asinh		
acosh		
atanh		

${\tt 1.2~Partly-defined~Functions~(ASWD-Functions)}$

DRAFU also allows to display (some kinds of) partly-defined functions, in the following called ASWD-Functions. (German: "abschnittsweise definierte Funktionen"). Please note the following:

- Select "multiple x-ranges"
- You now get into a second FunctionRequester, where you have to enter three (perhaps different) functions, and also a right intervalborder for each function.

This is quite the same like in the following mathematic term :

Certainly ASWD-Functions may later be selected within the normal FMemoRequester and then be edited in the FunctionRequester.

1.3 More information :

DRAFU 5 / 16

```
Zooming of rectangles on the Screen:
```

After selection of the Sub-Menu "Zoom" (second Menu), you may zoom parts of the currently displayed functions on the Screen as follows:

What you have to do is quite the same like a simple sizing of a Intuition-Window.

Just move the Mouse-Pointer to the left, upper corner of the rectangle

Then press the left mouse-button and keep it pressed. Now move the Pointer to the right, lower border of the rectangle and stop pressing the button after this.

While doing this, the currently chosen rectangle is constanly shown as a kind of a "Line-Window", so that you perhaps always see, which part you would zoom, when releasing the mouse-button.

Note: The stepsize for the function is only updated, if the specific menu-point is not set to "By hand".

```
The Speed of Drawing in the "By hand"-Mode:
```

If you think, that the drawing-speed of DRAFU is not high enough, you may change the precision of drawing, which means the "Step-Size", because normally this is set to 0.1 for each new function, which actually a very high value.

two times faster with 0.2,

```
two times faster with 0.2, three times faster with 0.3, four times faster with 0.4 and so on !!!
```

Reading of drawn values :

Well, it is not always easy to see only by the eye (no big glasses ...), at which point, e.g. a Null-Value exists, or e.g. two functions are crossing.

What to do ? Just zoom the critical part and then select the Sub-Menu "Cursor".

According to each move of the Mouse-Pointer then in the Titlebar of the Info-Window the exact X- and Y-Values (no pixel-values!) are displayed. Pressing of the left mouse-button exits from this feature.

```
Integrating Functions :
```

DRAFU also gives you the possibiliy, to integrate functions. This may be already entered functions (from the FMemoRequester) or other functions (static, not memorized).

ASWD-Functions cannot be integrated yet.

DRAFU 6 / 16

A graphical display of the calculated data is also not yet possible. Also the results are not memorized.

Zeropoints of Functions :

DRAFU further gives you the possibiliy, to search intervals of functions for zeropoints.

For this one of the currently displayed functions from the FMemoRequester is selected and an interval is specified via the Zoom-Function.

ASWD-Functions cannot be examined yet.

A graphical display of the calculated data is also not yet possible. Also the results are not memorized.

```
Saving of Screens (IFF-Support) :
```

With superview.library being installed, DRAFU is able to save any single window in one of the graphics file formats, which superview library allows to write.

superview.library is not needed to run the program as such.

```
Saving and Loading of Memo-Lists :
```

Saving of a Memo-List allows to "conservate" all currently entered functions inside the FMemoRequester.

Loading of a Memo-List allows to "restaurate" functions, which have been saved before (or edited as an ASCII-File).

Loading of a Memo-List also results in a "re-drawing" of those functions.

Things like Screen-Width or color-selection are not stored inside the the saved Memo-List, because of functional reasons.

Just set those "by hand" and then select the Sub-Menu "Draw Again".

Also the last set intervals for the X- and Y-Axis are not saved. Loaded Memo-List would just be drawn into the current one.

If you like to create such "load-ready" Memo-Files by hand or use them for other purposes, just look into the additional documentation-file "DRAFU_special.doc", where the format of ".dfu"-files is described.

Hardcopies :

If you want to print a HardCopy directly from the screen, without saving it as an IFF-ILBM-File and using a special tool, just select the Sub-Menu "Hardcopy".

If a printer is "on-line", you'll get a fine HardCopy of the current screen within about 1-2 Minutes (depending on the printer's speed).

DRAFU 7/16

Note: The HardCopy is just a "copy" of the Screen.

To save the life of your printer (or at least make it a little bit longer), please set the Background-Color to "white" before selecting "HardCopy".

Protection of the Display:

The last-drawn Function are conserved as long, as you select a Menu which causes the old Display to become "overwritten". When drawing new Functions via "Add-Draw", the Screen will be conserved.

Grid-Lines :

Don't you really like the "Grid-Lines", which are drawn by DRAFU when displaying functions on the screen ?

If you do not like those "support-lines", because you only need the graphical "look" of a function, you may turn this "Grid-Lines" simply off.

Look into the Menu "Display".

X-Marks / Y-Marks :

The Number of Marks at the X-Achsis or (also) the Y-Axis are changeable. Select the "X-Marken" or "Y-Marken".

A requester pops up, in which you see the old values, which can be modified for you own purposes.

Please remember, that too many or too less marks would perhaps destroy the display (a GURU may not appear, but one never know ... do one ?)

Advantages in speed (the second) :

If you are interested in speeding up the calculation and drawing of the functions, just put the screen of DRAFU into the background for a while.

You also may reduce the Color-Depth (less DMA-Accesses).

Behaviour when changing Colors :

Changed colors are only displayed after the next "write-access" to the Screen, e.g. when drawing a new function (also "Draw Again"). Only when changing the Background-Color the screen will be immediately cleared.

This is because DRAFU does not change color-values in registers, but DRAFU-internal values.

So the menus keep readable and the 3-D-Effect stays there (first four Color-Registers).

DRAFU 8 / 16

Loading and Saving the Preferences in "DRAFU.config":

A "DRAFU.config"-File, which is to be loaded, either at startup-time (automatically) or later by the user, has to be present in the directories "S:" or "ENV:" or in the current directory (in this order). Only there it can be found by DRAFU. Saving always is done to "S:DRAFU.config", to prevent unnecessary confusion.

The preferences done in the "DRAFU.config"-File, may be changed later by editing the file with a Text-Editor.

See point 1.5 (below) for more and detailed information.

Screen destroyed ?

If a Screen has been destroyed without an action of DRAFU, then the Sub-Menu "Draw Again" will restore the old Screen-Image by drawing it all again.

Shorter, faster, better ?

Like many other programs do, DRAFU allows you to make great use of so-called "ShortCuts", which can be used instead of mouse-based menu-selection.

Inside many menu-items you see the Amiga-Sign, followed by a singe char. Pressing the Amiga-Key and this Char-Key results in an immediately selection of the corresponding menu.

(Also see 1.4, "Function-Keys" !)

1.4 Function-Keys :

DRAFU the ESCAPE- and HELP-Key as follows :

ESC : "Leave program"
HELP : "Program Info"

1.5 Internal Commands :

DRAFU contains a set of "internal commands", which either are used in the "DRAFU.config"-Files, or in the Tooltypes of DRAFU, also in the Tooltypes of Memo-Files (Files with extension ".dfu"). Also all of these commands are available via ARexx, when DRAFU already has been started.

ARexx has a higher priority than the Tooltypes, which just have a higher

DRAFU 9 / 16

Priority than the entries of the "DRAFU.config"-File.
The "DRAFU.config"-File so mostly contains Default-Entries.

Below you find a listing of all those commands. The flag-combinations behind them show you, by which way ("C"=Config-File, "T"=Tooltypes, "A"=ARexx) you can reach the specific command.

Command-Listing :

```
"LOAD=<FileName>"
                            ; Load FMemo-List [ C T A ]
                                   ; Save FMemo-List [
; Make a HardCopy [
; Screenshot (IFF-ILBM) [
; Screenshot (IFF-ACBM) [
"SAVE=<FileName>"
                                                                            [ A ]
"HARDCOPY=<0..6>"
                                                                                    A ]
"SAVE_ILBM=<FileName>"
"SAVE_ACBM=<FileName>"
                                                                                 A ]
A ]
                                       ; Set new X-Mark Number
"X_MARKS=<Number>"
                                                                            [ C T A ]
"Y_MARKS=<Number>"
                                       ; Set new Y-Mark Number
                                                                           [ C T A ]
"OUIT"
                                        ; Quit DRAFU
                                                                                    A ]
                                                                            [
"GITTER=<ON/OFF>"
                                                                             [ C T A ]
                                        ; Gitter-Status
"AUTOSTEP=<HAND/PRECISE/FAST>" ; Stepsize-Status
                                                                            [CTA]
"SCALA=<DECIMAL/SCIENTIFIC/
         EFFICIENCY/LOG10>" ; Scaling-Status ; Y-Autorange-Status
                                                                            [ C T A ]
"Y_AUTORANGE=<ON/OFF>"
                                                                           [CTA]
"Y_AUTORANGE=<ON/OFF>" ; r-Autorange-status [ C I A ]
"BACK_COLOR=<ColorNumber>" ; Background-Color [ C T A ]
"AXIS_COLOR=<ColorNumber>" ; Axis-Color [ C T A ]
"DRAW_COLOR=<ColorNumber>" ; Default-Draw-Color [ C T A ]
"MODE=<Name Width Height D.>" ; Display-Mode (see below) [ C T A ]
                               ; Double-Axis-Status [ C T A ]
; Requester after Zoom [ C T A ]
"DOUBLEAXIS=<ON/OFF>"
"ZOOMREQUEST=<ON/OFF>"
                                      ; Requester after Zoom
                                                                           [ C T A ]
```

THE QUOTATION MARKS ONLY HAVE TO BE USED WITH THE AREXX-COMMANDS ! (AND WITH THE "MODE"-COMMAND)

1.6 The use from Workbech :

1.6.1 : ".dfu"-Files on the Workbench

Each DRAFU-Memo-File (with the ".dfu"-extension) automatically gets a Workbench-Icon.

When clicking on such an Icon on the Workbench, automatically loading of DRAFU is the result.

You'll only have specify a Screen-Mode, then the loaded functions of the Memo-List will be displayed.

1.6.2 : Autoloading on the Workbench

Another possibility consists of an additional ToolType for DRAFU itself, which would look as follows :

```
LOAD=<FileName[.dfu]>

(The extension ".dfu" need not be written here.)
```

DRAFU 10 / 16

When starting DRAFU, this File then will always be loaded automatically. You still only have to specify a Screen-Mode.

1.6.3 : More Tooltypes

Tooltype Possible Parameters Meaning

MODE= <Name Width Height Depth> (see Point 1.7)

1.7 CLI-/Shell-Start :

Use the following Commandline-Syntax for starts of DRAFU from the CLI/Shell :

DRAFU [-Mode=<Mode>] [<FileName[.dfu]>]

When starting from CLI you have the possibility to specify a single DRAFU-Memo-File (this needs to have extension ".dfu", which nevertheless need not be specified).

After Starting DRAFU this way, this file is automatically loaded. You only need to display a suitable Screen-Mode and then directly the loaded Memo-List will be displayed.

But you also may specify this Screen-Mode at command-line level. Please note, that first the Mode (optional) and then the File-Name (optional) has to be specified.

For possible Modes under OS V2.04 / V2.1 / V3.00+ please run your Screen-Mode Preferences.

For example:

- "PAL:LowRes 320 256 <Depth: 2..8>"
- "PAL:LowRes Interlace 320 512 <Depth: 2..8>"
- "PAL:HighRes 640 256 <Depth: 2..8>"
- "PAL:HighRes Interlace 640 512 <Depth: 2..8>"

Examples :

1. DRAFU "-Mode=PAL:HighRes 640 256 2"

Starts DRAFU in HIRES-Mode with 4 Colors.

2. DRAFU MemoPad.dfu

Starts DRAFU and loads the File MemoPad.dfu. The Screen-ModeRequester pops up then.

3. DRAFU "-Mode=PAL:HighRes 640 256 2 " MemoPad.dfu

Starts DRAFU in HIRES-Mode with 4 Colors.

DRAFU 11 / 16

```
and loads the File MemoPad.dfu.
           The Screen-ModeRequester does NOT pop up then.
  1.8 Using the ARexx-Interface of DRAFU:
  At first start DRAFU with a Screen-Mode and - maybe - a FileName
  (see 1.4, CLI-/Shell-Start).
  This is also possible inside the ARexx-Script.
  After that you may send commands to DRAFU's ARexx-Port "DRAFU.rx".
  All available commands are described under 1.5 (internal commands).
  Syntax is as follows :
   address 'DRAFU.rx' "Command with quotation marks"
  The ARexx-Script has to be written in the following format (generally) :
   Run "DRAFU -Mode=PAL:HighRes 640 256 4"
   wait 2
   address 'DRAFU.rx' "LOAD=MemoPad.dfu"
  Please look into the special ARexx-DemoScript with the name
  "DRAFU_ARexxDemo.rx" !
______
= EXAMPLES :
______
   At the end there's a little nice example :
      1. Select "f(x)=???" (second Menu)
      2. Enter "x^2" as Function
      3. Enter "0.5"
                      as "Step-Size"
      4. Enter "-20"
                       as "lower X-Border"
      5. Enter "20"
                       as "higher X-Border"
      6. Enter "-20"
                       as "lower Y-Border"
      7. Enter "20"
                        as "higher Y-Border"
   Then you'll see a quite nice standard-function (simple, eh?).
1.6 history
 DRAFU plus
 V2.10 (18.8.97):
```

- completely recompiled with SAS/C V6.58

- small changes

- screen save routine now requires superview.library V17+

DRAFU 12 / 16

```
- eMail/WWW addresses changed/added
V2.00 (3.1.97):
_____
 - completely recompiled with SAS/C V6.57
 - applied some changes to screen save routine
V1.07 (28.9.96):
 - misc
V1.06 (26.9.96):
 - V37 mode requester replacement still was separate and
  GadToolsBox-based. Completely rewritten and assimilated.
 - fixed bug in V37 moderequester error handling
 - fixed some problems in locale code generation
 - now also searches for keyfile in PROGDIR: (not recommended)
 - fixed some bugs in window sizing, resizing and according IDCMP
 - upgraded some remaining V33 Dos code to V37 (NameFromLock)
 - rewrote Zoom and Fadenkreuz functions (V37-alike)
 - and more
V1.05 (11.8.96):
 - did not run under OS V37, since locale.library V38+ was
   explicitely required (although V37 workaround-code was present :-(
 - menu checkmark verification routine still way buggy and caused
  MASSES of Enforcer hits. Fixed.
 - removed remaining Alloc/FreeMem() pairs by Alloc/FreeVec()
 - fixed Mungwall/EHit in function list delocation routine
   (occured when loading new list or quitting)
 - fixed enforcer hit on exit (screen NULL pointer).
  Did only occur in registered version.
 - fixed enforcer hits (MASSES of) in alphabetical sort routine
   for SVObject list generation (only did occur when saving window
   contents as graphics via superview.library)
 - fixed some other possible hits
V1.04 (27.7.96):
______
 - function enlistment was missing
   (-> G Statt, gstatt@gpu.srv.ualberta.ca)
 - added localized italian catalogs
   done by Luca Giolo (grifon@vega.unive.de).
   Thanks, Luca !
 - also added an "help/italiano" directory, which e.g.
   includes a modified version of Alessandro Bassos
   italian "RegisterForm" translation for SuperView
V1.03 (22.4.96):
 - english registration form did contain many german texts |-)
 - misc changes
V1.02 (2.2.96):
______
```

DRAFU 13 / 16

```
- fixed some keyfile stuff
 - registered user's name now in screen title bar
- prevented deletion of screen/window title bars
  under certain circumstances
V1.01 (30.12.95):
 - saving was not possible due to bug in V1.00.
  Fixed now, but disabled again as an "evalution restriction"
  (files may be created by hand, but for saving you need a keyfile)
- installer script did create an unnecessary entry in user-startup
 - "grid-lines" menu was not mutual exclusive
 - fixed small spelling bug in german gui catalog
- menus now are "check"ed correctly
- compiler messed up some menu command keys within "settings"
V1.00 (28.12.95):
_____
 - the first, completely-rewritten non-DEMO Shareware version
  since a long time
- GUI and program code have been completely rewritten by using the
  "Designer". OS V37 is now needed and nearly everything has changed
   (beginning with the GuideFile, over localization und finally upto
  AGA and full superview-library support).
- SHAREWARE
V0.83 (22.10.94):
______
 - internal version
V0.82 (23.2.93):
______
 - the second DEMO version of DRAFU plus
V0.80:
 - the first DEMO version of DRAFU plus
DRAFU (without the "plus")
______
V2.02c:
 - versionen upto V2.02c had been OS1.2/1.3 versions with a primitive
  function parser and and simple GUI (Shareware)
```

1.7 correspondence

DRAFU WWW Site http://www.amigaworld.com/support/drafu/

```
You may reach me the following way.

| Send bug-reports, money or whatever to:
```

DRAFU 14/16

* SuperView Development & Registration * * DRAFU Development & Registration * * Image Engineer Registration Site Europe * PerSuaSiVe SoftWorX Andreas R. Kleinert Sandstrasse 1 D-57072 Siegen Germany, Europe Any snail mail to the old address will still be routed. | Phone: +49-271-22869 also FAX + AM +49-271-22838 Weekdays after 17.00h. When calling via phone you may leave a message, if I'm not available - but don't expect me calling back to USA, Australia, ... since german phone rates are HIGHLY expensive.

EMail:

Please only send binaries after you have asked me and I did confirm your request - my postbox is not unlimited in size.

- * Do not send binaries via Fido or Fido-Gates! *
 - Fido Andreas Kleinert 2:2457/350.18
 - Usenet

ARK@superview.ftn.neckar-alb.de (Fido-Gate)
Andreas_Kleinert@t-online.de (T-Online)
ARK@News.wwbnet.de (Z-Netz)
ARK@amigaworld.com (AmigaWorld)

- If nothing else works, try one of these public Fido-Usenet gateways:

In Germany:

Andreas_Kleinert@p18.f350.n2457.z2.fido.sub.org

From USA or elsewhere:
 Andreas_Kleinert@p18.f350.n2457.z2.fidonet.org

When reporting any bugs, please don't forget to include a detailed description of the bug and tell me, if it is reproduceable or not. Please also mention the version number of DRAFU you used and describe your system configuration (Amiga model 500/.../4000T-060, Kickstart/OS, RAM, HardDisk, special configurations).

If you want to get a newer - and maybe debugged - version of DRAFU

DRAFU 15 / 16

do not forget to register as an user of DRAFU with the included registration form.

Nevertheless unregistered users are as welcome to report bugs as users who decide(d) to register.

The function parser (FWB routinen) have been written by Dipl.Ing. Ulrich Degens, who granted permission to use these with DRAFU. He is no longer actually directly involved with the program, but concerning further questions about FWB you may contact him under the following address:

Dipl.Inform. Ulrich Degens Hamburger Strasse 43 D-44135 Dortmund Germany

1.8 distribution

Copyright

The program DRAFU in this version and its documentation files are (C) opyright 1990-97 by Andreas R. Kleinert. All rights reserved.

The FWB routinen are (C)opyright 1991-97 by Dipl.Ing. Ulrich Degens. All rights reserved.

The right of using this program is granted to you by paying the SHAREWARE-fee of 30,- (40,-) DM to the author. This does concern the current version and possible updates, which may as well be Shareware.

Together with the registration you also receive your personal KEYFILE.

Disclaimer

The author takes no responsibility for any results of the use of this program.

This software is provided "AS IS" and there is no warranty of any kind, so that you use this software at your own risk.

Rights

Registered users which paid the ${\tt SHAREWARE-fee}$ get the rights described on the registration form.

Distribution

The REGISTERED version of DRAFU MUST NOT be redistributed. The Distribution of Keyfiles is FORBIDDEN.

The following only applies to the unregistered evaluation (EL)

DRAFU 16 / 16

version of DRAFU:

The program DRAFU in this version is freely distributable (SHAREWARE). You may copy it, if the copyright notice is left intact and all of its parts are included in the distribution.

This program must not be included in commercial packages or commercial program collections without my written permission.

This program must not be sold in any way, but it is allowed to take a nominal fee including the costs for copying.

This program may be put on public domain disks or included in public domain disk libraries.

Special permission hereby goes to Fred Fish's AmigaLib-Disks and the german series (in alphabetical order):

AmigaSzene, BerndsPD, FRANZ, GPD, SaarAG, TAIFUN and TIME.

This program may also be distributed via electronic mail and may be put into mailboxes as long as the redistribution conditions are respected in all points.

By using or distributing this program you automatically agree to all of the above conditions and terms.

1.9 copyrights

Copyrights

Some of the mentioned names or products above may be copyrighted by companies or trademarks of companies.

The Installer script icon is (C) by Roman Patzner (taken from the SuperView distribution, originally from "RomIcons").