

World-Clock

COLLABORATORS

	<i>TITLE :</i> World-Clock		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		August 4, 2022	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	World-Clock	1
1.1	WoRLD-CLoCK V1.18 - /X uTiL WRiTTeN BY SieGeL/tRSi	1
1.2	INTRODUCTION	1
1.3	INSTALLATION OF WORLD-CLOCK V1.18	2
1.4	ALL TOOLTYPES USED BY WORLD-CLOCK V1.18	2
1.5	KNOWN ARGUMENTS GIVEN AT AMIEX-PROMPT	4
1.6	SOME EXAMPLES FOR THE DIGIT-STYLES	5
1.7THE AMAZING GREETINGS.....	6
1.8	TRSI (/X-iNNOVATiON)	6
1.9	HOW TO CONTACT US	7
1.10	HOW TO CONTACT US	7

Chapter 1

World-Clock

1.1 WoRLD-CLoCK V1.18 - /X uTiL WRITTeN BY SieGeL/tRSi

```

_____ ↔
| _____ |
| \ _____ / ( _____ : / _____ / _____ / _____ / _____ / |
| \ _____ / : _____ / \ _____ / _____ / _____ / |
| \ _____ / : _____ / _____ / Mo! / _____ / _____ / |
| \ \ / _____ / _____ / _____ / 1 _____ |
| \ / SIEGEL/TRSI (/X·INNOVATION) PRESENTS |
| ----- |
|          INTRODUCTION |
|          | |
| INSTALLATION |
|          | |
| TOOL-TYPES |
|          | |
|          ..W·O·R·L·D·C·L·O·C·K.. |
| ARGs IN /X |
|          | |
| DIGIT-EXAMPLES |
|          | |
|          V1.18 pUBLIC |
| GREETINGS! |
| \ |
| \ \ \ | gRAPHICAL dESIGN bY
| ----- |
| AMBLIN/dEZiGN / COUNT ZERO/SCL / aXe/MST / -rEDSKIN/aRT / 2fAST/aRTcORE!

```

1.2 INTRODUCTION

iNTRODUCTION

Aehm...in the last public Version (V1.16) I had said that *NO* update of this clock will be ever released in the Future...but then 2fAST from aRTcORE! had painted a nice charset, so I decided to write another update..:)

During the update, I made again some changings in the code, now it's possible to define the Date & Location Line for yourself. Detailed Informations for

this could be found in the
 ToolTypes
 - Chapter.

To get a complete overview what changed take a look to the History-File
 included in this archive...let's go on with
 Installation
 ...

1.3 INSTALLATION OF WORLD-CLOCK V1.18

rEQUIREMENTS & iNSTALLATION

Of course you need any Amigamodel (500-4000T) with Kickstart V37++ and a full
 installed and working Amiex (Should work under /X V2.xx, too).

Put WORLD-cLOCK V1.18 and the icon wherever you want, but I recommend to
 create an Directory for WORLD-cLOCK, coz WORLD-cLOCK is now able to save the
 user-preferences, and they will be saved in the dir WORLD-cLOCK is started
 from.

NOTE: In difference to previous versions, WORLD-cLOCK needs *NO* icon anymore
 to run correctly. So if you don't copy the icon to the same drawer the
 clock is stored, WORLD-cLOCK only shows the local time. The times of
 the other cities couldn't be displayed, coz you have to define the GMT-
 Time-Offset in the Icon to let WORLD-cLOCK calculates the other times !

Copy the icon 'T.info' to your BBSCMD/ drawer and change the Location to the
 path where WORLD-cLOCK V1.18 could be found. That's all. To configure the
 Clock to your needs take a look to the
 Tooltypes
 .

NOTE: Starting from V1.16, every user is able to configure the clock to his
 own needs, and therefore it's not necessary that you configure the
 clock in the icon. If you configure it in the Tooltypes, this
 configuration is only the default one which will be overwritten by the
 user's config.

1.4 ALL TOOLTYPES USED BY WORLD-CLOCK V1.18

tOOLTYPES

LOCATION=<string> = Here you could enter the Location of your city,
 i.e. Berlin-Germany. If you don't want to enter
 a Location, put this Tooltype in Branches. The
 Clock uses then as location the name of your bbs.

LOCATION_LINE=<string> = Here you could define your own default-line for
 the location from where the time is shown.
 Default is :
 "tIME sHOWING FROM %L" <-- The %L will be replaced

by your Location !!!

This will be used if you don't define this Tool-type. If you want to specify your own, make sure that you don't write too much chars, coz the %L will always be replaced by your Location ! Of course you don't have to use the %L command, in this case only the string you have defined will be printed.

DATE_LINE=<STRING>

= This command allows you to define your own Date-line...for this option currently exists two commands:

%T --> Day (i.e. Wednesday)

%D --> The actual date (i.e. 09-FEB-95)

The Defaultsetting for this option is :

"actual systemdate is %D (%T)"

NOTE FOR WB 2.1++ USERS:

Both commands will be translated to the Language, you have defined in your SYS:Prefs/Locale Program. So if you have German as default language, both commands will be translated in :

%T = Mittwoch and %D = 09.02.95

GMT=<GMT-Time>

= Here you must define your GMT-Time (GMT=Greenwich-MeanTime). For Germany, it's +1. If U don't define this Tooltype, the WoRLD-CLoCK wouldn't be shown, you only see the time from your board.

LINE_ART=<char>

= If you want to separate the Clock from the cities, you could enter here *one* char (i.e. -, +, =) and this char will be used to create two lines between the clock and the cities. If you don't want to separate it, put this Tooltype in branches or don't define a char for it.

CHARSET=<number>

= I've included five different styles for the clock. Here you could choose which one will be used to show the time. Only 0,1,2,3 and 4 are allowed as valid numbers. The numbers are defined as follow:

0 = dIGITS fROM Amblin (Default!)

1 = dIGITS fROM Axe

2 = dIGITS fROM Count Zero

3 = dIGITS fROM -redSkin

4 = dIGITS fROM 2fAST/aRTcORE!

To check out the digits, take a look to

DIGITS

.

All following ToolTypes are the defines for the colors. Valid colornumbers are 30-37, which represents the ANSI-Colors in /X. I recommend not to use 30, as

this color is black and you won't see very much if you enter it...:)

MAIN_COLOR=<color> = The color for the Title and the Lines between the clock and the cities. Default is 33 (yellow).

CITY_COLOR=<color> = The color for "TIME SHOWING FROM.." and the cities. Default is 36 (light blue).

DIGITS_COLOR=<color> = The color for the digits and the citytimes. Default is 35 (lila).

DATELINE_COLOR=<color> = The Color for the Dateline (MM-DD-YY (DAY)). Default is 34 (dark blue).

1.5 KNOWN ARGUMENTS GIVEN AT AMIEX-PROMPT

aRGUMENTS

You could start the clock in three different ways...

1) Normal Start: T

This is the easiest way to start the clock...the actual time(s) will be shown and the clock quits.

2) Configuration: T E

If you start the clock in this mode, you get an options screen which allows all users to configure their 'own' clock-style. In Configuration-Mode the following options are accessible:

- 1,2,3,4 - Changes the Colors of the clock
- 5 - Allows you to change the separator char
- 6 - Select the Digitstyle, available are five different ones. Take a look to
DIGITS
for some examples.
- 7 - Select one of five different Date-Formats.
- S - Save current settings as default ones and display the clock in the current settings.
- P - 'Preview' of current settings..use this if you don't know how the current settings looks like...:)
- A - Use current Settings and start WORLD-cLOCK in Animation-Mode.
- Q - No saving and reset Settings to default.

3) Animation: T A

In this mode WORLD-cLOCK starts with displaying the time(s), but in difference to the normal mode the Local-System-Time will be updated every second and the World-Times will be updated every minute. To stop the anim


```

::: `:~::~: ~::~:'      ::: ~::~:' `:~::~'   :::: `:~::~'   ~::~' `:~::~'

```

1.7THE AMAZING GREETINGS.....

fAST gREETINGS fLY to :

```

aMBLiN/DeZiGN   - THX for the fast work. Personally my favourite digits...:)
aXe/MYSTiC      - CeWL digits Dude. Hope to see yar one time again..
Count Zero/SCL  - Great paintings dude..should i write sTYLEz ? :)
-redSkin/aRT     - Very cewl digits, hope to get a BBStitle from U soon..:)
2fAST/aRTcORE!  - For the many pictures you've painted 4 me..thx dude..
ByteAndi/tRSi   - Thx for givin me ur routine..:)
aRGoN/dTL       - THX 4 support and testing on my BBS..
dEATH aNGEL/SDC - You're my best Beta-Tester !!

```

and of course all tRSi-mEMBAS and all my users on my BBS

Musical Support: dEATH, sADE, pINK fLOYD, jEAN-mICHEL jARRE

Technical Supp.: A4000/040 (T-REX pOWER rOOLEZ :), Ced V3.5, SAS-C V6.51

1.8 TRSI (/X-iNNOVATiON)

```

      .-----
l____ /      \ \      _/____.:
 /      / / /  \ \____ /
 /_____/ -rS! \____ \____ / |'95
      /_____|      \ \ /_____|
      (/X-iNNOVATiON) Members are:

```

ByteAndi
SieGeL
Spy
Delta-X
Dr.Dre!

if you wanna join us so get in touch with

one of our members.

If you want to order a tool, give us Bugreports, hints and tips for this or other tools comin' from (tRSi/X-iNNOVATiON), try to contact us on any TRSI Board Worldwide, or try one of the following (but both 100% LEGAL ONLY!) :

pUNISHMENT iNC. - WHQ & bETA/rEGISTER SITE

pARALYSIS - GHQ & bETA/rEGISTER SITE

1.9 HOW TO CONTACT US

```

sYsPW: GURUsUXX

1

Mo!

100% LeGaL sTUFF oN aM;Ga^PC
RUNN;NG oN a4ooo/4o . V.FasT

TR;sTaR & ReD seCToR ;NC. (/X.;nNoVaT;oN) WoRLD HeaDQUaRTeR
aND eTH;C D;ST s;Te [> +49-(o)-3o-694-84-7o <] sYsoP: s;eGeL/TRs;

```

1.10 HOW TO CONTACT US

```

-[-[ THE BeST eQUIPPeD PuBLIC DoMAIN BoARd IN BeRLIN ]-
-[ WiTh 4 GReaT U.S.ROBOTICS V.FAST CLASS MoDeMS WiTh FLASH-RoMS ]-

-- -[-[ SYNDIC/\TE WHQ ]- --

[ViC!]\

\SYSTeM CHieFS: SPY/TRSi, ARTHuR DeNT, PHaNToM, Cat, JTC, big-rat/

1: +49(0) 30 721 6071 USR DuAL STaNDaRD V.34 28.8 /
2: +49(0) 30 721 6072 USR DuAL STaNDaRD V.34 28.8 /
3: +49(0) 30 721 6073 USR DuAL STaNDaRD V.34 28.8 /
4: +49(0) 30 722 6065 USR DuAL STaNDaRD V.34 28.8/

```

SUPPORTS ONLY PD-/SHAREWARE !