

Default

COLLABORATORS					
	TITLE : Default				
ACTION	NAME	DATE	SIGNATURE		
WRITTEN BY		August 7, 2022			

REVISION HISTORY					
DATE	DESCRIPTION	NAME			
	DATE	DATE DESCRIPTION			

Default

Contents

1	Defa	ult	1
	1.1	Table of contents	1
	1.2	Introduction to SongPlayer	1
	1.3	Supported audio formats	2
	1.4	adp4	2
	1.5	Requirements	3
	1.6	Installation of SongPlayer	3
	1.7	Use	3
	1.8	Main window	4
	1.9	Scopes window	5
	1.10	Karaoke window	5
	1.11	Karaoke editor window	5
	1.12	Options window	6
	1.13	Main settings	6
	1.14	Audio settings	7
	1.15	Karaoke settings	8
	1.16	Scopes settings	8
	1.17	MPEG Audio settings	9
	1.18	The menus	10
	1.19	Audio database	11
	1.20	CLI use	11
	1.21	AREXX commands	12
	1.22	Distribution of SongPlayer	13
	1.23	Utilities	13
	1.24	In the future	14
	1.25	History of SongPlayer	14
	1.26	Copyrights	14
	1.27	Thanks	15
	1.28	Disclaimer	15
	1.29	About me!	15
	1.30	My Friend	15

Default 1/16

Chapter 1

Default

1.1 Table of contents

SongPlayer 1.2 (23-Mar-1998) GIFTWARE

Introduction

Requirements

Installation

Use

CLI Options

AREXX

Utilities

History

In the future

Distribution

Disclaimer

Thanks

About the author

1.2 Introduction to SongPlayer

Default 2 / 16

SongPlayer is an audio file player of various formats

.

It can play 8 or 16 bits samples, mono or stereo ones, compressed or not.

It can be used as a shell utility thanks to its command parameters or with the Workbench with its graphical interface

MUI

.

The 16 bit sounds are played in 14 bit with the calibration principle of Christian \leftarrow BUCHNER or

in real 16 bit via a sound card with

AHI

Others features:

- Playlists
- Karaoke mode to see lyrics
- Pseudo-stereo effect for mono files
- Scopes (CPU, Vu-meters, Level-meters, Spectrum analyzer)
- Treble and bass adjustment
- Audio data base
- AREXX
- Read of compressed XPK files

1.3 Supported audio formats

IFF 8SVX PCM format and Fibonacci delta

AIFF 8 or 16 bits and ADP4 (ADPCM 4)

WAVE 8 or 16 bits

AU 8 or 16 bits and ULAW

MPEG Layer I, II and III. Norm 1, 2 and 2.5

1.4 adp4

I have implemented an ADPCM 4-bits (ADaptative Pulse Code \leftrightarrow Modulation) compression for the AIFF format. This format divide by 4 the size of the original 16-bit sample. The Compress/Expand processes are relatively simple and give very good results, \leftrightarrow that's why

Default 3/16

```
I decided to add this format.
```

See

Utilities

1.5 Requirements

An Amiga

A MC68EC020 or +

Amiga Workbench 3.0 or +

MUI V3.3 or + (not needed for a command line use)

Only one version of SongPlayer is provided for 68EC020 to 68060.

The mpega.library (aminet/util/lib) that correspond to your CPU.

1.6 Installation of SongPlayer

Click on the installation icon (you should have the 'Installer' utility)

That's all :)

Note: the SONGPLAYER assign is no longer needed in this version.

1.7 Use

The

main window

The

scopes

window

The

karaoke

window

The

karaoke editor

window

The

audio data base

window

Default 4 / 16

The

options window

The

menus

1.8 Main window

Song List:

The song list contains the current files selected for playing. This list can be filled or loaded with the eject button or with the menu "Project/Open". You can choose audio files or play lists. It is possible to add files to the current list with the menu "Project/Append". To remove an entry in the list, just select the line to remove and press DEL key or select the menu "Porject/Close". The list can be cleared with the menu "Project/Close all". The entries of the list can be moved to change the list order. This list can besaved with the record button or with the menu "Project/Save" or "Project/Save as". The total play time and the number of songs of the list are always displayed at the top of the list.

File Info:

The file info text area show informations about the selected file. It is composed of a maximum of 3 lines. When the play list is not active, one more line shows the duration and the title of the current file. These 3 lines are:

- Artist and album of file
- The file format
- The file comment

Time Slider:

This slider allows to seek into the current file.

Volume:

The volume button switches between Normal volume and Boost volume. Normal volume gives a slider from 0 to 64 and Boost volume from 0 to 256 (256 = 400% boost).

Balance:

The button reset the balance. The slider goes from -64 (full left) to +64 (full right).

Bass & Treble:

These features are available when the Bass & Treble adjust is enabled

Default 5 / 16

in the Audio Options. The buttons reset the bass or the treble (set to OdB). The sliders adjust the bass or treble from -20dB to +20dB.

Buttons:

Most of the buttons can be hide (see the option window) in order to simplify the control bar.

1.9 Scopes window

This window contains the various scopes selected in the Options/Scopes window. There are 4 types of scopes.

Vu-meter: A hand indicator of the sound level.

Level-meter: A bar graph indicator of the sound level.

Spectrum analyzer: An 8 frequencies band level indicator.

CPU usage: A gauge that indicates the CPU % used for audio decoding.

1.10 Karaoke window

This window display the song text in a karaoke way. One or two lines can be displayed. In case of a 2 lines display, the bottom line is the coming text.

1.11 Karaoke editor window

This window allows you to create or modify a karaoke file. Each line of the list correspond to one karaoke line. A line is composed of a time and a text line. The time format is MM:SS.T, i.e. minutes, seconds and 1/10th second. This time indicate when the text has to be displayed.

EDITING

Copy: Copy the current line to the clipboard

Cut: Copy the current line to the clipboard and remove it from the list

Paste: Insert the clipboard line after the current line

The string text just bellow the list allows you to modify the selected karaoke line (you must press ${\tt Enter}$ to validate the modification).

Pick Time: When you click on this button, the current playing time is copied to the editing line. This feature is very interesting:

You only have to enter all the song text without considering the time. Then, select the first line, play the song and click on this button each time the selected line must be displayed.

Default 6 / 16

FILES

Load: Load an existing Karaoke file (.kok). Import: Import a text file to the editor.

Save: Save the editor content to a Karaoke file (.kok).

Karaoke file format:

Each line of this text file has the following format:

MM:SS.T <Karaoke text>

 ${\tt MM:SS.T}$ is the time of display the karaoke text. The karaoke text is the rest of the line.

Lines must be ordered by time.

1.12 Options window

The options window allows you to customize SongPlayer. Theses options are saved in file "SongPlayer.cfg" of the SongPlayer program directory.

There are 5 separate settings:

The

Main settings

The

Audio settings

The

Karaoke settings

The

Scopes settings

The

MPEG Audio settings

1.13 Main settings

Fichier

Auto play:

Start to play automatically after tha load of a new play list.

Inter file delay:

Default 7 / 16

Wait time between two successives play.

Initial drawer:

It's the starting drawer of the audio file selector.

Initial file:

It's the file to load automatically at SongPlayer start.

File pattern:

It's the pattern of the file selector used at the load time.

PLaylist pattern:

It's tha accept pattern of the playlists. Only playlist filenames that correspond to this pattern will be examined.

Display

File list Show/hide the current play list

Artist & album Show/hide artist and album of current file

File format Show/hide the current file format
File comment Show/hide the curent file comment
Volume & Balance Show/hide the volume and balance
Time slider Show/hide the time progress bar
Sizable window Enable the window resizing

Buttons

Allows to choose the buttons to show in the control bar.

Intro duration: play duration of the intro mode

1.14 Audio settings

Use AHI: Use the AHI system for the audio output.

You have to select an AHI audio mode with the selector button a the end of the line.

Mixing Mode:

There are 3 mixing modes: Off, On and Auto.

Off: No mixing, the audio output frequency is equal to the audio file frequency.

On: The mixing is always performed. The audio output frequency is set to the value of the "Mixing frequency" Slider.

Auto: The mixing is only enabled when the audio file frequency is lower than the "Limit frequency" Slider.

Note: If the requested audio frequency is to high for your computer (depending of the video mode for built-in audio), the mixing is automatically enabled and set to the maximum frequency supported.

Bass & Treble Adjust:

Default 8 / 16

This feature allows to adjust the bass and the treble in the Main Window. WARNING this function may use a lot of CPU time on slow machines.

Priority: It's the audio decoding process priority.

Buffer Size: This slider set the size of the audio buffer in memory. It correspond to the amount of pre-decoded audio.

1.15 Karaoke settings

Karaoke Window: Opens or closes the karaoke window.

Display:

The karaoke window can display 1 or 2 lines. When 2 lines mode is selected, the bottom line show the coming text.

Advance Time:

This value allows to display the karaoke lines a little time before it should appear normally. This value is subtracted to the time of the karaoke line to get the corrected time of display.

Default path:

You can specify here the location of your karaoke files. Normally, these files are in the same directory as the associated audio file. But, sometimes, it is not always possible to do so (like on a CD-ROM already burned). If the karaoke file can't be found, then it is search with this default path.

1.16 Scopes settings

Scopes window:

Opens or closes the scopes window.

Vu-Meters

The vu-meters are indicators with a hand. They show the current sound level.

None: No vu-meter

Normal: Use a standard MUI indicator

Custom: Customized indicator

The following colors can then be modified:

- Back
- Scale
- Needle

Default 9 / 16

Level-Meters

The level-meters are line indicators. They show the current sound level.

None: No level-meter

Normal: Use a standard MUI gauge Custom: Customized level-meter

The following colors can then be modified:

- Back

- Body

- Top

Spectrum-Meters

The spectrum meters are bars indicators. They show the current levels of 8 bands of frequency.

None: No spectrum-meter

Normal: Use standard MUI gauges Custom: Customized spectrum-meter

The following colors can then be modified:

- Back

- Body

- Top

Show CPU Usage:

When enabled, the current CPU usage used for audio file decoding is displayed in a scale gauge.

Priority:

It's the indicators display process priority.

Refresh delay:

It's the refresh rate of the indicators in video frames.

1.17 MPEG Audio settings

These options allows to setup the decoding quality of MPEG Audio files. Because this audio decoding is very CPU intensive, on slow CPU (<68040), you will need to decrease the quality and/or the decoding frequency. You can have 2 different settings for Mono files and Stereo files because stereo files need almost 2 time more CPU than mono files. There are 2 separates options for MPEG I & II and MPEG III because MPEG III needs more CPU power than I or II. So you can have better settings for MPEG I & II than MPEG III.

Quality:

Default 10 / 16

High: Perform the full decoding process

Medium: Perform almost 1/2 of the decoding process Low: Perform almost 1/4 of the decoding process

Max Freq:

If the audio file frequency if greater than this value, the MPEG decoder try to divide by 2, then by 4 the output audio frequency. When the frequency is divided the decoder needs less CPU. So if you have a slow CPU, set the Max Frequency to a low value.

Force to Mono:

In order to reduce the CPU usage when decoding stereo files, you can force the decoder to use only 1 voice (left), so saving almost 50% of CPU.

1.18 The menus

PROJECT

Open... Load audio files or playlists
Append... Add audio files to the current list
Close Remove the current file of the list

Close all Clear the list

Save the current playlist

Save as... Save the current playlist with a new name

About... Infos about the author and greetings

About MUI... Infos about MUI

Quit SongPlayer

DISPLAY

File list Show/hide the current play list

Artist & album Show/hide artist and album of current file

File format

File comment

Show/hide the current file format

Show/hide the curent file comment

Volume & Balance

Time slider

Show/hide the volume and balance

Show/hide the time progress bar

Sizable window

Enable the window resizing

WINDOWS

Scopes Open/close the scopes window Karaoke Open/close the karaoke window

Karaoke editor Open/close the karaoke editor window

Audio database Open/close the audio database

SETTINGS

Options... Open the settings window of SongPlayer

MUI... Open the settings window of MUI

Default 11 / 16

1.19 Audio database

The audio database allows you to class all your audio files. It is build in an hierachical manner, 4 levels:

Genre
Artist
Album
Title

For each file you can associate a title, an album, an artist, a genre, its duration and a comment.

At the input of this informations, SongPlayer use the informations in the file to fill by advance several fields. So, for an MPEG file, if this one had TAG ID's, they will be used to fill all the fields.

The window of this database allows you to navigate through the hierarchy and to use drag & drop to the current play list. Four buttons are located at the bottom of the window:

New: Create a new element in the database Edit: Edit an element in the database Delete: Remove an element from the database

Save: Save the database

The database is located in the file 'SongPlayer.aub'

1.20 CLI use

Bass: -20 to +20 dB

Default 12 / 16

Treble: -20 to +20 dB

Filter: Enable audio filter (only Amiga build-in audio hardware)

GUI: Open the Graphical User Interface

ICONIFIED: Starts into icon mode

1.21 AREXX commands

The Arexx address is SONGPLAYER.x, x is the number of the SongPlayer active copy. If SongPlayer is launched only one time, the adress is also SONGPLAYER.1.

The Arexx commands available are:

ICONIFIY STATE/F Iconify or not the application

OPEN FILES/M Load files into the playlist

ADD FILES/M Add files to the playlist

CLOSE Remove the current file from the playlist

CLEAR Clear the playlist

PLAY Start the audio playing

PAUSE STATE/F Set the pause state

STOP Stop the audio playing

NEXT Select the next file in the playlist

PREV Select the previous file in the playlist

SELECT INDEX/N Select the given file number in the playlist

QUIT Quit SongPlayer

RANDOM STATE/F Enable or disable the random mode

INTRO STATE/F Enable or disable the intro mode

EXPAND STATE/F Enable or disable the pseudo-stereo mode

FILTER STATE/F Enable or disable the audio filter

VOLUME LEVEL/N Adjust the volume

BALANCE LEVEL/N Adjust the balance

BASS LEVEL/N Adjust the bass

TREBLE LEVEL/N Adjust the treble

Default 13 / 16

1.22 Distribution of SongPlayer

This program is copyright (c) 1994-1997 by Stéphane TAVENARD

It may be distributed freely under the condition that no profit is gained from its distribution, nor from any other program distributed in the same package.

Permission is granted to distribute this package by Bulletin Board systems or network sites, under the condition that no fee is charged on downloading it.

All files that are part of this package have to be distributed together and none of them may be changed in any way other than archiving or crunching. The only exception to this rule are the icons, including the tooltypes, which may be changed to accommodate them to the rest of the disk it is distributed on.

```
This program is distributed as $\operatorname{\textsc{GIFTWARE}}$
```

1.23 Utilities

AudioConvert

This utility allows you to convert a raw file (RAW) or AIFF in ${\sf AIFF}$

ADPCM4

. Other options allow to convert in mono a stereo file or to change the sampling frequency.

Usage: AudioConvert [<options>] <input file> <output file>

```
options:
```

```
-if <freq> input frequency (for raw file)
-it <tracks> input tracks (1 or 2, only for raw file)
```

-f <freq> output frequency

Default 14 / 16

1.24 In the future...

```
- Support of other audio formats
```

- Use of PPC ?
- More audio effects
- Real karaoke function (suppress of voices)

1.25 History of SongPlayer

V0.1	08-May-1994	Initial version, unique format: IFF 8SVX
V0.2	10-Nov-1994	Added IFF Fibonnacci delta
V0.3	29-Jul-1995	Added AIFF, AU, WAVE
V0.5	05-Nov-1995	Added MPEG format
V0.6	07-Jul-1996	use of MUI
V0.63	09-Feb-1997	First Aminet release
V1.0	28-Aug-1997	New design
		Playlists
		MPEG 1, 2 and 2.5 Layer III
		Scopes
		Karaoke
		AHI.
V1.2	23-Mar-1998	Less bugs
		Localization
		More options !
		Use mpega.library for the audio decoding
		AppIcon & AppWindow
		Audio database
		Random play
		Intro mode
		Arexx
		XPK Support

1.26 Copyrights

```
MUI is copyright (c) Stefan STUNTZ
EMail: stuntz@sasg.com

AHI is copyright (c) Martin BLOM
EMail: lcs@lysator.liu.se
```

Default 15 / 16

Web: http://www.lysator.liu.se/~lcs

1.27 Thanks

Amiga , the best computer ever made.

1.28 Disclaimer

This package is provided "as is" without warranty of any kind. The author assumes no responsibility or liability whatsoever for any damage or data loss caused by using this package.

1.29 About me!



Stéphane TAVENARD (ANGERS/France) Email: stephane.tavenard@wanadoo.fr IRC: Tatav

Send your gifts here :^)

Stéphane TAVENARD La Bézanière 49070 Saint Jean de Linières FRANCE

1.30 My Friend

Default 16 / 16

