

Adjust Page

Changes the brightness of the scanned image. If you find that a scanned image is too dark or too light, you can change the brightness to balance the final image.

Changes the balance of highlights and shadows in the image.

Determines the minimum amount of color that a dot must have to be defined as black. When a dot from an image is scanned, it is compared to the threshold value to determine whether it is black or white.

Increasing the value of the threshold causes Corel TWAIN to assign more dots to black. Reducing the threshold causes Corel TWAIN to assign more dots to white. The Threshold slider bar only affects black and white line art images. It has no effect on scans with any other color settings.

Determines the sharpness of edges in the image. Higher values produce sharper edges.

Returns all the slider bars to their original positions of 128.

Sets all the slider bars to their last stored positions. The positions of the slider bars are stored each time you exit from Corel TWAIN.

Making image adjustments



Adjusting images

The Adjust page lets you modify the scanning parameters for grayscale images. Changes to these settings affect both the scan and preview image.

The Brightness slider bar lets you lighten or darken a scanned image. The Contrast slider bar lets you adjust the balance of shadow and highlights in the image. The Edge Emphasis slider lets you adjust the sharpness of edges in the image.

The Threshold setting defines the minimum amount of color a scanned dot must have before Corel TWAIN considers it to be black. Increasing the value of the threshold causes Corel TWAIN to assign more dots to the color black. Reducing the threshold causes Corel TWAIN to assign more dots to the color white.

Default restores the sliders to their default values of 128, and Restore to resets all of the slider bars to their last stored positions. The positions of the slider bars are stored each time you exit from Corel TWAIN.




Adjusting edge emphasis

1. Choose the Adjust page.
2. Set the Edge Emphasis sliders to the desired value. Higher values produce sharper edges.

Tip

- To see the result of your changes, click Prescan.

`{button ,AL(` PRC Making image adjustments;',0,"Defaultoverview",,)} Related Topics`



Adjusting contrast, brightness and threshold

1. Choose the Adjust page.
2. Set the Contrast, Brightness and Threshold sliders to the desired values. The greater the number, the greater the effect. Contrast should be increased about one-tenth the amount you increase brightness.



Tip

- To see the result of your changes, click Prescan.

{button ,AL(`PRC Making image adjustments;`,0,"Defaultoverview",)} Related Topics

