

VistaScan ReadMe

System Requirements

- * System 7 or later
- * If you use PhotoShop 3.0 or later, set PhotoShop's preferred memory size to 12MB(68K)/24MB(PPC) or more using the file--Get Info command.
- * If you use VistaScan DA, set VistaScan DA's preferred memory size to 6MB or more using File--Get Info command.

Installation Procedures

Make sure PhotoShop is installed first, if you have not yet installed it, before installing VistaScan.

Follow the steps below to install VistaScan:

1. Double-click on the VistaScan Installer icon.
2. Follow the on-screen instructions to install VistaScan.
Please note that:
 - * If you choose Easy Install, the UMAXShare and UMAXChooser won't be installed.
 - * When a dialog box prompts you to select the plug-ins folder, select the Plug-ins folder in PhotoShop. The VistaScan plug-in driver should be stored in the folder you select in this dialog box.
3. After installation, restart your Macintosh. A new folder containing the VistaScan software is created. To know how to use VistaScan, refer to your VistaScan User's Guide for detailed information.

Note: If you find the VistaScan plug-in driver is located in the VistaScan 3.0 folder, you need to drag the VistaScan plug-in driver to PhotoShop's Plug-ins folder.