

BME.MDE

Copyright © 1995 Soft-Logik Publishing Corporation

COLLABORATORS

	<i>TITLE :</i> BME.MDE		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		August 23, 2022	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	BME.MDE	1
1.1	BME2 ALPHABETICAL MACRO INDEX	1
1.2	Picture Names	3
1.3	clone	3
1.4	close	3
1.5	colorpalette	4
1.6	convert	4
1.7	copy	5
1.8	crop	5
1.9	cut	5
1.10	effect	6
1.11	erase	6
1.12	eyedrop	6
1.13	fill	7
1.14	flip	7
1.15	getpicture	8
1.16	getportname	8
1.17	getscreendpi	8
1.18	getscreename	9
1.19	loadsettings	9
1.20	macropalette	10
1.21	moveselection	10
1.22	new	10
1.23	open	11
1.24	paint	11
1.25	paste	12
1.26	quit	12
1.27	redo	12
1.28	remap	13
1.29	resize	13

1.30 rotate	14
1.31 rx	14
1.32 save	14
1.33 savesettings	15
1.34 screentoback	15
1.35 screentofront	15
1.36 select	16
1.37 setbrushsize	16
1.38 setcolor	17
1.39 setmacropath	17
1.40 setmagnify	17
1.41 setpicturepath	18
1.42 setsmartmap	18
1.43 setundolevels	18
1.44 undo	19

Chapter 1

BME.MDE

1.1 BME2 ALPHABETICAL MACRO INDEX

- C -

clone

close

colorpalette

convert

copy

crop

cut

- E -

effect

erase

eyedrop

- F -

fill

flip

- G -

getpicture

getportname

getscreendpi

getscreename

- L -

loadsettings
- M -

moveselection
- N -

new
- O -

open
- P -

paint

paste
- Q -

quit
- R -

redo

remap

resize

rotate

rx
- S -

save

savesettings

screeentoback

screeentofront

select

setbrushsize

setcolor

setmacropath

setmagnify

setpicturepath

setsmartmap

setundolevels
- U -

undo

1.2 Picture Names

Picture Names

The NAME parameter is used in many BME macro commands to specify to which open picture window the command is directed. The picture name is the complete path of the picture as shown in the title bar of the picture.

For example, if you open a picture titled "Tiger.ILBM" from your "PageStream3:Graphics" directory, the picture name will be "PageStream3:Graphics/Tiger.ILBM". This name cannot be abbreviated, although the NAME parameter is usually optional and will default to the current picture window.

1.3 clone

CLONE

Purpose: Opens a new picture window containing just the selected area, without affecting the original picture.

Syntax: clone [NAME name/F]

Format: Parameter Values to enter
NAME is the picture name to modify. (Default=current)

Example: clone
clone name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.4 close

CLOSE

Purpose: Close a picture.

Syntax: close [NAME name/F] [FORCE | ALERT | QUIET]

Format: Parameter Values to enter
FORCE ignores the saved status of the picture.
ALERT opens an alert requester if the picture has been changed.
QUIET ignores the saved status of the picture but returns an error if the picture has been changed. (Default)
NAME is the picture name to close. (Default=current)

Example: close name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.5 colorpalette

COLORPALETTE

Purpose: Displays the color palette.

Syntax: colorpalette [SHOW | HIDE | TOGGLE] [AT pointx/I pointy/I]
[SAVE]

Format: Parameter Values to enter
 SHOW toggles on the palette.
 HIDE toggles off the palette.
 TOGGLE toggles the palette on and off.
 AT sets the palette position.
 SAVE saves the value to the BME.prefs file.

Note: The TOGGLE parameter may not be used in conjunction with the SAVE parameter.

Example: colorpalette toggle
 colorpalette show at 500 300

Command Format

1.6 convert

CONVERT

Purpose: Converts a picture to a different type.

Syntax: convert [TYPE type/S] [DEPTH depth/I] [NAME name/F]

Format: Parameter Values to enter
 TYPE is the picture type. (Default=current)
 DEPTH is the picture depth. (Default=current)
 NAME is the picture name to modify. (Default=current)

Notes: Valid options for the TYPE parameter are:
 <BW|GRAYSCALE|PALETTE|RGB|CMYK>

Example: convert type rgb depth 12
 convert type palette name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.7 copy

COPY

Purpose: Copies the selected area to the clipboard.

Syntax: copy [NAME name/F]

Format: Parameter Values to enter
NAME is the picture name to modify. (Default=current)

Example: copy
copy name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.8 crop

CROP

Purpose: Crops the picture to the selected area.

Syntax: crop [NAME name/F]

Format: Parameter Values to enter
NAME is the picture name to modify. (Default=current)

Example: crop
crop name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.9 cut

CUT

Purpose: Cuts the selected area to the clipboard.

Syntax: cut [NAME name/F]

Format: Parameter Values to enter
NAME is the picture name to modify. (Default=current)

Example: cut
cut name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.10 effect

EFFECT

Purpose: Performs the specified effect. If an area is selected and the command can be applicable to an area, it will be applied to the area. If an area is not selected and the command is not applicable to an entire picture, the command will do nothing.

Syntax: effect <EFFECT name/S> [NAME name/F]

Format: Parameter Values to enter
EFFECT is the name of the effect module.
NAME is the picture name to modify. (Default=current)

Notes: Some effect filters have additional options. Record the execution of an effect to see its options.

Example: effect effect 'Contrast'
effect effect 'Pixelize' name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.11 erase

ERASE

Purpose: Removes the selected area from the picture without copying it to the clipboard.

Syntax: erase [NAME name/F]

Format: Parameter Values to enter
NAME is the picture name to modify. (Default=current)

Example: erase
erase name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.12 eyedrop

EYEDROP

Purpose: Selects the color from a pixel in a picture.

Syntax: eyedrop <horz/I vert/I> [FORE | BACK] [NAME name/F]

Format: Parameter Values to enter
 horz is the horizontal coordinate of the pixel.
 vert is the vertical coordinate of the pixel.
 FORE picks up the foreground color.
 BACK picks up the background color.
 NAME is the picture name to modify. (Default=current)

Example: eyedrop 50 50 back
 eyedrop 100 78 name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.13 fill

FILL

Purpose: Fills the selected area.

Syntax: fill [FORE | BACK] [NAME name/F]

Format: Parameter Values to enter
 FORE fills with the foreground color. (Default)
 BACK fills with the background color.
 NAME is the picture name to modify. (Default=current)

Example: fill back
 fill name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.14 flip

FLIP

Purpose: Flips the selected area horizontally or vertically. If an area is not selected, the entire picture will be affected.

Syntax: flip [HORZ | VERT] [NAME name/F]

Format: Parameter Values to enter
 HORZ flips horizontally. (Default)

VERT flips vertically.
NAME is the picture name to modify. (Default=current)

Example: flip vert
 flip name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.15 getpicture

GETPICTURE

External macros only!

Purpose: Queries BME to find if a picture is open.

Syntax: getpicture <name/S>

Format: Parameter Values to enter
 name is the name of the picture to check.

Errors: Returns 10 to RC if the picture is not open.

Example: getpicture 'pagestream3:graphics/mygraphic.ilbm'
 if rc~=0 then say 'Picture is open.'
 else say 'Picture is not open!'

Command Format

1.16 getportname

GETPORTNAME

External macros only!

Purpose: Gets the name of BME's ARexx port.

Syntax: getportname (no parameters)

Result: The name is returned to RESULT.

Example: getportname /* will return the portname */
 name=result

Command Format

1.17 getscreendpi

GETSCREENDPI

External macros only!

Purpose: Gets the display resolution of the current screen.

Syntax: getscreendpi <dpistem/V>

Format: Parameter Values to enter
dpistem gets the display dpi.

Result: dpistem.x horizontal display dpi.
dpistem.y vertical display dpi.

Example: getscreendpi rez /* will return the screenname */
say rez.x
say rez.y

Command Format

1.18 getscreenname

GETSCREENNAME

External macros only!

Purpose: Gets the name of the screen on which BME is opened.

Syntax: getscreenname (no parameters)

Result: The name is returned to RESULT.

Example: getscreenname /* will return the screenname */
screen=result

Command Format

1.19 loadsettings

LOADSETTINGS

Purpose: This loads the program settings from a preferences file.

Syntax: loadsettings [DEFAULT | FILE filepath/F]

Format: Parameter Values to enter
DEFAULT loads the BME.prefs file.
FILE is the filename and path of the settings file to load.

Example: loadsettings file 'PageStream3:bme.specialprefs'

Command Format

1.20 macropalette

MACROPALETTE

Purpose: Displays the macro palette.

Syntax: macropalette [SHOW | HIDE | TOGGLE] [AT pointx/I pointy/I]
[SIZE width/I height/I] [SAVE]

Format:	Parameter	Values to enter
	SHOW	toggles on the palette.
	HIDE	toggles off the palette.
	TOGGLE	toggles the palette on and off.
	AT	sets the palette position.
	SIZE	sets the palette size in pixels. (Min=160x50)
	SAVE	saves the value to the BME.prefs file.

Note: The TOGGLE parameter may not be used in conjunction with the SAVE parameter.

Example: macropalette toggle
macropalette show at 500 300 size 180 172
macropalette hide

Command Format

1.21 moveselection

MOVESELECTION

Purpose: Moves a selected area.

Syntax: moveselection <horz/I vert/I> [COPY] [NAME name/F]

Format:	Parameter	Values to enter
	horz	is the horizontal movement amount.
	vert	is the vertical movement amount.
	COPY	will leave a copy of the selection at the current position.
	NAME	is the picture name to modify. (Default=current)

Example: moveselection 25 30
moveselection 130 45 copy name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.22 new

NEW

Purpose: Creates a new picture.

Syntax: new [TYPE type/S] [DEPTH depth/I] [SIZE width/I height/I]
[DPI horz/I vert/I] [NAME name/F]

Format: Parameter Values to enter
 TYPE is the picture type. (Default=Palette)
 DEPTH is the picture depth. (Default=RGB:6; others:8)
 SIZE is the size of the picture. (Default=320x200)
 DPI is the resolution of the picture. (Default=displaydpi)
 NAME is the picture name.

Notes: Valid options for the TYPE parameter are:
 <BW|GRAYSCALE|PALETTE|RGB|CMYK>

Example: new type rgb depth 9 size 640 400

Command Format

Picture Names

1.23 open

OPEN

Purpose: Opens a picture.

Syntax: open [FILE filepath/F]

Format: Parameter Values to enter
 FILE is the filepath and name of the picture to open.

Example: open file 'Graphics:Tiger.ILBM'

Command Format

Picture Names
 filepath

1.24 paint

PAINT

Purpose: Paints with the brush.

Syntax: paint <horz/I vert/I> [FORE | BACK] [NAME name/F]

Format: Parameter Values to enter
 horz is the horizontal coordinate of the position to paint.
 vert is the vertical coordinate of the position to paint.
 FORE paints with the foreground color. (Default)
 BACK paints with the background color.

NAME is the picture name to modify. (Default=current)

Example: paint 15 18
paint 137 43 back name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.25 paste

PASTE

Purpose: Pastes the contents of the clipboard into a picture as an area.

Syntax: paste [NAME name/F]

Format: Parameter Values to enter
NAME is the picture name to modify. (Default=current)

Example: paste
paste name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.26 quit

QUIT

Purpose: Quit BME.

Syntax: quit [FORCE | ALERT | QUIET]

Format: Parameter Values to enter
FORCE ignores the saved status of the pictures.
ALERT opens an alert requester if the picture has been changed.
QUIET ignores the saved status of the pictures but returns
an error if the pictures have been changed. (Default)

Example: quit force

Command Format

1.27 redo

REDO

Purpose: Redoes the last undone command or action.

Syntax: redo [NAME name/F]

Format: Parameter Values to enter
NAME is the picture name to modify. (Default=current)

Example: redo
redo name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.28 remap

REMAP

Purpose: Remaps the palette of a palette picture.

Syntax: remap [NAME name/F]

Format: Parameter Values to enter
NAME is the picture name to modify. (Default=current)

Example: remap
remap name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.29 resize

RESIZE

Purpose: Resizes the selected area. If an area is not selected, it will resize the entire picture.

Syntax: resize [SIZE width/I height/I] [DPI horz/I vert/I]
[IMAGE option/I] [NAME name/F]

Format: Parameter Values to enter
SIZE is the size of the picture. (Default=current)
DPI is the resolution of the picture. (Default=current)
IMAGE is the existing image option. (Default=SCALE)
NAME is the picture name to modify. (Default=current)

Notes: Valid options for the IMAGE parameter are:
<CENTER|SCALE|LOWERLEFT|LOWERRIGHT|UPPERLEFT|UPPERRIGHT>

Example: resize size 50 100 image upperleft
resize dpi 150 150 name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.30 rotate

ROTATE

Purpose: Rotates the selected area horizontally or vertically. If an area is not selected, the entire picture will be affected.

Syntax: rotate [90CW | 90CCW | 180] [NAME name/F]

Format:

Parameter	Values to enter
90CW	rotates 90\textdegree{} clockwise. (Default)
90CCW	rotates 90\textdegree{} counterclockwise.
180	rotates 180\textdegree{}.
NAME	is the picture name to modify. (Default=current)

Example: rotate 90ccw
rotate name 'Graphics:Tiger.IIBM'

Command Format

Picture Names

1.31 rx

RX

Purpose: This executes an external ARexx macro.

Syntax: rx [filepath/F]

Format:

Parameter	Values to enter
filepath	is the filename and path of the macro to execute.

Example: rx 'PageStream3:Macros/Test.REXX'

Command Format

1.32 save

SAVE

Purpose: Saves an open picture.

Syntax: save [DEFAULT | FILE filepath/F] [NAME name/F] [FILTER name/S]

Format: Parameter Values to enter
 DEFAULT saves the picture with the current filename. (Default)
 FILE saves the picture with the specified name.
 NAME is the picture name to save. (Default=current)
 FILTER is the import/export filter to use. (Default=current)

Notes: Valid filter parameters at the date of this writing are:
 IFFILBM, TIFF, GIF, MacPaint, BMP. The names of filters are normally
 the same as the filename, less the '.filter' extension. You can
 determine the filter name by typing 'version name.filter' in a
 shell, where name is the filter to examine.

Example: saveas file 'ram:temp' name 'Graphics:House.ILBM' filter BMP

Command Format

Picture Names
 filepath

1.33 savesettings

SAVESETTINGS

Purpose: This saves the current program settings.

Syntax: savesettings [DEFAULT | FILE filepath/F]

Format: Parameter Values to enter
 DEFAULT saves the settings to the BME.prefs file. (Default)
 FILE is the filename and path of the settings file to save.

Example: savesettings file 'PageStream3:BME.specialprefs'

Command Format

filepath

1.34 screentoback

SCREENTOBACK

Purpose: Sends the screen on which BME is open to the back of all screens.

Syntax: screentoback (no parameters)

Example: screentoback

Command Format

1.35 screentofront

SCREENTOFONT

Purpose: Brings the screen on which BME is open to the front of all screens.

Syntax: screentofront (no parameters)

Example: screentofront

Command Format

1.36 select

SELECT

Purpose: Selects an area in a picture.

Syntax: select <ALL | CLEAR | MARQUEE left/I top/I width/I height/I>
[NAME name/F]

Format: Parameter Values to enter
 ALL selects the entire picture as an area.
 CLEAR deselects the area if one is selected.
 MARQUEE selects an area with of specified coordinates.
 NAME is the picture name to modify. (Default=current)

Example: select marquee 50 50 250 325
 select clear name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.37 setbrushsize

SETBRUSHSIZE

Purpose: Sets the size of the brush.

Syntax: setbrushsize <width/I height/I> [NAME name/F]

Format: Parameter Values to enter
 width is the width of the brush. (Max=64)
 height is the height of the brush. (Max=64)
 NAME is the picture name to modify. (Default=current)

Example: setbrushsize 16 16
 setbrushsize 5 7 name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.38 setcolor

SETCOLOR

Purpose: Sets the brush color.

Syntax: setcolor [FORE color/I] [BACK color/I] [NAME name/F]

Format: Parameter Values to enter
FORE sets the foreground color.
BACK sets the background color.
NAME is the picture name to modify. (Default=current)

Example: setcolor fore 5
setcolor fore 3 back 255 name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.39 setmacropath

SETMACROPATH

Purpose: To set the default file path for executing and exporting external ARexx macros, and for loading and saving the BME.macros file.

Syntax: setmacropath <filepath/F>

Format: Parameter Values to enter
filepath is the path for the files.

Example: setmacropath 'Rexx:'

Command Format

1.40 setmagnify

SETMAGNIFY

Purpose: Changes the magnification of the picture.

Syntax: setmagnify <horz/I vert/I>
<SCALE custom/P | ZOOMIN | ZOOMOUT | ACTUAL> [NAME name/F]

Format: Parameter Values to enter
horz is the horizontal zoom center point. (Default=center)
vert is the vertical zoom center point. (Default=center)
SCALE is the magnification level to use.
ZOOMIN doubles the magnification.
ZOOMOUT halves the magnification.
ACTUAL sets the magnification to actual size (100%).

NAME is the picture name to modify. (Default=current)

Notes: Valid options for the SCALE parameter are:
<3.125 | 6.25 | 12.5 | 25 | 50 | 100 | 200 | 400 | 800 | 1600 | 3200>

Example: setmagnify scale 25
setmagnify zoomout name 'Graphics:Tiger.ILBM'

Command Format

Picture Names

1.41 setpicturepath

SETPICTUREPATH

Purpose: To set the default file path for opening and saving pictures.

Syntax: setpicturepath <filepath/F>

Format: Parameter Values to enter
filepath is the path for the files.

Example: setpicturepath 'Brilliance:Pictures'

Command Format

1.42 setsmartmap

SETSMARTMAP

Purpose: Sets whether colors are sorted in the most used order before allocating them.

Syntax: setsmartmap <ON | OFF> [SAVE]

Format: Parameter Values to enter
ON toggles on smart map.
OFF toggles off smart map.
SAVE saves the value to the BME.prefs file.

Example: setsmartmap on save

Command Format

1.43 setundolevels

SETUNDOLEVELS

Purpose: Changes the number of undo levels available.

Syntax: setundolevels <levels/I> [SAVE]

Format: Parameter Values to enter
levels is the number of undo levels to permit.
SAVE saves the value to the BME.prefs file.

Notes: The number of undo levels is limited only by memory. For unlimited levels of undo, set levels to -1. It is recommended that you restrict the number of levels of undo to conserve memory.

Example: setundolevels 16 save

Command Format

1.44 undo

UNDO

Purpose: Undoes the last command or action.

Syntax: undo [NAME name/F]

Format: Parameter Values to enter
NAME is the picture name to modify. (Default=current)

Example: undo
undo name 'Graphics:Tiger.ILBM'

Command Format

Picture Names
